



Modifying Cloud Volumes ONTAP systems

Cloud Manager

Ben Cammett
July 20, 2021

Table of Contents

- Modifying Cloud Volumes ONTAP systems 1
 - Changing the instance or machine type for Cloud Volumes ONTAP 1
 - Changing between hourly (pay-as-you-go) configurations 1
 - Moving to an alternate Cloud Volumes ONTAP configuration 2
 - Changing write speed to normal or high 2
 - Modifying the storage VM name 3
 - Changing the password for Cloud Volumes ONTAP 4
 - Changing route tables associated with HA pairs in multiple AWS AZs 4

Modifying Cloud Volumes ONTAP systems

You might need to change the configuration of Cloud Volumes ONTAP systems as your storage needs change. For example, you can change between pay-as-you-go configurations, change the instance or VM type, and more.

Changing the instance or machine type for Cloud Volumes ONTAP

You can choose from several instance or machine types when you launch Cloud Volumes ONTAP in AWS, Azure, or GCP. You can change the instance or machine type at any time if you determine that it is undersized or oversized for your needs.

About this task

- Automatic giveback must be enabled on a Cloud Volumes ONTAP HA pair (this is the default setting). If it isn't, then the operation will fail.

[ONTAP 9 Documentation: Commands for configuring automatic giveback](#)

- Changing the instance or machine type affects cloud provider service charges.
- The operation restarts Cloud Volumes ONTAP.

For single node systems, I/O is interrupted.

For HA pairs, the change is nondisruptive. HA pairs continue to serve data.



Cloud Manager gracefully changes one node at a time by initiating takeover and waiting for give back. NetApp's QA team tested both writing and reading files during this process and didn't see any issues on the client side. As connections changed, we did see retries on the I/O level, but the application layer overcame these short "re-wire" of NFS/CIFS connections.

Steps

1. From the working environment, click the menu icon, and then click **Change license or instance** for AWS, **Change license or VM** for Azure, or **Change license or machine** for GCP.
2. If you are using a pay-as-you-go configuration, you can optionally choose a different license.
3. Select an instance or machine type, select the check box to confirm that you understand the implications of the change, and then click **OK**.

Result

Cloud Volumes ONTAP reboots with the new configuration.

Changing between hourly (pay-as-you-go) configurations

After you launch an hourly, pay-as-you-go Cloud Volumes ONTAP system, you can change between the Explore, Standard, and Premium configurations at any time by modifying the license. Changing the license increases or decreases the raw capacity limit and enables you to choose from different instance or VM types.

About this task

Note the following about changing between pay-as-you-go licenses:

- The operation restarts Cloud Volumes ONTAP.

For single node systems, I/O is interrupted.

For HA pairs, the change is nondisruptive. HA pairs continue to serve data.

- Changing the instance or machine type affects cloud provider service charges.

Steps

1. From the working environment, click the menu icon, and then click **Change license or instance** for AWS, **Change license or VM** for Azure, or **Change license or machine** for GCP.
2. Select a license type and an instance type or machine type, select the check box to confirm that you understand the implications of the change, and then click **OK**.

Result

Cloud Volumes ONTAP reboots with the new license, instance type or machine type, or both.

Moving to an alternate Cloud Volumes ONTAP configuration

If you want to switch between a pay-by-the-hour (PAYGO) subscription, an annual contract (AWS only), or a BYOL subscription, then you need to create a new Cloud Volumes ONTAP working environment and then replicate data from the existing working environment to the new working environment. The same is true if you want to switch between a single Cloud Volumes ONTAP system and an HA pair.

Steps

1. Create a new Cloud Volumes ONTAP working environment.

[Launching Cloud Volumes ONTAP in AWS](#)

[Launching Cloud Volumes ONTAP in Azure](#)

[Launching Cloud Volumes ONTAP in GCP](#)

2. [Set up one-time data replication](#) between the systems for each volume that you must replicate.
3. Terminate the Cloud Volumes ONTAP system that you no longer need by [deleting the original working environment](#).

Changing write speed to normal or high

Cloud Manager enables you to choose a normal or high write speed for Cloud Volumes ONTAP. The default write speed is normal. You can change to high write speed if fast write performance is required for your workload.

High write speed is supported with all types of single node systems. It's also supported with HA pairs in AWS and Azure when using a specific instance or VM type ([click here to see the list of supported instances and VM types](#)). High write speed is not supported with HA pairs in GCP.

Before you change the write speed, you should [understand the differences between the normal and high settings](#).

About this task

- Ensure that operations such as volume or aggregate creation are not in progress.

- Be aware that this change restarts Cloud Volumes ONTAP.

Steps

1. From the working environment, click the menu icon, and then click **Advanced > Writing Speed**.
2. Select **Normal** or **High**.

If you choose High, then you'll need to read the "I understand..." statement and confirm by checking the box.

3. Click **Save**, review the confirmation message, and then click **Proceed**.


Modifying the storage VM name


Cloud Manager automatically names the single storage VM (SVM) that it creates for Cloud Volumes ONTAP. You can modify the name of the SVM if you have strict naming standards. For example, you might want the name to match how you name the SVMs for your ONTAP clusters.

But if you created any additional SVMs for Cloud Volumes ONTAP, then you can't rename the SVMs from Cloud Manager. You'll need to do so directly from Cloud Volumes ONTAP by using System Manager or the CLI.


Steps

1. From the working environment, click the menu icon, and then click **Information**.
2. Click the edit icon to the right of the storage VM name.



 Working Environment Information

ONTAP


Serial Number: 

System ID: system-id-capacitytest

Cluster Name: capacitytest

ONTAP Version: 9.7RC1

Date Created: Jul 6, 2020 07:42:02 am

Storage VM Name: svm_capacitytest 

3. In the Modify SVM Name dialog box, change the name, and then click **Save**.

Changing the password for Cloud Volumes ONTAP

Cloud Volumes ONTAP includes a cluster admin account. You can change the password for this account from Cloud Manager, if needed.



You should not change the password for the admin account through System Manager or the CLI. The password will not be reflected in Cloud Manager. As a result, Cloud Manager cannot monitor the instance properly.

Steps

1. From the working environment, click the menu icon, and then click **Advanced > Set password**.
2. Enter the new password twice and then click **Save**.

The new password must be different than one of the last six passwords that you used.

Changing route tables associated with HA pairs in multiple AWS AZs

You can modify the AWS route tables that include routes to the floating IP addresses for an HA pair. You might do this if new NFS or CIFS clients need to access an HA pair in AWS.

Steps

1. From the working environment, click the menu icon and then click **Information**.
2. Click **Route Tables**.
3. Modify the list of selected route tables and then click **Save**.

Result

Cloud Manager sends an AWS request to modify the route tables.

Copyright Information

Copyright © 2021 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system-without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP "AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at <http://www.netapp.com/TM> are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.