



# Provisioning NFS volumes from the Volume View

Cloud Manager 3.6

NetApp  
June 10, 2024

# Table of Contents

- Provisioning NFS volumes from the Volume View ..... 1
  - Changing to the Volume View ..... 1
  - Creating and mounting NFS volumes ..... 1
  - Managing NFS volumes ..... 4

# Provisioning NFS volumes from the Volume View

## Changing to the Volume View

Cloud Manager provides two management views: the Storage System View for managing storage systems across a hybrid cloud and the Volume View for creating volumes in AWS without having to manage storage systems. You can switch between these views, but those instances should be rare because a single view should meet your needs.

For more information about the Volume View, see [Simplified storage management using the Volume View](#).

### Steps

1. In the upper right of the Cloud Manager console, click the menu, and then click **View Selection**.
2. On the View Selection page, select **Storage System View**, and then click **Switch**.

### Result

Cloud Manager switches to the Volume View.

## Creating and mounting NFS volumes

You can use Cloud Manager to create NFS volumes that provide enterprise-class features on top of AWS storage.

### Creating NFS volumes

You can create a volume attached to a single AWS instance or to an instance that is mirrored to another instance to provide high availability.

### Steps

1. In the Volumes tab, click **Create New Volume**.
2. On the Create New Volume page, select a volume type:

Option	Description
Create Volume	Creates a volume attached to a single AWS instance.
Create HA volume	Creates a volume attached to a single AWS instance and mirrored to another instance to provide high availability in case of failures. Click the Info icon to see additional details about the instances required for an HA volume.

3. If you chose Create Volume, specify details for your first volume, and then click **Create**.

The following table describes fields for which you might need guidance:

Field	Description
Size	The maximum size for the volume depends on the capacity available in existing storage systems. Thin provisioning is automatically enabled on the volume, which enables you to create a volume that is bigger than the physical storage currently available to it. Instead of preallocating storage space, space is allocated to each volume as data is written.
AWS Disk Type	You should choose the disk that meets your requirements for both performance and cost. <ul style="list-style-type: none"> <li>• General Purpose SSD disks balance cost and performance for a broad range of workloads. Performance is defined in terms of IOPS.</li> <li>• Throughput Optimized HDD disks are for frequently accessed workloads that require fast and consistent throughput at a lower price.</li> <li>• Cold HDD disks are meant for backups, or infrequently accessed data, because the performance is very low. Like Throughput Optimized HDD disks, performance is defined in terms of throughput.</li> </ul> <p>For more details, refer to <a href="#">AWS Documentation: EBS Volume Types</a>.</p>

The following image shows the Create Volume page filled out:

The screenshot shows the AWS Create Volume page with the following details:

- Details:**
  - Volume Name:
  - Size (GB):
  - AWS Disk Type:
- Location:**
  - AWS Region: US East | N. Virginia
  - VPC: vpc-a6c1eac2 | 172.32.0.0/16
  - Subnet: 172.32.0.0/24

4. If you chose Create HA volume, specify details for the volume, and then click **Create**.

The following table describes fields for which you might need guidance:

Field	Description
Size	The maximum size for the volume depends on the capacity available in existing storage systems. Thin provisioning is automatically enabled on the volume, which enables you to create a volume that is bigger than the physical storage currently available to it. Instead of preallocating storage space, space is allocated to each volume as data is written.

Field	Description
AWS Disk Type	<p>You should choose the disk that meets your requirements for both performance and cost.</p> <ul style="list-style-type: none"> <li>• General Purpose SSD disks balance cost and performance for a broad range of workloads. Performance is defined in terms of IOPS.</li> <li>• Throughput Optimized HDD disks are for frequently accessed workloads that require fast and consistent throughput.</li> </ul> <p>For more details, refer to <a href="#">AWS Documentation: EBS Volume Types</a>.</p>
Location	You should choose a VPC that includes three subnets in three separate Availability Zones.
Nodes and Mediator	If possible, Cloud Manager chooses separate Availability Zones for each instance because it is the supported and optimal configuration.
Floating IP	The IP addresses must be outside of the CIDR block for all VPCs in the region.
Route Table	<p>If you have more than one route table, it is very important to select the correct route tables. Otherwise, some clients might not have access to the HA pair.</p> <p>For more details, refer to <a href="#">AWS Documentation: Route Tables</a>.</p>

The following image shows the Nodes and Mediator page. Each instance is in a separate Availability Zone.

Nodes & Mediator <span style="float: right;"><a href="#">Edit</a></span>			
<b>Node 1</b>	Availability Zone us-east-1d	Subnet 172.31.0.0/20	
<b>Node 2</b>	Availability Zone us-east-1c	Subnet 172.31.16.0/20	
<b>Mediator</b>	Availability Zone us-east-1b	Subnet 172.31.32.0/20	Key Pair EranVirginia

## Result

Cloud Manager creates the volume on an existing system or on a new system. If a new system is required, creating the volume can take approximately 25 minutes.

## Mounting volumes to Linux hosts

After you create a volume, you should mount it to your hosts so that they can access the volume.

### Steps

1. In the Volumes tab, place your mouse cursor over the volume, select the menu icon, and then click **Mount**.
2. Click **Copy**.
3. On your Linux hosts, modify the copied text by changing the destination directory, and then enter the command to mount the volume.

# Managing NFS volumes

You can manage NFS volumes by cloning them, managing data access, changing the underlying disk type, and more.

## Cloning volumes

If you need an instantaneous copy of your data without using a lot of disk space, you can create a clone of an existing volume.

### About this task

The cloned volume is a writable, point-in-time copy that is space-efficient because it uses a small amount of space for metadata, and then only consumes additional space as data is changed or added.

### Steps

1. In the Volumes tab, place your mouse cursor over the volume, select the menu icon, and then click **Clone**.
2. Modify the name of the cloned volume, if needed, and then click **Clone**.

### Result

Cloud Manager creates a new volume that is a clone of an existing volume.

## Managing data access to volumes

When you create a volume, Cloud Manager makes the volume available to all EC2 instances in the VPC in which the volume was created. You can modify this default value if you need to restrict data access to the volume.

### Steps

1. In the Volumes tab, place your mouse cursor over the volume, select the menu icon, and then click **Manage Access**.
2. Modify the volume access list, and then click **Save**.

## Changing the underlying AWS disk for a volume

You can change the underlying AWS disk that a volume uses to provide storage. For example, if higher performance is needed, you can change from a Throughput Optimized HDD to a General Purpose SSD.

### Steps

1. In the Volumes tab, place your mouse cursor over the volume, select the menu icon, and then click **Change Disk**.
2. Select the AWS disk type and click **Change**.

### Result

Cloud Manager moves the volume to an existing aggregate that uses the selected disk type or it creates a new aggregate for the volume.

## Viewing and modifying AWS resources

When you create a new volume, Cloud Manager allocates the AWS instances and EBS storage required for that volume. If required, you can view details about AWS instances and EBS storage, change instance types,


and turn instances off and on.

### Steps

1. Click **AWS Resources**.

The list of AWS instances displays. You can view details such as instance type, AWS location, and the volumes attached to the instance.

2. If required, select the menu icon next to the Status column, and then choose one of the available actions:



### Deleting volumes

You can delete volumes that you no longer need.

### Steps

1. In the Volumes tab, place your mouse cursor over the volume, select the menu icon, and then click **Delete**.
2. Click **Delete** to confirm that you want to delete the volume.

## Copyright information

Copyright © 2024 NetApp, Inc. All Rights Reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means—graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system—without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP "AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

LIMITED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (b)(3) of the Rights in Technical Data -Noncommercial Items at DFARS 252.227-7013 (FEB 2014) and FAR 52.227-19 (DEC 2007).

Data contained herein pertains to a commercial product and/or commercial service (as defined in FAR 2.101) and is proprietary to NetApp, Inc. All NetApp technical data and computer software provided under this Agreement is commercial in nature and developed solely at private expense. The U.S. Government has a non-exclusive, non-transferrable, nonsublicensable, worldwide, limited irrevocable license to use the Data only in connection with and in support of the U.S. Government contract under which the Data was delivered. Except as provided herein, the Data may not be used, disclosed, reproduced, modified, performed, or displayed without the prior written approval of NetApp, Inc. United States Government license rights for the Department of Defense are limited to those rights identified in DFARS clause 252.227-7015(b) (FEB 2014).

## Trademark information

NETAPP, the NETAPP logo, and the marks listed at <http://www.netapp.com/TM> are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.