



volume clone commands

ONTAP 9.3 commands

NetApp
September 27, 2022

Table of Contents

- volume clone commands 1
 - volume clone create 1
 - volume clone show 4
 - volume clone split estimate 10
 - volume clone split show 13
 - volume clone split start 15
 - volume clone split stop 16

volume clone commands

volume clone create

Create a FlexClone volume

Availability: This command is available to *cluster* and *Vserver* administrators at the *admin* privilege level.

Description

The `volume clone create` command creates a FlexClone volume on the aggregate containing the specified parent volume. This command is only supported for flexible volumes. The maximum volume clone hierarchy depth is 500 and the default depth is 60. You can optionally specify the following attributes for the new FlexClone volume:

- Vserver on which the parent volume resides
- Name of the FlexClone parent snapshot
- Junction path where FlexClone volume should be mounted
- State of the junction path
- Space guarantee style (none, volume or file)
- Comment
- Whether the `volume clone create` command runs as a foreground or background process

Parameters

-vserver <vserver name> - Vserver Name

This parameter specifies the Vserver on which the FlexClone volume is to be created. If only one data Vserver exists, you do not need to specify this parameter.

-flexclone <volume name> - FlexClone Volume

This parameter specifies the name of the FlexClone volume. The name must be unique within the hosting Vserver.

[-type {RW|DP}] - FlexClone Type

This parameter specifies the type of FlexClone volume. A read-only FlexClone volume is created if you specify the *type* as DP; otherwise a read-write FlexClone volume is created.

[-parent-vserver <vserver name>] - FlexClone Parent Vserver

This parameter specifies the name of the Vserver to which the FlexClone parent volume belongs. If it is different from the Vserver on which the FlexClone volume is to be created, then the FlexClone volume inherits the export policies from the residing Vserver, and not from the FlexClone parent volume.

-b, -parent-volume <volume name> - FlexClone Parent Volume

This parameter specifies the name of parent volume from which the FlexClone clone volume is derived.

[-parent-snapshot <snapshot name>] - FlexClone Parent Snapshot

This specifies the name of the parent snapshot from which the FlexClone clone volume is derived.

[-junction-path <junction path>] - Junction Path

This specifies the junction path at which the new FlexClone clone volume should be mounted.

[-junction-active {true|false}] - Junction Active

This optionally specifies whether the volume's junction path is active. The default setting is `true`. If the junction path is inactive, the volume does not appear in the Vserver's namespace. This parameter is available only at the advanced privilege level and higher.

[-s, -space-guarantee {none|volume}] - Space Guarantee Style

This optionally specifies the space guarantee style for the FlexClone volume. A value of `volume` reserves space on the aggregate for the entire volume. A value of `none` reserves no space on the aggregate, meaning that writes can fail if the aggregate runs out of space. The default setting is inherited from the parent volume.

[-comment <text>] - Comment

This optionally specifies a comment for the FlexClone volume.

[-foreground {true|false}] - Foreground Process

This optionally specifies whether the FlexClone volume create operation runs as a foreground process. The default setting is `true` (that is, the operation runs in the foreground).

{ [-qos-policy-group <text>] - QoS Policy Group Name

This parameter optionally specifies which QoS policy group to apply to the FlexClone volume. The policy group defines measurable service level objectives (SLOs) that apply to the storage objects with which the policy group is associated. If you do not assign a policy group to the FlexClone volume, the system does not monitor and control the traffic to the volume.

{ [-qos-adaptive-policy-group <text>] - QoS Adaptive Policy Group Name }

This optionally specifies which QoS adaptive policy group to apply to the volume. This policy group defines measurable service level objectives (SLOs) and Service Level Agreements (SLAs) that adjust based on the volume allocated space or used space. This parameter is not supported on FlexGroups or Infinite Volumes.

[-caching-policy <text>] - Caching Policy Name

This optionally specifies the caching policy to apply to the volume. A caching policy defines how the system caches this volume's data in Flash Cache modules. If a caching policy is not assigned to this volume, the system uses the caching policy that is assigned to the containing Vserver. If a caching policy is not assigned to the containing Vserver, the system uses the default cluster-wide policy. This parameter is not supported on Infinite Volumes. The available caching policies are:

- `none` - Does not cache any user data or metadata blocks.
- `auto` - Read caches all metadata and randomly read user data blocks, and write caches all randomly overwritten user data blocks.
- `meta` - Read caches only metadata blocks.
- `random_read` - Read caches all metadata and randomly read user data blocks.
- `random_read_write` - Read caches all metadata, randomly read and randomly written user data blocks.
- `all_read` - Read caches all metadata, randomly read, and sequentially read user data blocks.
- `all_read_random_write` - Read caches all metadata, randomly read, sequentially read and randomly written user data.

- all - Read caches all data blocks read and written. It does not do any write caching.
- noread-random_write - Write caches all randomly overwritten user data blocks. It does not do any read caching.
- meta-random_write - Read caches all metadata and write caches randomly overwritten user data blocks.
- random_read_write-random_write - Read caches all metadata, randomly read and randomly written user data blocks. It also write caches randomly overwritten user data blocks.
- all_read-random_write - Read caches all metadata, randomly read, and sequentially read user data blocks. It also write caches randomly overwritten user data blocks.
- all_read_random_write-random_write - Read caches all metadata, randomly read, sequentially read and randomly written user data. It also write caches randomly overwritten user data blocks.
- all-random_write - Read caches all data blocks read and written. It also write caches randomly overwritten user data blocks.

Note that in a caching-policy name, a hyphen (-) separates read and write policies. Default caching-policy is auto.

[-vserver-dr-protection {protected|unprotected}] - Vserver DR Protection

This optionally specifies whether the volume should be protected by Vserver level SnapMirror. This parameter is applicable only if the Vserver is the source of a Vserver level SnapMirror relationship. By default the clone volume will inherit this value from the parent volume. This parameter is not supported on Infinite Volumes.

[-uid <integer>] - Volume-Level UID

This parameter optionally specifies a volume-level user ID (UID). All files and directories in a FlexClone volume will inherit this UID.

[-gid <integer>] - Volume-Level GID

This parameter optionally specifies a volume-level group ID (GID). All files and directories in a FlexClone volume will inherit this GID.

Examples

The following command creates a FlexClone volume `fc_vol_1` from parent volume `fv2` on Vserver `vs1` and the job runs as a foreground process.

```

cluster1::> volume clone create -vserver vs1 -flexclone fc_vol_1
-parent-volume fv2 -junction-active true -foreground true -comment
"Testing FlexClone creation"
cluster1::> volume clone show fc_vol_1 -vserver vs1

          Vserver Name: vs1
          FlexClone Volume: fc_vol_1
          FlexClone Parent Volume: fv2
          FlexClone Parent Snapshot: clone_fc_vol_1.0
          Junction Path: -
          Junction Active: -
          Space Guarantee Style: volume
          Space Guarantee In Effect: true
          FlexClone Aggregate: test_aggr
          FlexClone Data Set ID: 1046
          FlexClone Master Data Set ID: 2147484694
          FlexClone Size: 19MB
          Used Size: 108KB
          Split Estimate: 0.00B
          Inodes processed: -
          Total Inodes: -
          Percentage complete: -
          Blocks Scanned: -
          Blocks Updated: -
          Comment: Testing FlexClone creation

```

volume clone show

Display a list of FlexClones

Availability: This command is available to *cluster* and *Vserver* administrators at the *admin* privilege level.

Description

The `volume clone show` command displays information about FlexClone clone volumes. This command is only supported for flexible volumes. By default, the command displays the following information about all FlexClone volume clones:

- Vserver name
- FlexClone volume name
- Parent volume name
- Parent snapshot name
- Whether a FlexClone volume is online or offline

To display detailed information about all FlexClone volumes, run the command with the `-instance` parameter.

Parameters

{ [-fields <fieldname>,...]

Selects the fields to be displayed.

| [-estimate]

Displays an estimate of the free disk space required in the aggregate to split the indicated clone volume from its underlying parent volume. The value reported may differ from the space actually required to perform the split, especially if the clone volume is changing when the split is being performed.

| [-instance] }

Displays detailed information about FlexClone volumes. If `-flexclone` is also specified, the command displays detailed information about the FlexClone volume.

[-vserver <vserver name>] - Vserver Name

Selects summary information for the FlexClone volumes on the specified Vserver. If `-flexclone` is also specified, the command displays detailed information about the specified FlexClone volume.

[-flexclone <volume name>] - FlexClone Volume

Selects summary information for the specified FlexClone volume. If `-vserver` is also specified, the command displays detailed information about the specified FlexClone volume.

[-type {RW|DP}] - FlexClone Type

Selects information for the specified type of FlexClone volume. The type can be specified as either read-only (DP) or read-write (RW).

[-parent-vserver <vserver name>] - FlexClone Parent Vserver

Selects summary information for the FlexClone volumes that are clone volumes in the specified parent Vserver.

[-b, -parent-volume <volume name>] - FlexClone Parent Volume

Selects summary information for the FlexClone volumes that are clones of the specified parent volume.

[-parent-snapshot <snapshot name>] - FlexClone Parent Snapshot

Selects summary information for the FlexClone volumes that are clones of the parent volume to which the specified snapshot belongs.

[-state {online|restricted|offline|force-online|force-offline|mixed}] - FlexClone Volume State

Selects summary information for the FlexClone volumes that are in the specified state.

[-junction-path <junction path>] - Junction Path

Selects summary information for the FlexClone volumes that have the specified junction path.

[-junction-active {true|false}] - Junction Active

Selects summary information for the FlexClone volumes that have the specified junction path status.

[-s, -space-guarantee {none|volume}] - Space Guarantee Style

If this parameter is specified, the command displays information only about the volumes that have the specified space guarantee style.

[-space-guarantee-enabled {true|false}] - Space Guarantee In Effect

Selects summary information for the FlexClone volumes that have the specified space-guarantee setting.

[-aggregate <aggregate name>] - FlexClone Aggregate

Selects summary information for the FlexClone volumes that reside on the specified storage aggregate.

[-dsid <integer>] - FlexClone Data Set ID

Selects summary information for the FlexClone volumes that have the specified Data Set ID.

[-msid <integer>] - FlexClone Master Data Set ID

Selects summary information for the FlexClone volumes that have the specified Master Data Set ID.

[-size {<integer>[KB|MB|GB|TB|PB]}] - FlexClone Size

Selects summary information for the FlexClone volumes that have the specified size.

[-used {<integer>[KB|MB|GB|TB|PB]}] - Used Size

Selects summary information for the FlexClone volumes that have the specified amount of used space.

[-split-estimate {<integer>[KB|MB|GB|TB|PB]}] - Split Estimate

Selects summary information for the FlexClone volumes that require the specified amount of free disk space for splitting from the parent.

[-inodes-processed <integer>] - Inodes Processed

Selects summary information for the FlexClone volumes that have the specified number of Inodes processed for splitting the FlexClone volume from its parent volume.

[-inodes-total <integer>] - Total Inodes

Selects summary information for the FlexClone volumes that have the specified number of total Inodes.

[-inode-percentage-complete <integer>] - Inode Percentage Complete

Selects summary information for the FlexClone volumes that have specified percentage of Inodes processed for splitting the FlexClone volume from its parent volume.

[-blocks-scanned <integer>] - Blocks Scanned

Selects summary information for the FlexClone volumes that have the specified number of blocks scanned for splitting the FlexClone volume from its parent volume.

[-blocks-updated <integer>] - Blocks Updated

Selects summary information for the FlexClone volumes that have the specified number of blocks updated for after splitting the FlexClone volume from its parent volume.

[-comment <text>] - Comment

Selects summary information for the FlexClone volumes that have the specified comment.

[-qos-policy-group <text>] - QoS Policy Group Name

Selects summary information for the FlexClone volumes that have the specified QoS policy group.

[-qos-adaptive-policy-group <text>] - QoS Adaptive Policy Group Name

Selects summary information for the FlexClone volumes that have the specified QoS adaptive policy group.

[-caching-policy <text>] - Caching Policy Name

This optionally specifies the caching policy to apply to the volume. A caching policy defines how the system caches this volume's data in Flash Cache modules. If a caching policy is not assigned to this volume, the system uses the caching policy that is assigned to the containing Vserver. If a caching policy is not assigned to the containing Vserver, the system uses the default cluster-wide policy. This parameter is not supported on Infinite Volumes. The available caching policies are:

- none - Does not cache any user data or metadata blocks.
- auto - Read caches all metadata and randomly read user data blocks, and write caches all randomly overwritten user data blocks.
- meta - Read caches only metadata blocks.
- random_read - Read caches all metadata and randomly read user data blocks.
- random_read_write - Read caches all metadata, randomly read and randomly written user data blocks.
- all_read - Read caches all metadata, randomly read, and sequentially read user data blocks.
- all_read_random_write - Read caches all metadata, randomly read, sequentially read and randomly written user data.
- all - Read caches all data blocks read and written. It does not do any write caching.
- noread-random_write - Write caches all randomly overwritten user data blocks. It does not do any read caching.
- meta-random_write - Read caches all metadata and write caches randomly overwritten user data blocks.
- random_read_write-random_write - Read caches all metadata, randomly read and randomly written user data blocks. It also write caches randomly overwritten user data blocks.
- all_read-random_write - Read caches all metadata, randomly read, and sequentially read user data blocks. It also write caches randomly overwritten user data blocks.
- all_read_random_write-random_write - Read caches all metadata, randomly read, sequentially read and randomly written user data. It also write caches randomly overwritten user data blocks.
- all-random_write - Read caches all data blocks read and written. It also write caches randomly overwritten user data blocks.

Note that in a caching-policy name, a hyphen (-) separates read and write policies. Default caching-policy is auto.

[-parent-vol-type <volAccessType>] - Parent volume type

Selects summary information for the FlexClone volumes that are clones of the parent volumes with the specified type.

[-flexclone-used-percent <percent>] - FlexClone Used Percentage

Selects summary information for the FlexClone volumes that have the specified percentage of used space.

[-vserver-dr-protection {protected|unprotected}] - Vserver DR Protection

Selects summary information for the FlexClone volumes that have the specified type of Vserver SnapMirror protection. This parameter is applicable only if the Vserver is the source of a Vserver level SnapMirror relationship.

[-block-percentage-complete <integer>] - Block Percentage Complete

Selects summary information for the FlexClone volumes that have specified percentage of Blocks processed for splitting the FlexClone volume from its parent volume.

[-uid <integer>] - Volume-Level UID

Selects summary information for the FlexClone volumes that are created with the specified volume-level UID.

[-gid <integer>] - Volume-Level GID

Selects summary information for the FlexClone volumes that are created with the specified volume-level GID.

Examples

The following example displays detailed information about all FlexClone volumes on Vserver vs0:

```
cluster1::> volume clone show -vserver vs0
(volume clone show)
Vserver    FlexClone      Parent-Volume  Parent-Snapshot
-----
vs0        fc_vol_1       test_vol       clone_fc_vol_1.0
          fc_vol_2       test_vol2      clone_fc_vol_2.0
          fc_vol_3       tv9            clone_fc_vol_3.0
          tv8           tv7            clone_tv8.0
          tv9           test_vol2      clone_tv9.0
5 entries were displayed.
```

The following example displays detailed information about FlexClone volume fc_vol_2 on Vserver vs0:

```

cluster1::> volume clone show -vserver vs0 -flexclone fc_vol_2

      Vserver Name: vs0
      FlexClone Volume: fc_vol_2
      FlexClone Parent Volume: test_vol2
      FlexClone Parent Snapshot: clone_fc_vol_2.0
      Junction Path: -
      Junction Active: -
      Space Guarantee Style: volume
      Space Guarantee In Effect: true
      FlexClone Aggregate: test_aggr
      FlexClone Data Set ID: 1038
      FlexClone Master Data Set ID: 2147484686
      FlexClone Size: 47.50MB
      Used Size: 128KB
      Split Estimate: 0.00B
      Inodes processed: -
      Total Inodes: -
      Inode Percentage complete: -
      Blocks Scanned: -
      Blocks Updated: -
      Comment:
      Qos Policy Group Name: pg1
      FlexClone Parent Volume Type: RW
      Block Percentage complete: -

```

The following example displays summary information about all FlexClone volumes residing on Vserver vs0 along with the fields msid, dsid, state and parent-volume.

```

cluster1::> volume clone show -vserver vs0 -fields msid, dsid, state,
parent-volume
vserver flexclone parent-volume state dsid msid
-----
vs0 fc_vol_1 test_vol online 1037 2147484685
vs0 fc_vol_3 tv9 online 1039 2147484687
vs0 flex_clone1
      fc_vol_1 online 1041 2147484689
vs0 fv_2 fc_vol_1 online 1043 2147484691
vs0 tv9 test_vol2 online 1036 2147484684
5 entries were displayed.

```

The following example displays summary information about all FlexClone volumes residing on Vserver vs0 along with space-guarantee-enabled and space-guarantee information about each FlexClone volume.

```

cluster1::> vol clone show -vserver vs0 -fields space-guarantee-enabled,
space-guarantee
  (volume clone show)
vserver flexclone space-guarantee space-guarantee-enabled
-----
vs0      fc_vol_1  volume      true
vs0      fc_vol_3  volume      true
vs0      flex_clone1
          volume      true
vs0      fv_2     volume      true
vs0      tv9      volume      true
5 entries were displayed.

```

volume clone split estimate

Estimates the space required by the containing-aggregate to split the FlexClone volume

Availability: This command is available to *cluster* and *Vserver* administrators at the *admin* privilege level.

Description

The `volume clone split estimate` command displays an estimate of the free disk space required in the aggregate to split the indicated clone volume from its underlying parent volume. The value reported might differ from the space actually required to perform the split, especially if the clone volume is changing when the split is being performed. This command is only supported for flexible volumes.

Parameters

[`-vserver <vserver name>`] - Vserver Name

This specifies the estimates for free disk space required for splitting FlexClone volumes residing on this Vserver. If the `-flexclone` option is also specified, then the command displays the free disk space estimate only for the specified FlexClone volume residing on the specified Vserver.

[`-flexclone <volume name>`] - FlexClone Volume

This specifies the free disk space estimate for splitting this FlexClone volume.

[`-type {RW|DP}`] - FlexClone Type

This parameter specifies the type of FlexClone volume. A read-only FlexClone volume is created if you specify the `type` as `DP`; otherwise a read-write FlexClone volume is created.

[`-parent-vserver <vserver name>`] - FlexClone Parent Vserver

This specifies the free disk space estimates for splitting the FlexClone volumes that are clones in the specified parent Vserver.

[`-b, -parent-volume <volume name>`] - FlexClone Parent Volume

This specifies the free disk space estimates for splitting the FlexClone volumes cloned off this parent volume.

[~~-parent-snapshot~~ <snapshot name>] - FlexClone Parent Snapshot

This specifies the free disk space estimates for splitting the FlexClone volumes cloned off this parent snapshot.

[~~-state~~ {online|restricted|offline|force-online|force-offline|mixed}] - FlexClone Volume State

This specifies the free disk space estimates for splitting the FlexClone volumes with the specified state.

[~~-junction-path~~ <junction path>] - Junction Path

This specifies the free disk space estimates for splitting the FlexClone volumes mounted at this junction path.

[~~-junction-active~~ {true|false}] - Junction Active

If this specified, the command displays the free disk space estimate for splitting the FlexClone volumes with the specified junction path status.

[~~-s, -space-guarantee~~ {none|volume}] - Space Guarantee Style

This specifies the free disk space estimates for splitting the FlexClone volumes with the specified type of space guarantee.

[~~-space-guarantee-enabled~~ {true|false}] - Space Guarantee In Effect

This specifies the free disk space estimates for splitting the FlexClone volumes with the specified state of space guarantee.

[~~-aggregate~~ <aggregate name>] - FlexClone Aggregate

This specifies the free disk space estimates for splitting the FlexClone volumes residing on the specified aggregate.

[~~-dsid~~ <integer>] - FlexClone Data Set ID

This specifies the free disk space estimates for splitting the FlexClone volume with the specified DSID (data set ID).

[~~-msid~~ <integer>] - FlexClone Master Data Set ID

This specifies the free disk space estimates for splitting the FlexClone volumes with the specified MSID (master data set ID).

[~~-size~~ {<integer>[KB|MB|GB|TB|PB]}] - FlexClone Size

This specifies the free disk space estimates for splitting FlexClone volumes with the specified size.

[~~-used~~ {<integer>[KB|MB|GB|TB|PB]}] - Used Size

This specifies the free disk space estimates for splitting the FlexClone volumes with the specified amount of used disk space.

[~~-split-estimate~~ {<integer>[KB|MB|GB|TB|PB]}] - Split Estimate

This specifies the free disk space estimates for splitting the FlexClone volumes which match with the specified free disk space estimate for splitting.

[~~-inodes-processed~~ <integer>] - Inodes Processed

This specifies the free disk space estimates for splitting the FlexClone volumes for which the specified number of Inodes have been processed already.

[-inodes-total <integer>] - Total Inodes

This specifies the free disk space estimates for splitting the FlexClone volumes for which the specified total number of inodes need to be processed.

[-inode-percentage-complete <integer>] - Inode Percentage Complete

This specifies the free disk space estimates for splitting the FlexClone volumes for which the specified percentage of Inode processing has been completed.

[-blocks-scanned <integer>] - Blocks Scanned

This specifies the free disk space estimates for splitting the FlexClone volumes for which the specified number of blocks have been scanned.

[-blocks-updated <integer>] - Blocks Updated

This specifies the free disk space estimates for splitting the FlexClone volumes for which the specified number of blocks have been updated.

[-comment <text>] - Comment

This specifies the free disk space estimates for splitting the FlexClone volumes that have the specified value for the comment field.

[-qos-policy-group <text>] - QoS Policy Group Name

This parameter optionally specifies which QoS policy group to apply to the FlexClone volume. The policy group defines measurable service level objectives (SLOs) that apply to the storage objects with which the policy group is associated. If you do not assign a policy group to the FlexClone volume, the system does not monitor and control the traffic to the volume.

[-qos-adaptive-policy-group <text>] - QoS Adaptive Policy Group Name

This optionally specifies which QoS adaptive policy group to apply to the volume. This policy group defines measurable service level objectives (SLOs) and Service Level agreements (SLAs) that adjust based on the volume allocated space or used space. This parameter is not supported on FlexGroups or Infinite Volumes.

[-caching-policy <text>] - Caching Policy Name

This specifies the free disk space estimates for splitting the FlexClone volumes that are clones with the specified caching policy.

[-parent-vol-type <volAccessType>] - Parent volume type

This specifies the free disk space estimates for splitting the FlexClone volumes that are clones of the parent volumes with the specified type.

[-flexclone-used-percent <percent>] - FlexClone Used Percentage

This specifies the free disk space estimates for splitting the FlexClone volumes that are clones with the specified percentage of used space.

[-vserver-dr-protection {protected|unprotected}] - Vserver DR Protection

This specifies the free disk space estimates for splitting the FlexClone volumes that are clones with the specified Vserver SnapMirror protection. This parameter is not supported on Infinite Volumes.

[-block-percentage-complete <integer>] - Block Percentage Complete

This specifies the free disk space estimates for splitting the FlexClone volumes for which the specified percentage of Block processing has been completed.

[`-uid <integer>`] - Volume-Level UID

This specifies the free disk space estimates for splitting the FlexClone volumes that are clones with the specified volume-level UID.

[`-gid <integer>`] - Volume-Level GID

This specifies the free disk space estimates for splitting the FlexClone volumes that are clones with the specified volume-level GID.

Examples

The following example displays the FlexClone split free disk space estimates for the FlexClone volumes residing on Vserver `vs0`.

```
cluster1::> volume clone split estimate -vserver vs0
(volume clone split estimate)

```

Vserver	FlexClone	Split Estimate
vs0	fc_vol_1	851.5MB
	fc_vol_3	0.00B
	flex_clone1	350.3MB
	fv_2	47.00MB
	tv9	0.00B

5 entries were displayed.

volume clone split show

Show the status of FlexClone split operations in-progress

Availability: This command is available to *cluster* and *Vserver* administrators at the *admin* privilege level.

Description

The `volume clone split show` command displays the progress information of all the active FlexClone volume splitting jobs. This command is only supported for flexible volumes. By default, this command displays the following information:

- Vserver name
- FlexClone volume name
- Number of inodes processed during clone splitting
- Total inodes to be processed during clone splitting
- Percentage of inodes processed
- Percentage of blocks processed
- Total number of blocks scanned for clone splitting
- Total number of blocks updated for clone splitting

If the `-instance` option is also specified, detailed information about all splitting jobs is displayed.

Parameters

{ [-fields <fieldname>,...]

This specifies the fields to be displayed, for all the ongoing FlexClone splitting jobs.

| [-instance] }

This specifies the command to display detailed information about the ongoing FlexClone volume splitting jobs.

[-vserver <vserver name>] - Vserver Name

Selects information about the ongoing FlexClone volume splitting jobs for all FlexClone volumes on this Vserver.

[-flexclone <volume name>] - FlexClone Volume

Selects information about ongoing FlexClone volume splitting jobs for this FlexClone volume.

[-inodes-processed <integer>] - Inodes processed

Selects information about all the ongoing FlexClone splitting jobs which have the specified number of Inodes processed.

[-inodes-total <integer>] - Total Inodes

Selects information about all the ongoing FlexClone splitting jobs that have the specified number of total Inodes to be processed.

[-inode-percentage-complete <integer>] - Inode Percentage complete

Selects information about all the ongoing FlexClone splitting jobs that have the specified percentage of Inode processing completed.

[-block-percentage-complete <integer>] - Block Percentage complete

Selects information about all the ongoing FlexClone splitting jobs that have the specified percentage of Block processing completed.

[-blocks-scanned <integer>] - Blocks Scanned

Selects information about all the ongoing FlexClone splitting jobs that have the specified number of blocks scanned.

[-blocks-updated <integer>] - Blocks Updated

Selects information about all the ongoing FlexClone splitting jobs that have the specified number of blocks updated.

Examples

The following example displays information about all the ongoing FlexClone splitting jobs in the cluster.


```

cluster1::> volume clone split show
(volume clone split show)

```

Vserver	FlexClone	Inodes		Blocks		% Inode	%
		Processed	Total	Scanned	Updated		
Block							
		Complete	Complete				
vs1	fc_vol_1	0	1260	0	0	0	0

The following example displays information about FlexClone volume `fc_vol_2` residing on Vserver `vs0`.

```

cluster1::> volume clone split show -vserver vs0 -flexclone fc_vol_2
-instance
(volume clone split show)

```

```

Vserver Name: vs0
FlexClone Volume: fc_vol_2
FlexClone Volume: fc_vol_2
Inodes processed: 0
Total Inodes: 3192
Inode Percentage complete: 0
Block Percentage complete: 0
Blocks Scanned: 0
Blocks Updated: 0

```

volume clone split start

Split a FlexClone from the parent volume

Availability: This command is available to *cluster* and *Vserver* administrators at the *admin* privilege level.

Description

The `volume clone split start` command starts a job to separate the FlexClone volume from the underlying parent volume. Both, the parent and the FlexClone volumes will be available for the duration of the split operation. After the job starts, you can stop it using the [volume clone split stop](#) command. You can also stop the job using the [job stop](#) command. You can monitor the current progress of the job using the [volume clone split show](#) and [job show](#) commands. This command is only supported for flexible volumes. This command is not supported on volumes that are being protected as part of a Vserver level SnapMirror.

Parameters

-vserver <vserver name> - Vserver Name

This specifies the Vserver that the FlexClone volume exists on.

-flexclone <volume name> - FlexClone Volume

This specifies the FlexClone volume that will be split from its parent volume.

[-foreground <true>] - Foreground Process

This specifies whether the clone splitting job will run as a foreground job. The default value of this option is `true`.

Examples

The following example starts splitting FlexClone volume `fc_vol_1` on Vserver `vs1` as a foreground job.

```
cluster1::> volume clone split start -vserver vs1 -flexclone fc_vol_1
-foreground true
```

Related Links

- [volume clone split stop](#)
- [job stop](#)
- [volume clone split show](#)
- [job show](#)

volume clone split stop

Stop an ongoing FlexClone split job

Availability: This command is available to *cluster* and *Vserver* administrators at the *admin* privilege level.

Description

The `volume clone split stop` command stops the process of separating the FlexClone volume from its underlying parent volume, but does not lose any of the progress achieved while the split process was active. That is, all the clone volume blocks already separated from the parent volume remain separated. If you restart the split operation, splitting process begins from the beginning because no information about previously achieved progress is saved, but previously split blocks are not re-split. This command is only supported for flexible volumes.

Parameters

-vserver <vserver name> - Vserver Name

This specifies the Vserver that the FlexClone volume exists on.

-flexclone <volume name> - FlexClone Volume

This specifies the FlexClone volume whose separation from the parent volume will be stopped.

Examples

The following example stops an ongoing clone splitting job for FlexClone volume `fc_vol_1` on Vserver `vs1`.

```
cluster1::> volume clone split stop -vserver vs1 -flexclone fc_vol_1
```

Copyright Information

Copyright © 2022 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system-without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP "AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at <http://www.netapp.com/TM> are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.