



security certificate commands

ONTAP 9.6 commands

NetApp
June 26, 2024

Table of Contents

- security certificate commands 1
 - security certificate create 1
 - security certificate delete 3
 - security certificate generate-csr 5
 - security certificate install 7
 - security certificate rename 10
 - security certificate show-generated 11
 - security certificate show-truststore 14
 - security certificate show-user-installed 17
 - security certificate show 20
 - security certificate sign 23
 - security certificate ca-issued revoke 27
 - security certificate ca-issued show 27
 - security certificate truststore show 30

security certificate commands

security certificate create

Create and Install a Self-Signed Digital Certificate

Availability: This command is available to *cluster* and *Vserver* administrators at the *admin* privilege level.

Description

The `security certificate create` command creates and installs a self-signed digital certificate, which can be used for server authentication, for signing other certificates by acting as a certificate authority (CA), or for Data ONTAP as an SSL client. The certificate function is selected by the `-type` field. Self-signed digital certificates are not as secure as certificates signed by a CA. Therefore, they are not recommended in a production environment.

Parameters

-vserver <Vserver Name> - Name of Vserver

This specifies the name of the Vserver on which the certificate will exist.

-common-name <FQDN or Custom Common Name> - FQDN or Custom Common Name

This specifies the desired certificate name as a fully qualified domain name (FQDN) or custom common name or the name of a person. The supported characters, which are a subset of the ASCII character set, are as follows:

- Letters a through z, A through Z
- Numbers 0 through 9
- Asterisk (*), period (.), underscore (_) and hyphen (-)

The common name must not start or end with a "-" or ".". The maximum length is 253 characters.

-type <type of certificate> - Type of Certificate

This specifies the certificate type. Valid values are the following:

- *server* - creates and installs a self-signed digital certificate and intermediate certificates to be used for server authentication
- *root-ca* - creates and installs a self-signed digital certificate to sign other certificates by acting as a certificate authority (CA)
- *client* - includes a self-signed digital certificate and private key to be used for Data ONTAP as an SSL client

[-subtype <kmip-cert>] - (DEPRECATED)-Certificate Subtype



This parameter has been deprecated in ONTAP 9.6 and may be removed in a future release of Data ONTAP.

This specifies a certificate subtype. This optional parameter can have an empty value (the default). The only valid value is as follows:

- *kmip-cert* - this is a Key Management Interoperability Protocol (KMIP) certificate

[-cert-name <text>] - Unique Certificate Name

This specifies the system's internal identifier for the certificate. It must be unique within a Vserver. If not provided, it is automatically generated by the system.

-size <size of requested certificate in bits> - Size of Requested Certificate in Bits

This specifies the number of bits in the private key. The larger the value, the more secure is the key. The default is 2048. Possible values include *512*, *1024*, *1536*, *2048* and *3072* when the "FIPS Mode" in "security config" is false. When the "FIPS Mode" is true, the possible values are *2048* and *3072*.

-country <text> - Country Name

This specifies the country where the Vserver resides. The country name is a two-letter code. The default is US. Here is the list of country codes:

[Country Codes](#)

-state <text> - State or Province Name

This specifies the state or province where the Vserver resides.

-locality <text> - Locality Name

This specifies the locality where the Vserver resides. For example, the name of a city.

-organization <text> - Organization Name

This specifies the organization where the Vserver resides. For example, the name of a company.

-unit <text> - Organization Unit

This specifies the unit where the Vserver resides. For example, the name of a section or a department within a company.

-email-addr <mail address> - Contact Administrator's Email Address

This specifies the email address of the contact administrator for the Vserver.

-expire-days <integer> - Number of Days until Expiration

This specifies the number of days until the certificate expires. The default value is 365 days. Possible values are between *1* and *3652*.

-protocol <protocol> - Protocol

This specifies the protocol type. This parameter currently supports only the SSL protocol type. The default is SSL.

-hash-function <hashing function> - Hashing Function

This specifies the cryptographic hashing function for signing the certificate. The default is SHA256. Possible values include *SHA1*, *SHA256*, *MD5*, *SHA224*, *SHA384* and *SHA512* when the "FIPS Mode" in "security config" is false. When the "FIPS Mode" is true, the possible values are *SHA224*, *SHA256*, *SHA384* and *SHA512*.

Examples

This example creates a server type, self-signed digital certificate for a Vserver named vs0 at a company whose custom common name is *www.example.com* and whose Vserver name is vs0.

```
cluster1::> security certificate create -vserver vs0 -common-name
www.example.com -type server
```

This example creates a root-ca type, self-signed digital certificate with a 2048-bit private key generated by the SHA256 hashing function that will expire in 365 days for a Vserver named vs0 for use by the Software group in IT at a company whose custom common name is *www.example.com*, located in Sunnyvale, California, USA. The email address of the contact administrator who manages the Vserver is *web@example.com*.

```
cluster1::> security certificate create -vserver vs0 -common-name
www.example.com -type root-ca -size 2048 -country US -state California
-locality Sunnyvale -organization IT -unit Software -email-addr
web@example.com -expire-days 365 -hash-function SHA256
```

This example creates a client type of self-signed digital certificate for a Vserver named vs0 at a company that uses Data ONTAP as an SSL client. The company's custom common name is *www.example.com* and its Vserver name is vs0.

```
cluster1::> security certificate create -vserver vs0 -common-name
www.example.com -type client -size 2048 -country US -state California
-locality Sunnyvale -organization IT -unit Software -email-addr
web@example.com -expire-days 365 -hash-function SHA256
```

security certificate delete

Delete an Installed Digital Certificate

Availability: This command is available to *cluster* and *Vserver* administrators at the *admin* privilege level.

Description

This command deletes an installed digital security certificate.

Parameters

-vserver <Vserver Name> - Name of Vserver

This specifies the Vserver that contains the certificate.

-common-name <FQDN or Custom Common Name> - FQDN or Custom Common Name

This specifies the desired certificate name as a fully qualified domain name (FQDN) or custom common name or the name of a person. The supported characters, which are a subset of the ASCII character set, are as follows:

- Letters a through z, A through Z
- Numbers 0 through 9
- Asterisk (*), period (.), underscore (_) and hyphen (-)

The common name must not start or end with a "-" or a ".". The maximum length is 253 characters.

[`-serial <text>`] - Serial Number of Certificate

This specifies the certificate serial number.

`-ca <text>` - Certificate Authority

This specifies the certificate authority (CA).

`-type <type of certificate>` - Type of Certificate

This specifies the certificate type. Valid values are the following:

- *server* - includes server certificates and intermediate certificates
- *root-ca* - includes a self-signed digital certificate to sign other certificates by acting as a certificate authority (CA)
- *client-ca* - includes the public key certificate for the root CA of the SSL client. If this *client-ca* certificate is created as part of a *root-ca*, it will be deleted along with the corresponding deletion of the *root-ca*.
- *server-ca* - includes the public key certificate for the root CA of the SSL server to which Data ONTAP is a client. If this *server-ca* certificate is created as part of a *root-ca*, it will be deleted along with the corresponding deletion of the *root-ca*.
- *client* - includes a public key certificate and private key to be used for Data ONTAP as an SSL client

[`-subtype <kmip-cert>`] - (DEPRECATED)-Certificate Subtype



This parameter has been deprecated in ONTAP 9.6 and may be removed in a future release of Data ONTAP.

This specifies a certificate subtype. This optional parameter can have an empty value (the default). The only valid value is as follows:

- *kmip-cert* - this is a Key Management Interoperability Protocol (KMIP) certificate

[`-cert-name <text>`] - Unique Certificate Name

This specifies the system's internal identifier for the certificate. It is unique within a Vserver.

Examples

This example deletes a *root-ca* type digital certificate for a Vserver named *vs0* in a company named *www.example.com* with serial number *4F57D3D1*.

```
cluster1::> security certificate delete -vserver vs0 -common-name
www.example.com -ca www.example.com -type root-ca -serial 4F57D3D1
```

security certificate generate-csr

Generate a Digital Certificate Signing Request

Availability: This command is available to *cluster* and *Vserver* administrators at the *admin* privilege level.

Description

This command generates a digital certificate signing request and displays it on the console. A certificate signing request (CSR or certification request) is a message sent securely to a certificate authority (CA) via any electronic media, to apply for a digital identity certificate.

Parameters

-common-name <FQDN or Custom Common Name> - FQDN or Custom Common Name

This specifies the desired certificate name as a fully qualified domain name (FQDN) or custom common name or the name of a person. The supported characters, which are a subset of the ASCII character set, are as follows:

- Letters a through z, A through Z
- Numbers 0 through 9
- Asterisk (*), period (.), underscore (_) and hyphen (-)

The common name must not start or end with a "-" or a ".". The maximum length is 253 characters.

[-size <size of requested certificate in bits>] - Size of Requested Certificate in Bits

This specifies the number of bits in the private key. The higher the value, the more secure is the key. The default is 2048. Possible values include *512*, *1024*, *1536* and *2048*.

[-country <text>] - Country Name

This specifies the country where the Vserver resides. The country name is a two-letter code. The default is US. Here is the list of country codes:

[Country Codes](#)

[-state <text>] - State or Province Name

This specifies the state or province where the Vserver resides.

[-locality <text>] - Locality Name

This specifies the locality where the Vserver resides. For example, the name of a city.

[-organization <text>] - Organization Name

This specifies the organization where the Vserver resides. For example, the name of a company.

[-unit <text>] - Organization Unit

This specifies the unit where the Vserver resides. For example, the name of a section or a department within a company.

[-email-addr <mail address>] - Contact Administrator's Email Address

This specifies the email address of the contact administrator for the Vserver.

[-hash-function <hashing function>] - Hashing Function

This specifies the cryptographic hashing function for signing the certificate. The default is SHA256. Possible values include *SHA1* , *SHA256* and *MD5* .

Examples

This example creates a certificate-signing request with a 2048-bit private key generated by the SHA256 hashing function for use by the Software group in IT at a company whose custom common name is *www.example.com* , located in Sunnyvale, California, USA. The email address of the contact administrator who manages the Vserver is *web@example.com* .

```
cluster1::> security certificate generate-csr -common-name www.example.com
-size 2048 -country US -state California -locality Sunnyvale -organization
IT -unit Software
-email-addr web@example.com -hash-function SHA256
```

Certificate Signing Request :

-----BEGIN CERTIFICATE REQUEST-----

```
MIIBGjCBxQIBADBgMRQwEgYDVQQDEwtleGFtcGxlLmNvbTELMakGA1UEBhMCVVMx
CTAHBgNVBAgTADExMAcGA1UEBxMAMQkwBwYDVQQKEwAxCTAHBgNVBAsTADExPMA0G
CSqGSIB3DQEJARYAMFwwDQYJKoZIhvcNAQEBBQADSwAwSAJBAPXFanNoJApTlnzS
xOcxixqImRRGZCR7tVmTYyqPSuTvfVhVtwDJbmXuj6U3alwoUsb13wfEvQnHVFNCi
2ninsJ8CAwEAAaAAMA0GCSqGSIB3DQEBcWUAA0EA6EagLfso5+4g+ejiRKKKTUPQO
UqOUEoKuvxhOvPC2w7b//fNSFsFHvXloqEOhYECn/NX9h8mbphCoM5YZ4OfnKw==
-----END CERTIFICATE REQUEST-----
```

Private Key :

-----BEGIN RSA PRIVATE KEY-----

```
MIIBOwIBAAJBAPXFanNoJApTlnzSxOcxixqImRRGZCR7tVmTYyqPSuTvfVhVtwDJb
mXuj6U3alwoUsb13wfEvQnHVFNCi2ninsJ8CAwEAAQJAWt2AO+bW3FKezEuIrQlu
KoMyRYK455wtMk8BrOyJfhYsB20B28eifjJvRWdTOBEav99M7cEzgPv+p5kaZTTM
gQIhAPsp+j1hrUXSRj979LIJJY0sNez397i7ViFXWQScx/ehAiEA+oDbOooWlVvu
xj4aitxVBu6ByVckYU8LbsfeRNsZwD8CIQCbZ1/ENvmlJ/P7N9Exj2NCtEYxd0Q5
cwBZ5NfZeMBpwQIhAPk0KWQSLadGfsKO077itF+h9FGFNHbtuNTrVq4vPW3nAiAA
peMBQgEv28y2r8D4dkYzxcXmjzJluUSZSZ9c/wS6fA==
-----END RSA PRIVATE KEY-----
```

Note: Please keep a copy of your certificate request and private key for future reference.

security certificate install

Install a Digital Certificate

Availability: This command is available to *cluster* and *Vserver* administrators at the *admin* privilege level.

Description

The `security certificate install` command installs digital security certificates signed by a certificate authority (CA) and the public key certificate of the root CA. Digital security certificates also include the intermediate certificates to construct the chain for server certificates (the `server` type), client-side root CA certificates (the `client-ca` type), or server-side root CA certificates (the `server-ca` type). With FIPS enabled, the following restrictions apply to the certificate getting installed. `server/client/server-ca/client-ca`: Key size \geq 2048, `server/client`: Hash function (No MD-5, No SHA-1), `server-ca/client-ca`: (Intermediate CA), Hash Function (No MD-5, No SHA-1), `server-ca/client-ca`: (Root CA), Hash Function (No MD-5)

Parameters

-vserver <Vserver Name> - Name of Vserver

This specifies the Vserver that contains the certificate.

-type <type of certificate> - Type of Certificate

This specifies the certificate type. Valid values are the following:

- `server` - includes server certificates and intermediate certificates.
- `client-ca` - includes the public key certificate for the root CA of the SSL client
- `server-ca` - includes the public key certificate for the root CA of the SSL server to which Data ONTAP is a client
- `client` - includes a self-signed or CA-signed digital certificate and private key to be used for Data ONTAP as an SSL client

[-subtype <kmip-cert>] - (DEPRECATED)-Certificate Subtype



This parameter has been deprecated in ONTAP 9.6 and may be removed in a future release of Data ONTAP.

This specifies a certificate subtype. This optional parameter can have an empty value (the default). The only valid value is as follows:

- `kmip-cert` - this is a Key Management Interoperability Protocol (KMIP) certificate

[-kmip-server-ip <IP Address>] - (DEPRECATED)-IPv4 and IPv6 address



This parameter is deprecated and might be removed in the future releases of Data ONTAP.

This parameter is applicable only to the ```_kmip-cert_``` subtype. It specifies the IP address of the KMIP server.

[-cert-name <text>] - Unique Certificate Name

This specifies the system's internal identifier for the certificate. It must be unique within a Vserver. If not provided, it is automatically generated by the system.

Examples

This example installs a CA-signed certificate (along with intermediate certificates) for a Vserver named vs0.

```
cluster1::> security certificate install -vserver vs0 -type server
Please enter Certificate: Press <Enter> when done
-----BEGIN CERTIFICATE-----
MIIB8TCCAZugAwIBAwIBADANBgkqhkiG9w0BAQQFADBfMRMwEQYDVQQDEwpuZXRh
cHAuY29tMQswCQYDVQQGEwJVUzEJMAcGA1UECBMAMQkwBwYDVQQHEwAxCTAHBgNV
BAoTADJEJMAcGA1UECXMAMQ8wDQYJKoZIhvcNAQkBFgAwHhcNMTAwNDI2MTk0OTI4
WhcNMTAwNTI2MTk0OTI4WjBfMRMwEQYDVQQDEwpuZXRhcHAuY29tMQswCQYDVQQG
EwJVUzEJMAcGA1UECBMAMQkwBwYDVQQHEwAxCTAHBgNVBAoTADJEJMAcGA1UECXM
AMQ8wDQYJKoZIhvcNAQkBFgAwXDANBgkqhkiG9w0BAQEFAANLADBIAkEAYxRk2sry
-----END CERTIFICATE-----
Please enter Private Key: Press <Enter> when done
-----BEGIN RSA PRIVATE KEY-----
MIIBPAIBAAJBAM16ytrK8nQj82UsWeHOeT8gk0BPX+Y5MLycsUdXA7hXhumHNpvF
C61X2G32Sx8VEalth94tx+vOEq+UaqHlt0CAwEAAQJBAMzjDWlglm3qIr/n8VT
PFnnZnbVcXVM70tbUsgPKw+QCCh9dF1jmuQKeDr+wUMWkn1DeGrfhILpzfJGhrLJ
z7UCIQDr8d3gOG71UyX+BbFmo/N0uAKjS2cvUU+Y8a8pDxGLLwIhANqa99SuS18U
DiPvdaKTj6+EcGuXfCXz+G0rfgTZK8uzAiEArlmnrFYC8KwE9k7A0y1RzBLdUwK9
AvuJDn+/z+H1Bd0CIQDD93P/xpaJETNz53Au49VE5Jba/Jugckrbosd/lSd7nQIg
aEMAZt6qHHT4mndi8Bo8sDGedG2SKx6Qbn2IpuNZ7rc=
-----END RSA PRIVATE KEY-----

Do you want to continue entering root and/or intermediate certificates
{y|n}: y

Please enter Intermediate Certificate: Press <Enter> when done
-----BEGIN CERTIFICATE-----
MIIE+zCCBGSgAwIBAgICAQ0wDQYJKoZIhvcNAQEFBQAwbG1DZXJ0IFZhbG1kYXRpb24gTmV0d29yazEXMBUGA1UEChMOVmfSaUN1cnQsIElu
Yy4xNTAzBgNVBAsTLFZhbG1DZXJ0IENsYXNzIDIgUG9saWN5IFZhbG1kYXRpb24g
QXV0aG9yaXR5MSEwHwYDVQQDEExhbnRvOj8vd3d3LnZhbG1kYXRpb24gZXRhbnRvOj8vd3d3LnZhbG1kYXRpb24gZXRhbnRvOj8vd3d3LnZhbG1kYXRpb24g
BgkqhkiG9w0BCQEWElwZm9AdmFsaWN1cnQuY29tMB4XDTA0MDYyOTE3MDYyMFoX
DTI0MDYyOTE3MDYyMFowYzELMAkGA1UEBhMCVVMxITAfBgNVBAoTGFZhbG1kYXRpb24gZXRhbnRvOj8vd3d3LnZhbG1kYXRpb24gZXRhbnRvOj8vd3d3LnZhbG1kYXRpb24g
YWRkeSBHcm91cCwgSW5jLjExMC8GA1UECXMOR28gRGFkZHZkgQ2xhc3MgMiBDZXJ0
-----END CERTIFICATE-----

Do you want to continue entering root and/or intermediate certificates
{y|n}: y

Please enter Intermediate Certificate: Press <Enter> when done
```

```
-----BEGIN CERTIFICATE-----
```

```
MIIC5zCCAlACAQEwDQYJKoZIhvcNAQEFBQAwbG1ZhbG1DZXJ0IFZhbG1kYXRpb24gTmV0d29yazEXMBUGA1UEChMOVmfSaUNlcnQsIEluYy4xNTAzBgNVBAsTFZhbG1DZXJ0IENsYXNzIDIGUG9saWN5IFZhbG1kYXRpb24gQXV0aG9yaXR5MSEwHwYDVQQDEzhodHRwOi8vd3d3LnZhbG1jZXJ0LmNvbS8xIDAeBgkqhkiG9w0BCQEWEluZm9AdmFsaWNlcnQuY29tMB4XDTk5MDYyNjAwMTk1NFoXDTE5MDYyNjAwMTk1NFowgbsxJDAiBgNVBACzG1ZhbG1DZXJ0IFZhbG1kYXRpb24gTmV0d29yazEXMBUGA1UEChMOVmfSaUNlcnQsIEluYy4xNTAzBgNVBAsTFZhbG1DZXJ0IENsYXNzIDIGUG9saWN5IFZhbG1kYXRpb24gQXV0aG9yaXR5MSEwHwYDVQQDEzhodHRw
```

```
-----END CERTIFICATE-----
```

Do you want to continue entering root and/or intermediate certificates
{y|n}: n

You should keep a copy of the private key and the CA-signed digital certificate for future reference.

This example installs a CA certificate for client authentication for a Vserver named vs0.

```
cluster1::> security certificate install -vserver vs0 -type client-ca
```

Please enter Certificate: Press <Enter> when done

```
-----BEGIN CERTIFICATE-----
```

```
MIIDNjCCAp+gAwIBAgIQNhIilsXjOKUgodJfTncJVDANBgkqhkiG9w0BAQUFADCBzjELMAkGA1UEBhMCWkExFTATBgNVBAGTDFdlc3Rlcm4gQ2FwZTESMBAGA1UEBxMJQ2FwZSBUb3duMR0wGwYDVQQKEExRUaGF3dGUgQ29uc3VsdGluZyBjYzEoMCMYGA1UECxmFQ2VydG1maWNhdGlvbiBTZXJ2aWNlcyBEaXZpc2l1b2ljEhMB8GA1UEAxMYVGhhd3RlIFByZW1pdW0gU2VydMvYIENBMSgwJgYJKoZIhvcNAQkBFhlwcmVtaXVtLXNlcnZlc3Rlcm4gQ2FwZGUuY29tMB4XDTk2MDgwMTAwMDAwMFoXDTE5MDYyNjAwMTk1OVowgc4xCzAJBgNVBAYTAlpBMRUwEwYDVQQIEWxxZzXN0ZXJ0IENhcGUxZjAQBgNVBACz
```

```
-----END CERTIFICATE-----
```

You should keep a copy of the CA-signed digital certificate for future reference.

This example installs a CA certificate for server authentication for a Vserver named vs0. In this case, Data ONTAP acts as an SSL client.

```
cluster1::> security certificate install -vserver vs0 -type server-ca
```

Please enter Certificate: Press <Enter> when done

```
-----BEGIN CERTIFICATE-----
```

```
MIIDNjCCAp+gAwIBAgIQNhIilsXjOKUgodJfTncJVDANBgkqhkiG9w0BAQUFADCB  
zjELMAkGA1UEBhMCWkExFTATBgNVBAGTDFdlc3Rlcm4gQ2FwZTESMBAGA1UEBxMJ  
Q2FwZSBUb3duMR0wGwYDVQQKEsRUaGF3dGUgQ29uc3VsdGluZyBjYzEoMCMYGA1UE  
CxMfQ2VydGhmaWNhdGlvbiBTZXJ2aWNlcYBEaXZpc2l1vbjEhMB8GA1UEAxMYVGhh  
d3RlIFByZW1pdW0gU2VydmVyIENBMSgwJgYJKoZIhvcNAQkBFhlwcmVtaXVtLXNl  
cnZlc3Rlcm4gU29tMB4XDk2MDgwMTAwMDAwMFOxMDEwMTIzNTk1OVow  
gc4xCzAJBgNVBAYTAlpBMRUwEwYDVQQIEwxXZjJ2aWNlcYBEaXZpc2l1vbjEhMB8GA1UEAxMYVGhh  
d3RlIFByZW1pdW0gU2VydmVyIENBMSgwJgYJKoZIhvcNAQkBFhlwcmVtaXVtLXNl  
cnZlc3Rlcm4gU29tMB4XDk2MDgwMTAwMDAwMFOxMDEwMTIzNTk1OVow
```

```
-----END CERTIFICATE-----
```

You should keep a copy of the CA-signed digital certificate for future reference.

security certificate rename

Rename a certificate

Availability: This command is available to *cluster* and *Vserver* administrators at the *admin* privilege level.

Description

This command allows the user to modify the system's identifier for an installed digital certificate. It does not alter the certificate itself.

Parameters

-vserver <Vserver Name> - Vserver Name

This specifies the name of the Vserver on which the certificate exists.

-cert-name <text> - Existing Certificate Name

This specifies the current system identifier for the certificate.

-new-name <text> - New Certificate Name

This specifies the desired system identifier for the certificate. It must be unique among certificates in the Vserver.

Examples

```
cluster1::> security certificate rename -vserver vs0 -cert-name  
AAACertificateServices -new-nameAAACertServ
```

security certificate show-generated

Display ONTAP generated certificates

Availability: This command is available to *cluster* and *Vserver* administrators at the *admin* privilege level.

Description

This command displays information about the Data ONTAP generated digital certificates. Some details are displayed only when you use the command with the `-instance` parameter.

Parameters

{ [-fields <fieldname>,...]

If you specify the `-fields <fieldname>, ...` parameter, the command output also includes the specified field or fields. You can use `'-fields ?'` to display the fields to specify.

| [-instance] }

If you specify the `-instance` parameter, the command displays detailed information about all fields.

[-vserver <Vserver Name>] - Name of Vserver

Selects the Vserver whose digital certificates you want to display.

[-common-name <FQDN or Custom Common Name>] - FQDN or Custom Common Name

Selects the certificates that match this parameter value.

[-serial <text>] - Serial Number of Certificate

Selects the certificates that match this parameter value.

[-ca <text>] - Certificate Authority

Selects the certificates that match this parameter value.

[-type <type of certificate>] - Type of Certificate

Selects the certificates that match this parameter value.

[-subtype <kmip-cert>] - (DEPRECATED)-Certificate Subtype



This parameter has been deprecated in ONTAP 9.6 and may be removed in a future release of Data ONTAP.

Selects the certificate subtype that matches the specified value. The valid values are as follows:

- `kmip-cert` - this is a Key Management Interoperability Protocol (KMIP) certificate

[-cert-name <text>] - Unique Certificate Name

This specifies the system's internal identifier for the certificate. It is unique within a Vserver.

[-size <size of requested certificate in bits>] - Size of Requested Certificate in Bits

Selects the certificates that match this parameter value.

[-start <Date>] - Certificate Start Date

Selects the certificates that match this parameter value.

[-expiration <Date>] - Certificate Expiration Date

Selects the certificates that match this parameter value.

[-public-cert <certificate>] - Public Key Certificate

Selects the certificates that match this parameter value.

[-country <text>] - Country Name

Selects the certificates that match this parameter value.

[-state <text>] - State or Province Name

Selects the certificates that match this parameter value.

[-locality <text>] - Locality Name

Selects the certificates that match this parameter value.

[-organization <text>] - Organization Name

Selects the certificates that match this parameter value.

[-unit <text>] - Organization Unit

Selects the certificates that match this parameter value.

[-email-addr <mail address>] - Contact Administrator's Email Address

Selects the certificates that match this parameter value.

[-protocol <protocol>] - Protocol

Selects the certificates that match this parameter value.

[-hash-function <hashing function>] - Hashing Function

Selects the certificates that match this parameter value.

[-self-signed {true|false}] - Self-Signed Certificate

Selects the certificates that match this parameter value.

Examples

The examples below display information about Data ONTAP generated digital certificates.

```
cluster1::> security certificate show-generated
```

Vserver	Serial Number	Certificate Name	Type
vs0	4F4E4D7B	www.example.com	server

Certificate Authority: www.example.com
Expiration Date: Thu Feb 28 16:08:28 2013

```
cluster1::> security certificate show-generated -instance
```

```
          Vserver: vs0
          Certificate Name: www.example.com
          FQDN or Custom Common Name: www.example.com
          Serial Number of Certificate: 4F4E4D7B
          Certificate Authority: www.example.com
          Type of Certificate: server
          Size of Requested Certificate(bits): 2048
          Certificate Start Date: Fri Apr 30 14:14:46 2010
          Certificate Expiration Date: Sat Apr 30 14:14:46 2011
          Public Key Certificate: -----BEGIN CERTIFICATE-----

MIIDfTCCAmWgAwIBAwIBADANBgkqhkiG9w0BAQsFADBgMRQwEgYDVQQDEwtsYWlu
YWJjLmNvbTEuMCA1UEBhMCVVMxCTAHBgNVBAgTQDEJMAcGA1UEBxMAMQkwBwYD
VQKKEwAxCTAHBgNVBAStADEPMA0GCSqGSIb3DQEJARYAMB4XDTEwMDQzMDE4MTQ0
BgNVHQ8BAf8EBAMCAQYwHQYDVR0OBBYEFcVg7dYGe51akeE14ecaCdL+LOAxUMA0G
CSqGSIb3DQEBCwUAA4IBAQBjLE51pkDY3ZpsSrQeMOoWLteIR+1H0wKZOM1Bhy6Q
+gsE3XEtnN07AE4npjIT0eVP0nI9QIJAbP0uPKaCGAVBSBMoM2mOwbfswI7aJoEh
+XuEoNr0GOz+mltnfhgvl1fT6Ms+xzd3LGZYQTworus2
          -----END CERTIFICATE-----

          Country Name (2 letter code): US
          State or Province Name (full name): California
          Locality Name (e.g. city): Sunnyvale
          Organization Name (e.g. company): example
          Organization Unit (e.g. section): IT
          Email Address (Contact Name): web@example.com
          Protocol: SSL
          Hashing Function: SHA256
```

security certificate show-truststore

Display default truststore certificates

Availability: This command is available to *cluster* and *Vserver* administrators at the *admin* privilege level.

Description

This command displays information about the default CA certificates that come pre-installed with Data ONTAP. Some details are displayed only when you use the command with the `-instance` parameter.

Parameters

{ [-fields <fieldname>,...]

If you specify the `-fields <fieldname>, ...` parameter, the command output also includes the specified field or fields. You can use `'-fields ?'` to display the fields to specify.

| [-instance] }

If you specify the `-instance` parameter, the command displays detailed information about all fields.

[-vserver <Vserver Name>] - Name of Vserver

Selects the Vserver whose digital certificates you want to display.

[-common-name <FQDN or Custom Common Name>] - FQDN or Custom Common Name

Selects the certificates that match this parameter value.

[-serial <text>] - Serial Number of Certificate

Selects the certificates that match this parameter value.

[-ca <text>] - Certificate Authority

Selects the certificates that match this parameter value.

[-type <type of certificate>] - Type of Certificate

Selects the certificates that match this parameter value.

[-subtype <kmip-cert>] - (DEPRECATED)-Certificate Subtype



This parameter has been deprecated in ONTAP 9.6 and may be removed in a future release of Data ONTAP.

Selects the certificate subtype that matches the specified value. The valid values are as follows:

- `kmip-cert` - this is a Key Management Interoperability Protocol (KMIP) certificate

[-cert-name <text>] - Unique Certificate Name

This specifies the system's internal identifier for the certificate. It is unique within a Vserver.

[-size <size of requested certificate in bits>] - Size of Requested Certificate in Bits

Selects the certificates that match this parameter value.

[-start <Date>] - Certificate Start Date

Selects the certificates that match this parameter value.

[-expiration <Date>] - Certificate Expiration Date

Selects the certificates that match this parameter value.

[-public-cert <certificate>] - Public Key Certificate

Selects the certificates that match this parameter value.

[-country <text>] - Country Name

Selects the certificates that match this parameter value.

[-state <text>] - State or Province Name

Selects the certificates that match this parameter value.

[-locality <text>] - Locality Name

Selects the certificates that match this parameter value.

[-organization <text>] - Organization Name

Selects the certificates that match this parameter value.

[-unit <text>] - Organization Unit

Selects the certificates that match this parameter value.

[-email-addr <mail address>] - Contact Administrator's Email Address

Selects the certificates that match this parameter value.

[-protocol <protocol>] - Protocol

Selects the certificates that match this parameter value.

[-hash-function <hashing function>] - Hashing Function

Selects the certificates that match this parameter value.

[-self-signed {true|false}] - Self-Signed Certificate

Selects the certificates that match this parameter value.

Examples

The examples below display information about the pre-installed truststore digital certificates.

```
cluster1::> security certificate show-truststore
```

Vserver	Serial Number	Certificate Name	Type
vs0	4F4E4D7B	www.example.com	server-ca
	Certificate Authority: www.example.com		
	Expiration Date: Thu Feb 28 16:08:28 2013		

```
cluster1::> security certificate show-truststore -instance
```

```
          Vserver: vs0
          Certificate Name: www.example.com
          FQDN or Custom Common Name: www.example.com
          Serial Number of Certificate: 4F4E4D7B
          Certificate Authority: www.example.com
          Type of Certificate: server-ca
          Size of Requested Certificate(bits): 2048
          Certificate Start Date: Fri Apr 30 14:14:46 2010
          Certificate Expiration Date: Sat Apr 30 14:14:46 2011
          Public Key Certificate: -----BEGIN CERTIFICATE-----

MIIDfTCCAmWgAwIBAwIBADANBgkqhkiG9w0BAQsFADBgMRQwEgYDVQQDEwtsYWlu
YWJjLmNvbTEuMCAwLWgkGA1UEBhMCVVMxCTAHBgNVBAgTADUuMCAwLWgkGA1UEBxMAMQkwBwYD
VQKKEwAxCTAHBgNVBAStADEPMA0GCSqGSIb3DQEJARYAMB4XDTEwMDQzMDE4MTQ0
BgNVHQ8BAf8EBAMCAQYwHQYDVR0OBBYEFcVg7dYGe51akE14ecaCdL+LOAxUMA0G
CSqGSIb3DQEBCwUAA4IBAQBj1E51pkDY3ZpsSrQeMOoWLteIR+1H0wKZOM1Bhy6Q
+gsE3XEtnN07AE4npjIT0eVP0nI9QIJAbP0uPKaCGAVBSBMoM2mOwbfswI7aJoEh
+XuEoNr0GOz+mltnfhgvl1fT6Ms+xzd3LGZYQTworus2
          -----END CERTIFICATE-----

          Country Name (2 letter code): US
          State or Province Name (full name): California
          Locality Name (e.g. city): Sunnyvale
          Organization Name (e.g. company): example
          Organization Unit (e.g. section): IT
          Email Address (Contact Name): web@example.com
          Protocol: SSL
          Hashing Function: SHA256
```

security certificate show-user-installed

Display user installed certificates

Availability: This command is available to *cluster* and *Vserver* administrators at the *admin* privilege level.

Description

This command displays information about the user installed digital certificates. Some details are displayed only when you use the command with the `-instance` parameter. In systems upgraded to Data ONTAP 9.4 or later, existing Data ONTAP generated certificates will also be shown as part of this command.

Parameters

{ [-fields <fieldname>,...]

If you specify the `-fields <fieldname>`, ... parameter, the command output also includes the specified field or fields. You can use `'-fields ?'` to display the fields to specify.

| [-instance] }

If you specify the `-instance` parameter, the command displays detailed information about all fields.

[-vserver <Vserver Name>] - Name of Vserver

Selects the Vserver whose digital certificates you want to display.

[-common-name <FQDN or Custom Common Name>] - FQDN or Custom Common Name

Selects the certificates that match this parameter value.

[-serial <text>] - Serial Number of Certificate

Selects the certificates that match this parameter value.

[-ca <text>] - Certificate Authority

Selects the certificates that match this parameter value.

[-type <type of certificate>] - Type of Certificate

Selects the certificates that match this parameter value.

[-subtype <kmip-cert>] - (DEPRECATED)-Certificate Subtype



This parameter has been deprecated in ONTAP 9.6 and may be removed in a future release of Data ONTAP.

Selects the certificate subtype that matches the specified value. The valid values are as follows:

- `kmip-cert` - this is a Key Management Interoperability Protocol (KMIP) certificate

[-cert-name <text>] - Unique Certificate Name

This specifies the system's internal identifier for the certificate. It is unique within a Vserver.

[-size <size of requested certificate in bits>] - Size of Requested Certificate in Bits

Selects the certificates that match this parameter value.

[-start <Date>] - Certificate Start Date

Selects the certificates that match this parameter value.

[-expiration <Date>] - Certificate Expiration Date

Selects the certificates that match this parameter value.

[-public-cert <certificate>] - Public Key Certificate

Selects the certificates that match this parameter value.

[-country <text>] - Country Name

Selects the certificates that match this parameter value.

[-state <text>] - State or Province Name

Selects the certificates that match this parameter value.

[-locality <text>] - Locality Name

Selects the certificates that match this parameter value.

[-organization <text>] - Organization Name

Selects the certificates that match this parameter value.

[-unit <text>] - Organization Unit

Selects the certificates that match this parameter value.

[-email-addr <mail address>] - Contact Administrator's Email Address

Selects the certificates that match this parameter value.

[-protocol <protocol>] - Protocol

Selects the certificates that match this parameter value.

[-hash-function <hashing function>] - Hashing Function

Selects the certificates that match this parameter value.

[-self-signed {true|false}] - Self-Signed Certificate

Selects the certificates that match this parameter value.

Examples

The examples below display information about user installed digital certificates.

```
cluster1::> security certificate show-user-installed
```

Vserver	Serial Number	Certificate Name	Type
vs0	4F4E4D7B	www.example.com	server

Certificate Authority: www.example.com
Expiration Date: Thu Feb 28 16:08:28 2013

```
cluster1::> security certificate show-user-installed -instance
```

```
      Vserver: vs0
      Certificate Name: www.example.com
      FQDN or Custom Common Name: www.example.com
      Serial Number of Certificate: 4F4E4D7B
      Certificate Authority: www.example.com
      Type of Certificate: server
      Size of Requested Certificate(bits): 2048
      Certificate Start Date: Fri Apr 30 14:14:46 2010
      Certificate Expiration Date: Sat Apr 30 14:14:46 2011
      Public Key Certificate: -----BEGIN CERTIFICATE-----

MIIDfTCCAmWgAwIBAwIBADANBgkqhkiG9w0BAQsFADBgMRQwEgYDVQQDEwtsYWlu
YWJjLnNvbTEuMCAkGA1UEBhMCVVMxCTAHBgNVBAgTADAEJMAcGA1UEBxMAMQkwBwYD
VQKKEwAxCTAHBgNVBAStADEPMA0GCSqGSIb3DQEJARYAMB4XDTEwMDQzMDE4MTQ0
BgNVHQ8BAf8EBAMCAQYwHQYDVR0OBBYEFcVg7dYGe51akeE14ecaCdL+LOAxUMA0G
CSqGSIb3DQEBCwUAA4IBAQBjLE51pkDY3ZpsSrQeMOoWlTeIR+1H0wKZOM1Bhy6Q
+gsE3XEtnN07AE4npjIT0eVP0nI9QIJAbP0uPKaCGAVBSBMoM2mOwbfswI7aJoEh
+XuEoNr0GOz+mltnfhgvl1fT6Ms+xzd3LGZYQTworus2
      -----END CERTIFICATE-----

      Country Name (2 letter code): US
      State or Province Name (full name): California
      Locality Name (e.g. city): Sunnyvale
      Organization Name (e.g. company): example
      Organization Unit (e.g. section): IT
      Email Address (Contact Name): web@example.com
      Protocol: SSL
      Hashing Function: SHA256
```

security certificate show

Display Installed Digital Certificates

Availability: This command is available to *cluster* and *Vserver* administrators at the *admin* privilege level.

Description

This command displays information about the installed digital certificates. Some details are displayed only when you use the command with the `-instance` parameter.

Parameters

{ [-fields <fieldname>,...]

If you specify the `-fields <fieldname>, ...` parameter, the command output also includes the specified field or fields. You can use `'-fields ?'` to display the fields to specify.

| [-instance] }

If you specify the `-instance` parameter, the command displays detailed information about all fields.

[-vserver <Vserver Name>] - Name of Vserver

Selects the Vserver whose digital certificates you want to display.

[-common-name <FQDN or Custom Common Name>] - FQDN or Custom Common Name

Selects the certificates that match this parameter value.

[-serial <text>] - Serial Number of Certificate

Selects the certificates that match this parameter value.

[-ca <text>] - Certificate Authority

Selects the certificates that match this parameter value.

[-type <type of certificate>] - Type of Certificate

Selects the certificates that match this parameter value.

[-subtype <kmip-cert>] - (DEPRECATED)-Certificate Subtype



This parameter has been deprecated in ONTAP 9.6 and may be removed in a future release of Data ONTAP.

Selects the certificate subtype that matches the specified value. The valid values are as follows:

- `kmip-cert` - this is a Key Management Interoperability Protocol (KMIP) certificate

[-cert-name <text>] - Unique Certificate Name

This specifies the system's internal identifier for the certificate. It is unique within a Vserver.

[-size <size of requested certificate in bits>] - Size of Requested Certificate in Bits

Selects the certificates that match this parameter value.

[-start <Date>] - Certificate Start Date

Selects the certificates that match this parameter value.

[-expiration <Date>] - Certificate Expiration Date

Selects the certificates that match this parameter value.

[-public-cert <certificate>] - Public Key Certificate

Selects the certificates that match this parameter value.

[-country <text>] - Country Name

Selects the certificates that match this parameter value.

[-state <text>] - State or Province Name

Selects the certificates that match this parameter value.

[-locality <text>] - Locality Name

Selects the certificates that match this parameter value.

[-organization <text>] - Organization Name

Selects the certificates that match this parameter value.

[-unit <text>] - Organization Unit

Selects the certificates that match this parameter value.

[-email-addr <mail address>] - Contact Administrator's Email Address

Selects the certificates that match this parameter value.

[-protocol <protocol>] - Protocol

Selects the certificates that match this parameter value.

[-hash-function <hashing function>] - Hashing Function

Selects the certificates that match this parameter value.

[-self-signed {true|false}] - Self-Signed Certificate

Selects the certificates that match this parameter value.

Examples

The examples below display information about digital certificates.

```
cluster1::> security certificate show
```

Vserver	Serial Number	Certificate Name	Type
---------	---------------	------------------	------

vs0	4F4E4D7B	www.example.com	
-----	----------	-----------------	--

server

Certificate Authority: www.example.com

Expiration Date: Thu Feb 28 16:08:28 2013


```

cluster1::> security certificate show -instance
                Vserver: vs0
                Certificate Name: www.example.com
                FQDN or Custom Common Name: www.example.com
                Serial Number of Certificate: 4F4E4D7B
                Certificate Authority: www.example.com
                Type of Certificate: server
                Size of Requested Certificate(bits): 2048
                Certificate Start Date: Fri Apr 30 14:14:46 2010
                Certificate Expiration Date: Sat Apr 30 14:14:46 2011
                Public Key Certificate: -----BEGIN CERTIFICATE-----

MIIDfTCCAmWgAwIBAwIBADANBgkqhkiG9w0BAQsFADBgMRQwEgYDVQQDEwtsYWlu
YWJjLmNvbTELMakGA1UEBhMCVVMxCTAHBgNVBAgTADAJMAcGA1UEBxMAMQkwBwYD
VQKKEwAxCTAHBgNVBAStADEPMA0GCSqGSIb3DQEJARYAMB4XDTEwMDQzMDE4MTQ0
BgNVHQ8BAf8EBAMCAQYwHQYDVR0OBBYEF7dYGe51akE14ecaCdL+LOAxUMA0G
CSqGSIb3DQEBCwUAA4IBAQBj1E51pkDY3ZpsSrQeMOoWLteIR+1H0wKZOM1Bhy6Q
+gsE3XEtnN07AE4npjIT0eVP0nI9QIJAbP0uPKaCGAVBSBMoM2mOwbfswI7aJoEh
+XuEoNr0GOz+mltnfhgvl1fT6Ms+xzd3LGZYQTworus2
                -----END CERTIFICATE-----

                Country Name (2 letter code): US
                State or Province Name (full name): California
                Locality Name (e.g. city): Sunnyvale
                Organization Name (e.g. company): example
                Organization Unit (e.g. section): IT
                Email Address (Contact Name): web@example.com
                Protocol: SSL
                Hashing Function: SHA256

```

security certificate sign

Sign a Digital Certificate using Self-Signed Root CA

Availability: This command is available to *cluster* and *Vserver* administrators at the *admin* privilege level.

Description

This command signs a digital certificate signing request and generates a certificate using a Self-Signed Root CA certificate in either PEM or PKCS12 format. You can use the [security certificate generate-csr](#) command to generate a digital certificate signing request.

Parameters

-vserver <Vserver Name> - Name of Vserver

This specifies the name of the Vserver on which the signed certificate will exist.

-ca <text> - Certificate Authority to Sign

This specifies the name of the Certificate Authority that will sign the certificate.

-ca-serial <text> - Serial Number of CA Certificate

This specifies the serial number of the Certificate Authority that will sign the certificate.

[-expire-days <integer>] - Number of Days until Expiration

This specifies the number of days until the signed certificate expires. The default value is 365 days. Possible values are between *1* and *3652*.

[-format <certificate format>] - Certificate Format

This specifies the format of signed certificate. The default value is PEM. Possible values include *PEM* and *PKCS12*.

[-destination {(ftp|http)://(hostname|IPv4 Address|['IPv6 Address'])...}] - Where to Send File

This specifies the destination to upload the signed certificate. This option can only be used when the format is PKCS12.

[-hash-function <hashing function>] - Hashing Function

This specifies the cryptographic hashing function for the self-signed certificate. The default value is SHA256. Possible values include *SHA1*, *SHA256* and *MD5*.

Examples

This example signs a digital certificate for a Vserver named vs0 using a Certificate Authority certificate that has a ca of *www.ca.com* and a ca-serial of 4F4EB629 in PEM format using the SHA256 hashing function.

```
cluster1::> security certificate sign -vserver vs0 -ca www.ca.com -ca
-serial 4F4EB629 -expire-days 36 -format PEM -hash-function SHA256
```

Please enter Certificate Signing Request(CSR): Press <Enter> when done

```
-----BEGIN CERTIFICATE REQUEST-----
```

```
MIIBGjCBxQIBADBGMRQwEgYDVQQDEwtleGFtcGxlLmNvbTElMAkGA1UEBhMCVVMx
CTAHBgNVBAGTADEJMAcGA1UEBxMAMQkwBwYDVQQKEwAxCTAHBgNVBAsTADEPMA0G
CSqGSIB3DQEJARYAMFwwDQYJKoZIhvcNAQEBBQADSwAwSAJBAPXFanNoJApTlnzS
xOcxixqImRRGZCR7tVmTYyqPSuTvfVhVtwDJbmXuj6U3a1woUsb13wfEvQnHVFNci
2ninsJ8CAwEAAaAAMA0GCSqGSIB3DQEBCwUAA0EA6EagLfso5+4g+ejiRKKTUPQO
UqOUEoKuvxhOvPC2w7b//fNSFsFHvXloqEOhYECn/NX9h8mbphCoM5YZ40fnKw==
```

```
-----END CERTIFICATE REQUEST-----
```

Signed Certificate: :

```
-----BEGIN CERTIFICATE-----
```

```
MIICwDCCAaigAwIBAgIET1oskDANBgkqhkiG9w0BAQsFADBdMREwDwYDVQQDEwh2
czAuY2VydDELMAkGA1UEBhMCVVMxCTAHBgNVBAGTADEJMAcGA1UEBxMAMQkwBwYD
VQQKEwAxCTAHBgNVBAsTADEPMA0GCSqGSIB3DQEJARYAMB4XDTEyMDMwOTE2MTUx
M1oXDTEyMDQxNDE2MTUxM1owYDEUMBIGAlUEAxMLZXhhbXBsZS5jb20xCzAJBgNV
BAYTA1VTMqkwBwYDVQQIEwAxCTAHBgNVBACjTADEJMAcGA1UEChMAMQkwBwYDVQQL
EwAxDzANBgkqhkiG9w0BCQEWADBCMA0GCSqGSIB3DQEBAQUAA0sAMEgCQQD1xWpz
```

```
-----END CERTIFICATE-----
```

This example signs and exports a digital certificate to destination <ftp://10.98.1.1//u/sam/sign.pfx> for a Vserver named vs0 using a Certificate Authority certificate that expires in 36 days and has a ca value of *www.ca.com* and a ca-serial value of 4F4EB629 in PKCS12 format by the MD5 hashing function.

```
cluster1::> security certificate sign -vserver vs0 -ca www.ca.com -ca
-serial 4F4EB629
-expire-days 36 -format PKCS12 -destination
ftp://10.98.1.1//u/sam/sign.pfx -hash-function MD5
```

Please enter Certificate Signing Request (CSR): Press <Enter> when done

-----BEGIN CERTIFICATE REQUEST-----

```
MIIBGjCBxQIBADBGMRQwEgYDVQQDEwtleGFtcGxlLmNvbTELMakGA1UEBhMVCVVMx
CTAHBgNVBAGTADEJMAcGA1UEBxMAMQkwBwYDVQQKEwAxCTAHBgNVBAsTADEPMA0G
CSqGSIB3DQEJARYAMFwwDQYJKoZIhvcNAQEBBQADSwAwSAJBAPXFanNoJApTlnzS
xOcxixqImRRGZCR7tVmTYyqPSuTvfVhVtwDJbmXuj6U3alwoUsb13wfEvQnHVFNCi
2ninsJ8CAwEAAaAAMA0GCSqGSIB3DQEBcWUAA0EA6EagLfso5+4g+ejiRKKKTUPQO
UqOUeOkuvxhOvPC2w7b//fNSFsFHvXloqEOhYECn/NX9h8mbphCoM5YZ4OfnKw==
```

-----END CERTIFICATE REQUEST-----

Signed Certificate: :

-----BEGIN CERTIFICATE-----

```
MIICwDCCAaigAwIBAgIET1ot8jANBgkqhkiG9w0BAQsFADBdMREwDwYDVQQDEwh2
czAuY2VydDELMAkGA1UEBhMVCVVMxCTAHBgNVBAGTADEJMAcGA1UEBxMAMQkwBwYD
VQQKEwAxCTAHBgNVBAsTADEPMA0GCSqGSIB3DQEJARYAMB4XDTEyMDMwOTE2MjEw
Nl0XDTEyMDQxNDE2MjEwNl0wYDEUMBIGA1UEAxMLZXhhbXBsZS5jb20xCzAJBgNV
BAYTA1VTMkQkwBwYDVQQIEwAxCTAHBgNVBACTADEJMAcGA1UEChMAMQkwBwYDVQQQL
EwAxDzANBgkqhkiG9w0BCQEWADBCMA0GCSqGSIB3DQEBAAQUAA0sAMEgCQQD1xWpz
oarXHSyDzv3T5QIxBGRJ0ActgdjJuqtuAdmnKvKfLS1o4C90
```

-----END CERTIFICATE-----

Please enter Private Key: Press <Enter> when done

-----BEGIN RSA PRIVATE KEY-----

```
MIIBOwIBAAJBAPXFanNoJApTlnzSxOcxixqImRRGZCR7tVmTYyqPSuTvfVhVtwDJb
mXuj6U3alwoUsb13wfEvQnHVFNCi2ninsJ8CAwEAAQJAWt2AO+bW3FKezEuIrQlu
KoMyRYK455wtMk8BrOyJfhYsB20B28eifjJvRwDToBEav99M7cEzgPv+p5kaZTTM
gQIhAPsp+j1hrUXSRj979LIJJY0sNez397i7ViFXWQScx/ehAiEA+oDbOooWlVvu
xj4aitxVBu6ByVckYU8LbsfeRNsZwD8CIQCbZ1/ENvmlJ/P7N9Exj2NctEYxd0Q5
cwBZ5NfZeMBpwQIhAPk0KWQSLadGfsKO077itF+h9FGFNHbtuNTrVq4vPW3nAiAA
peMBQgEv28y2r8D4dkYzxcXmjzJluUSZS9c/ws6fA==
```

-----END RSA PRIVATE KEY-----

Please enter a password for pkcs12 file:

Please enter it again:

Enter User for Destination URI: sam

Enter Password:

Related Links

- [security certificate generate-csr](#)

security certificate ca-issued revoke

Revoke a Digital Certificate

Availability: This command is available to *cluster* and *Vserver* administrators at the *admin* privilege level.

Description

This command revokes a digital certificate signed by a Self-Signed Root CA.

Parameters

-vserver <Vserver Name> - Vserver

This specifies the name of the Vserver on which the certificate is stored.

-serial <text> - Serial Number of Certificate

This specifies the serial number of the certificate.

-ca <text> - Certificate Authority

This specifies the name of the Certificate Authority whose certificate will be revoked.

-ca-serial <text> - Serial Number of CA Certificate

This specifies the serial number of Certificate Authority.

[-common-name <FQDN or Custom Common Name>] - FQDN or Custom Common Name

This specifies a fully qualified domain name (FQDN) or custom common name or the name of a person. This field is optional if ca-serial is specified.

Examples

This example revokes a signed digital certificate for a Vserver named vs0 with serial as 4F5A2DF2 for a Certificate Authority certificate that has a ca of *www.ca.com* and a ca-serial of 4F4EB629.

```
cluster1::> security certificate ca-issued revoke -vserver vs0 -serial
4F5A2DF2 -ca www.ca.com -ca-serial 4F4EB629
```

security certificate ca-issued show

Display CA-Issued Digital Certificates

Availability: This command is available to *cluster* and *Vserver* administrators at the *admin* privilege level.

Description

This command displays the following information about the digital certificates issued by the self-signed root-ca:

- Vserver
- Serial number of certificate

- FQDN or custom common name or the name of a person
- Serial number of CA certificate
- Status (`active`, `revoked`)
- Certificate Authority
- Expiration date
- Revocation date

To display more details, run the command with the `-instance` parameter. This will add the following information:

- Country name
- State or province name
- Locality name
- Organization name
- Organization unit
- Contact administrator's email address

Parameters

{ [-fields <fieldname>,...]

If you specify the `-fields <fieldname>`, ... parameter, the command output also includes the specified field or fields. You can use `'-fields ?'` to display the fields to specify.

| [-instance] }

If you specify the `-instance` parameter, the command displays detailed information about all fields.

[-vserver <Vserver Name>] - Vserver

Selects the certificates that match this parameter value.

[-serial <text>] - Serial Number of Certificate

Selects the certificates that match this parameter value.

[-ca <text>] - Certificate Authority

Selects the certificates that match this parameter value.

[-ca-serial <text>] - Serial Number of CA Certificate

Selects the certificates that match this parameter value.

[-common-name <FQDN or Custom Common Name>] - FQDN or Custom Common Name

Selects the certificates that match this parameter value.

[-status <status of certificate>] - Status of Certificate

Selects the certificates that match this parameter value. Possible values include `active` and `revoked`.

[-expiration <Date>] - Certificate Expiration Date

Selects the certificates that match this parameter value.

[-revocation <Date>] - Certificate Revocation Date

Selects the certificates that match this parameter value.

[-country <text>] - Country Name (2 letter code)

Selects the certificates that match this parameter value.

[-state <text>] - State or Province Name (full name)

Selects the certificates that match this parameter value.

[-locality <text>] - Locality Name (e.g. city)

Selects the certificates that match this parameter value.

[-organization <text>] - Organization Name (e.g. company)

Selects the certificates that match this parameter value.

[-unit <text>] - Organization Unit (e.g. section)

Selects the certificates that match this parameter value.

[-email-addr <mail address>] - Email Address (Contact Name)

Selects the certificates that match this parameter value.

Examples

The examples below display information about CA issued digital certificates.

```
cluster1::> security certificate ca-issued show
Serial Number of
Vserver      Serial Number  Common Name          CA's Certificate
Status
-----
-----
vs0          4F5A2C90       example.com          4F4EB629
active
  Certificate Authority: vs0.cert
  Expiration Date: Sat Apr 14 16:15:13 2012
  Revocation Date: -

vs0          4F5A2DF2       example.com          4F4EB629
revoked
  Certificate Authority: vs0.cert
  Expiration Date: Sat Apr 14 16:21:06 2012
  Revocation Date: Fri Mar 09 17:08:30 2012

2 entries were displayed.
```

```
cluster1::> security certificate ca-issued show -instance
Vserver: vs0
    Serial Number of Certificate: 4F5A2C90
    Certificate Authority: vs0.cert
Serial Number of CA Certificate: 4F4EB629
    FQDN or Custom Common Name: example.com
    Status of Certificate: active
    Certificate Expiration Date: Sat Apr 14 16:15:13 2012
    Certificate Revocation Date: -
    Country Name (2 letter code): US
State or Province Name (full name): California
    Locality Name (e.g. city): Sunnyvale
    Organization Name (e.g. company): example
    Organization Unit (e.g. section): IT
    Email Address (Contact Name): web@example.com
```

security certificate truststore show

Display default truststore certificates

Availability: This command is available to *cluster* and *Vserver* administrators at the *admin* privilege level.

Description

This command displays information about the default CA certificates that come pre-installed with Data ONTAP. Some details are displayed only when you use the command with the `-instance` parameter.

Parameters

{ [-fields <fieldname>,...]

If you specify the `-fields <fieldname>, ...` parameter, the command output also includes the specified field or fields. You can use `'-fields ?'` to display the fields to specify.

| [-instance] }

If you specify the `-instance` parameter, the command displays detailed information about all fields.

[-vserver <Vserver Name>] - Name of Vserver

Selects the Vserver whose digital certificates you want to display.

[-common-name <FQDN or Custom Common Name>] - FQDN or Custom Common Name

Selects the certificates that match this parameter value.

[-serial <text>] - Serial Number of Certificate

Selects the certificates that match this parameter value.

[-ca <text>] - Certificate Authority

Selects the certificates that match this parameter value.

[-type <type of certificate>] - Type of Certificate

Selects the certificates that match this parameter value.

[-subtype <kmip-cert>] - (DEPRECATED)-Certificate Subtype

Selects the certificate subtype that matches the specified value. The valid values are as follows:

- *kmip-cert* - this is a Key Management Interoperability Protocol (KMIP) certificate

[-cert-name <text>] - Unique Certificate Name

This specifies the system's internal identifier for the certificate. It is unique within a Vserver.

[-size <size of requested certificate in bits>] - Size of Requested Certificate in Bits

Selects the certificates that match this parameter value.

[-start <Date>] - Certificate Start Date

Selects the certificates that match this parameter value.

[-expiration <Date>] - Certificate Expiration Date

Selects the certificates that match this parameter value.

[-public-cert <certificate>] - Public Key Certificate

Selects the certificates that match this parameter value.

[-country <text>] - Country Name

Selects the certificates that match this parameter value.

[-state <text>] - State or Province Name

Selects the certificates that match this parameter value.

[-locality <text>] - Locality Name

Selects the certificates that match this parameter value.

[-organization <text>] - Organization Name

Selects the certificates that match this parameter value.

[-unit <text>] - Organization Unit

Selects the certificates that match this parameter value.

[-email-addr <mail address>] - Contact Administrator's Email Address

Selects the certificates that match this parameter value.

[-protocol <protocol>] - Protocol

Selects the certificates that match this parameter value.

[-hash-function <hashing function>] - Hashing Function

Selects the certificates that match this parameter value.

[`-self-signed {true|false}`] - Self-Signed Certificate

Selects the certificates that match this parameter value.

Examples

The examples below display information about the pre-installed truststore digital certificates.

```
cluster1::> security certificate truststore show
```

Vserver	Serial Number	Certificate Name	Type
vs0	4F4E4D7B	www.example.com	server-ca
	Certificate Authority:	www.example.com	
	Expiration Date:	Thu Feb 28 16:08:28 2013	

```

cluster1::> security certificate truststore show -instance
                Vserver: vs0
                Certificate Name: www.example.com
                FQDN or Custom Common Name: www.example.com
                Serial Number of Certificate: 4F4E4D7B
                Certificate Authority: www.example.com
                Type of Certificate: server-ca
                Size of Requested Certificate(bits): 2048
                Certificate Start Date: Fri Apr 30 14:14:46 2010
                Certificate Expiration Date: Sat Apr 30 14:14:46 2011
                Public Key Certificate: -----BEGIN CERTIFICATE-----

MIIDfTCCAmWgAwIBAwIBADANBgkqhkiG9w0BAQsFADBgMRQwEgYDVQQDEwtsYWlu
YWJjLmNvbTELMakGAlUEBhMCVVMxCTAHBgNVBAgTADAJMAcGA1UEBxMAMQkwBwYD
VQKKEwAxCTAHBgNVBAStADEPMA0GCSqGSIb3DQEJARYAMB4XDTEwMDQzMDE4MTQ0
BgNVHQ8BAf8EBAMCAQYwHQYDVR0OBBYEFcVG7dYGe51akE14ecaCdL+LOAxUMA0G
CSqGSIb3DQEBCwUAA4IBAQBj1E51pkDY3ZpsSrQeMOoWLteIR+1H0wKZOM1Bhy6Q
+gsE3XEtnN07AE4npjIT0eVP0nI9QIJAbP0uPKaCGAVBSBMoM2mOwbfswI7aJoEh
+XuEoNr0GOz+mltnfhgvl1fT6Ms+xzd3LGZYQTworus2
                -----END CERTIFICATE-----

                Country Name (2 letter code): US
                State or Province Name (full name): California
                Locality Name (e.g. city): Sunnyvale
                Organization Name (e.g. company): example
                Organization Unit (e.g. section): IT
                Email Address (Contact Name): web@example.com
                Protocol: SSL
                Hashing Function: SHA256

```

Copyright information

Copyright © 2024 NetApp, Inc. All Rights Reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means—graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system—without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

LIMITED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (b)(3) of the Rights in Technical Data -Noncommercial Items at DFARS 252.227-7013 (FEB 2014) and FAR 52.227-19 (DEC 2007).

Data contained herein pertains to a commercial product and/or commercial service (as defined in FAR 2.101) and is proprietary to NetApp, Inc. All NetApp technical data and computer software provided under this Agreement is commercial in nature and developed solely at private expense. The U.S. Government has a non-exclusive, non-transferrable, nonsublicensable, worldwide, limited irrevocable license to use the Data only in connection with and in support of the U.S. Government contract under which the Data was delivered. Except as provided herein, the Data may not be used, disclosed, reproduced, modified, performed, or displayed without the prior written approval of NetApp, Inc. United States Government license rights for the Department of Defense are limited to those rights identified in DFARS clause 252.227-7015(b) (FEB 2014).

Trademark information

NETAPP, the NETAPP logo, and the marks listed at <http://www.netapp.com/TM> are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.