



## **Manage NFS services**

### **ONTAP 9.6 REST API reference**

NetApp  
August 29, 2024

This PDF was generated from [https://docs.netapp.com/us-en/ontap-restapi-96/ontap/protocols\\_nfs\\_services\\_endpoint\\_overview.html](https://docs.netapp.com/us-en/ontap-restapi-96/ontap/protocols_nfs_services_endpoint_overview.html) on August 29, 2024. Always check docs.netapp.com for the latest.

# Table of Contents

- Manage NFS services ..... 1
  - Protocols NFS services endpoint overview ..... 1
  - Retrieve NFS configuration for SVMs ..... 2
  - Create the NFS configuration for an SVM ..... 10
  - Delete the NFS configuration for an SVM ..... 19
  - Retrieve the NFS configuration for an SVM ..... 21
  - Update the NFS configuration for an SVM ..... 27

# Manage NFS services

## Protocols NFS services endpoint overview

### Retrieving an NFS configuration

```
# The API:
GET /api/protocols/nfs/services

# The call:
curl -X GET "https://<mgmt-ip>/api/protocols/nfs/services"
```

### Creating an NFS configuration for an SVM

```
# The API:
POST /api/protocols/nfs/services

# The call:
curl -d "@test_nfs_post.txt" -X POST "https://<mgmt-ip>/api/protocols/nfs/services"
test_nfs_post.txt (body) :
{
  "svm": {
    "uuid": "1cd8a442-86d1-11e0-ae1c-123478563412"
  },
  "protocol": {
    "v4_id_domain": "nfs-nsr-w01.rtp.netapp.com"
  },
  "vstorage_enabled": "true"
}
```

### Updating an NFS configuration for an SVM

```
# The API:
PATCH /api/protocols/nfs/services/{svm.uuid}

# The call:
curl -d "@test_nfs_patch.txt" -X PATCH "https://<mgmt-
ip>/api/protocols/nfs/services/4a415601-548c-11e8-a21d-0050568bcb9"
test_nfs_patch.txt(body) :
{
"protocol": {
  "v4_id_domain": "nfs-nsr-w01.rtp.netapp.com"
},
"vstorage_enabled": "false"
}
```

### Deleting an NFS configuration for an SVM

```
# The API:
DELETE /api/protocols/nfs/services/{svm.uuid}

# The call:
curl -X DELETE "https://<mgmt-ip>/api/protocols/nfs/services/4a415601-
548c-11e8-a21d-0050568bcb9"
```

## Retrieve NFS configuration for SVMs

GET /protocols/nfs/services

Retrieves the NFS configuration of SVMs.

### Related ONTAP commands

- `vserver nfs show`
- `vserver nfs status`

### Learn more

- [DOC /protocols/nfs/services](#)

### Parameters

Name	Type	In	Required	Description
vstorage_enabled	boolean	query	False	Filter by vstorage_enabled

Name	Type	In	Required	Description
svm.uuid	string	query	False	Filter by svm.uuid
svm.name	string	query	False	Filter by svm.name
protocol.v41_features.write_delegation_enabled	boolean	query	False	Filter by protocol.v41_features.write_delegation_enabled
protocol.v41_features.acl_enabled	boolean	query	False	Filter by protocol.v41_features.acl_enabled
protocol.v41_features.read_delegation_enabled	boolean	query	False	Filter by protocol.v41_features.read_delegation_enabled
protocol.v41_features.pnfs_enabled	boolean	query	False	Filter by protocol.v41_features.pnfs_enabled
protocol.v40_enabled	boolean	query	False	Filter by protocol.v40_enabled
protocol.v41_enabled	boolean	query	False	Filter by protocol.v41_enabled
protocol.v4_id_domain	string	query	False	Filter by protocol.v4_id_domain
protocol.v40_features.acl_enabled	boolean	query	False	Filter by protocol.v40_features.acl_enabled
protocol.v40_features.write_delegation_enabled	boolean	query	False	Filter by protocol.v40_features.write_delegation_enabled
protocol.v40_features.read_delegation_enabled	boolean	query	False	Filter by protocol.v40_features.read_delegation_enabled

Name	Type	In	Required	Description
protocol.v3_enabled	boolean	query	False	Filter by protocol.v3_enabled
transport.udp_enabled	boolean	query	False	Filter by transport.udp_enabled
transport.tcp_enabled	boolean	query	False	Filter by transport.tcp_enabled
state	string	query	False	Filter by state
enabled	boolean	query	False	Filter by enabled
fields	array[string]	query	False	Specify the fields to return.
max_records	integer	query	False	Limit the number of records returned.
return_timeout	integer	query	False	The number of seconds to allow the call to execute before returning. When iterating over a collection, the default is 15 seconds. ONTAP returns earlier if either max records or the end of the collection is reached.
return_records	boolean	query	False	The default is true for GET calls. When set to false, only the number of records is returned.
order_by	array[string]	query	False	Order results by specified fields and optional [asc

## Response

Status: 200, Ok

Name	Type	Description
_links	<a href="#">_links</a>	
num_records	integer	Number of NFS Server Records
records	array[ <a href="#">nfs_service</a> ]	

## Example response

```
{
  "_links": {
    "next": {
      "href": "/api/resourcelink"
    },
    "self": {
      "href": "/api/resourcelink"
    }
  },
  "records": [
    {
      "_links": {
        "self": {
          "href": "/api/resourcelink"
        }
      },
      "protocol": {
        "v4_id_domain": "string"
      },
      "state": "string",
      "svm": {
        "_links": {
          "self": {
            "href": "/api/resourcelink"
          }
        },
        "name": "svm1",
        "uuid": "02c9e252-41be-11e9-81d5-00a0986138f7"
      }
    }
  ]
}
```

## Error

Status: Default, Error

Name	Type	Description
error	<a href="#">error</a>	



## Example error

```
{
  "error": {
    "arguments": [
      {
        "code": "string",
        "message": "string"
      }
    ],
    "code": "4",
    "message": "entry doesn't exist",
    "target": "uuid"
  }
}
```

## Definitions

## See Definitions

href

Name	Type	Description
href	string	

\_links

Name	Type	Description
next	<a href="#">href</a>	
self	<a href="#">href</a>	

\_links

Name	Type	Description
self	<a href="#">href</a>	

v40\_features

Name	Type	Description
acl_enabled	boolean	Specifies whether NFSv4.0 ACLs is enabled.
read_delegation_enabled	boolean	Specifies whether NFSv4.0 Read Delegation is enabled.
write_delegation_enabled	boolean	Specifies whether NFSv4.0 Write Delegation is enabled.

v41\_features

Name	Type	Description
acl_enabled	boolean	Specifies whether NFSv4.1 ACLs is enabled.
pnfs_enabled	boolean	Specifies whether NFSv4.1 Parallel NFS is enabled.
read_delegation_enabled	boolean	Specifies whether NFSv4.1 Read Delegation is enabled.
write_delegation_enabled	boolean	Specifies whether NFSv4.1 Write Delegation is enabled.

## protocol

Name	Type	Description
v3_enabled	boolean	Specifies whether NFSv3 protocol is enabled.
v40_enabled	boolean	Specifies whether NFSv4.0 protocol is enabled.
v40_features	<a href="#">v40_features</a>	
v41_enabled	boolean	Specifies whether NFSv4.1 protocol is enabled.
v41_features	<a href="#">v41_features</a>	
v4_id_domain	string	Specifies the domain portion of the string form of user and group names as defined by the NFSv4 protocol.

## svm

SVM, applies only to SVM-scoped objects.

Name	Type	Description
<a href="#">_links</a>	<a href="#">_links</a>	
name	string	The name of the SVM.
uuid	string	The unique identifier of the SVM.

## transport

Name	Type	Description
tcp_enabled	boolean	Specifies whether TCP transports are enabled on the server.
udp_enabled	boolean	Specifies whether UDP transports are enabled on the server.

## nfs\_service

Name	Type	Description
<a href="#">_links</a>	<a href="#">_links</a>	

Name	Type	Description
enabled	boolean	Specifies if the NFS service is administratively enabled.
protocol	<a href="#">protocol</a>	
state	string	Specifies the state of the NFS service on the SVM. The following values are supported: * online - NFS server is ready to accept client requests. * offline - NFS server is not ready to accept client requests.
svm	<a href="#">svm</a>	SVM, applies only to SVM-scoped objects.
transport	<a href="#">transport</a>	
vstorage_enabled	boolean	Specifies whether VMware vstorage feature is enabled.

#### error\_arguments

Name	Type	Description
code	string	Argument code
message	string	Message argument

#### error

Name	Type	Description
arguments	array[ <a href="#">error_arguments</a> ]	Message arguments
code	string	Error code
message	string	Error message
target	string	The target parameter that caused the error.

## Create the NFS configuration for an SVM

POST /protocols/nfs/services

Creates an NFS configuration for an SVM.

## Required properties

- `svm.uuid` or `svm.name` - Existing SVM for which to create the NFS configuration.

## Default property values

If not specified in POST, the following default property values are assigned:

- `enabled` - *true*
- `state` - *online*
- `transport.udp_enabled` - *true*
- `transport.tcp_enabled` - *true*
- `protocol.v3_enabled` - *true*
- `protocol.v4_id_domain` - *defaultv4iddomain.com*
- `protocol.v4_enabled` - *false*
- `protocol.v41_enabled` - *false*
- `protocol.v40_features.acl_enabled` - *false*
- `protocol.v40_features.read_delegation_enabled` - *false*
- `protocol.v40_features.write_delegation_enabled` - *false*
- `protocol.v41_features.acl_enabled` - *false*
- `protocol.v41_features.read_delegation_enabled` - *false*
- `protocol.v41_features.write_delegation_enabled` - *false*
- `protocol.v41_features.pnfs_enabled` - *false*
- `vstorage_enabled` - *false*

## Related ONTAP commands

- `vserver nfs create`

## Learn more

- [DOC /protocols/nfs/services](#)

## Request Body

Name	Type	Description
<code>_links</code>	<a href="#">_links</a>	
<code>enabled</code>	boolean	Specifies if the NFS service is administratively enabled.

Name	Type	Description
protocol	protocol	
state	string	Specifies the state of the NFS service on the SVM. The following values are supported: * online - NFS server is ready to accept client requests. * offline - NFS server is not ready to accept client requests.
svm	svm	SVM, applies only to SVM-scoped objects.
transport	transport	
vstorage_enabled	boolean	Specifies whether VMware vstorage feature is enabled.

### Example request

```
{
  "_links": {
    "self": {
      "href": "/api/resourcelink"
    }
  },
  "protocol": {
    "v4_id_domain": "string"
  },
  "state": "string",
  "svm": {
    "_links": {
      "self": {
        "href": "/api/resourcelink"
      }
    },
    "name": "svm1",
    "uuid": "02c9e252-41be-11e9-81d5-00a0986138f7"
  }
}
```

### Response

```
Status: 201, Created
```

Name	Type	Description
_links	<a href="#">_links</a>	
num_records	integer	Number of NFS Server Records
records	array[nfs_service]	

### Example response

```

{
  "_links": {
    "next": {
      "href": "/api/resourcelink"
    },
    "self": {
      "href": "/api/resourcelink"
    }
  },
  "records": [
    {
      "_links": {
        "self": {
          "href": "/api/resourcelink"
        }
      },
      "protocol": {
        "v4_id_domain": "string"
      },
      "state": "string",
      "svm": {
        "_links": {
          "self": {
            "href": "/api/resourcelink"
          }
        },
        "name": "svm1",
        "uuid": "02c9e252-41be-11e9-81d5-00a0986138f7"
      }
    }
  ]
}

```

## Error

Status: Default

### ONTAP Error Response Codes

Error Code	Description
3276916	Vserver is not running
3276994	Kerberos must be disabled on all LIFs on Vserver before adding or removing AES encryption. Disable Kerberos on the LIF and try again
3277038	Cannot enable \"showmount\" feature because it requires an effective cluster version of Data ONTAP 8.3.0 or later
3277049	Cannot enable \"showmount\" feature on ID-Discard Vserver. Ensure that the Vserver is initialized and retry the command
3277052	NFSv4.x access to transitioned volumes in this Vserver could trigger conversion of non-Unicode directories to Unicode, which might impact data-serving performance. Before enabling NFSv4.x for this Vserver, refer to the Data and Configuration Transition Guide
3277069	Cannot disable TCP because the SnapDiff RPC server is in the \"on\" state
3277089	Attempting to create an NFS server using 64-bits for NFSv3 FSIDs and File IDs on Vserver. Older client software might not work with 64-bit identifiers
3277099	Domain name contains invalid characters or it is too short. Allowed characters are: alphabetical characters (A-Za-z), numeric characters (0-9), minus sign (-), and the period (.). The first character must be alphabetical or numeric, last character must not be a minus sign or a period. Minimum supported length: 2 characters, maximum of 256 characters

Name	Type	Description
error	<a href="#">error</a>	



## Example error

```
{
  "error": {
    "arguments": [
      {
        "code": "string",
        "message": "string"
      }
    ],
    "code": "4",
    "message": "entry doesn't exist",
    "target": "uuid"
  }
}
```

## Definitions

## See Definitions

href

Name	Type	Description
href	string	

\_links

Name	Type	Description
self	<a href="#">href</a>	

v40\_features

Name	Type	Description
acl_enabled	boolean	Specifies whether NFSv4.0 ACLs is enabled.
read_delegation_enabled	boolean	Specifies whether NFSv4.0 Read Delegation is enabled.
write_delegation_enabled	boolean	Specifies whether NFSv4.0 Write Delegation is enabled.

v41\_features

Name	Type	Description
acl_enabled	boolean	Specifies whether NFSv4.1 ACLs is enabled.
pnfs_enabled	boolean	Specifies whether NFSv4.1 Parallel NFS is enabled.
read_delegation_enabled	boolean	Specifies whether NFSv4.1 Read Delegation is enabled.
write_delegation_enabled	boolean	Specifies whether NFSv4.1 Write Delegation is enabled.

protocol

Name	Type	Description
v3_enabled	boolean	Specifies whether NFSv3 protocol is enabled.

Name	Type	Description
v40_enabled	boolean	Specifies whether NFSv4.0 protocol is enabled.
v40_features	<a href="#">v40_features</a>	
v41_enabled	boolean	Specifies whether NFSv4.1 protocol is enabled.
v41_features	<a href="#">v41_features</a>	
v4_id_domain	string	Specifies the domain portion of the string form of user and group names as defined by the NFSv4 protocol.

svm

SVM, applies only to SVM-scoped objects.

Name	Type	Description
<a href="#">_links</a>	<a href="#">_links</a>	
name	string	The name of the SVM.
uuid	string	The unique identifier of the SVM.

transport

Name	Type	Description
tcp_enabled	boolean	Specifies whether TCP transports are enabled on the server.
udp_enabled	boolean	Specifies whether UDP transports are enabled on the server.

nfs\_service

Name	Type	Description
<a href="#">_links</a>	<a href="#">_links</a>	
enabled	boolean	Specifies if the NFS service is administratively enabled.
protocol	<a href="#">protocol</a>	

Name	Type	Description
state	string	Specifies the state of the NFS service on the SVM. The following values are supported: * online - NFS server is ready to accept client requests. * offline - NFS server is not ready to accept client requests.
svm	<a href="#">svm</a>	SVM, applies only to SVM-scoped objects.
transport	<a href="#">transport</a>	
vstorage_enabled	boolean	Specifies whether VMware vstorage feature is enabled.

#### [\\_links](#)

Name	Type	Description
next	<a href="#">href</a>	
self	<a href="#">href</a>	

#### nfs\_service

Name	Type	Description
<a href="#">_links</a>	<a href="#">_links</a>	
enabled	boolean	Specifies if the NFS service is administratively enabled.
protocol	<a href="#">protocol</a>	
state	string	Specifies the state of the NFS service on the SVM. The following values are supported: <ul style="list-style-type: none"> <li>• online - NFS server is ready to accept client requests.</li> <li>• offline - NFS server is not ready to accept client requests.</li> </ul>
svm	<a href="#">svm</a>	SVM, applies only to SVM-scoped objects.
transport	<a href="#">transport</a>	

Name	Type	Description
vstorage_enabled	boolean	Specifies whether VMware vstorage feature is enabled.

error\_arguments

Name	Type	Description
code	string	Argument code
message	string	Message argument

error

Name	Type	Description
arguments	array[ <a href="#">error_arguments</a> ]	Message arguments
code	string	Error code
message	string	Error message
target	string	The target parameter that caused the error.

## Delete the NFS configuration for an SVM

```
DELETE /protocols/nfs/services/{svm.uuid}
```

Deletes the NFS configuration of an SVM.

### Related ONTAP commands

- `vserver nfs delete`

### Learn more

- [DOC /protocols/nfs/services](#)

### Parameters

Name	Type	In	Required	Description
svm.uuid	string	path	True	

## Response

Status: 200, Ok

## Error

Status: Default

### ONTAP Error Response Codes

Error Code	Description
3276916	Vserver is not running
3277008	NFS Kerberos must be disabled on all LIFs of Vserver before deleting the NFS configuration. When all LIFs are disabled, try the operation
3277009	NFS Kerberos realms associated with the Vserver are deleted
3277111	Internal error. Failed to remove NFS-specific security trace filter for Vserver
3277112	Internal error. Failed to modify the protocols field of a security trace filter for Vserver

Name	Type	Description
error	<a href="#">error</a>	

### Example error

```
{
  "error": {
    "arguments": [
      {
        "code": "string",
        "message": "string"
      }
    ],
    "code": "4",
    "message": "entry doesn't exist",
    "target": "uuid"
  }
}
```

## Definitions

### See Definitions

error\_arguments

Name	Type	Description
code	string	Argument code
message	string	Message argument

error

Name	Type	Description
arguments	array[ <a href="#">error_arguments</a> ]	Message arguments
code	string	Error code
message	string	Error message
target	string	The target parameter that caused the error.

## Retrieve the NFS configuration for an SVM

```
GET /protocols/nfs/services/{svm.uuid}
```

Retrieves the NFS configuration of an SVM.

### Related ONTAP commands

- `vserver nfs show`
- `vserver nfs status`

### Learn more

- [DOC /protocols/nfs/services](#)

### Parameters

Name	Type	In	Required	Description
svm.uuid	string	path	True	

Name	Type	In	Required	Description
fields	array[string]	query	False	Specify the fields to return.

## Response

Status: 200, Ok

Name	Type	Description
_links	<a href="#">_links</a>	
enabled	boolean	Specifies if the NFS service is administratively enabled.
protocol	<a href="#">protocol</a>	
state	string	Specifies the state of the NFS service on the SVM. The following values are supported: <ul style="list-style-type: none"> <li>• online - NFS server is ready to accept client requests.</li> <li>• offline - NFS server is not ready to accept client requests.</li> </ul>
svm	<a href="#">svm</a>	SVM, applies only to SVM-scoped objects.
transport	<a href="#">transport</a>	
vstorage_enabled	boolean	Specifies whether VMware vstorage feature is enabled.



## Example response

```
{
  "_links": {
    "self": {
      "href": "/api/resourcelink"
    }
  },
  "protocol": {
    "v4_id_domain": "string"
  },
  "state": "string",
  "svm": {
    "_links": {
      "self": {
        "href": "/api/resourcelink"
      }
    },
    "name": "svm1",
    "uuid": "02c9e252-41be-11e9-81d5-00a0986138f7"
  }
}
```

## Error

Status: Default, Error

Name	Type	Description
error	error	

## Example error

```
{
  "error": {
    "arguments": [
      {
        "code": "string",
        "message": "string"
      }
    ],
    "code": "4",
    "message": "entry doesn't exist",
    "target": "uuid"
  }
}
```

## Definitions

## See Definitions

href

Name	Type	Description
href	string	

\_links

Name	Type	Description
self	<a href="#">href</a>	

v40\_features

Name	Type	Description
acl_enabled	boolean	Specifies whether NFSv4.0 ACLs is enabled.
read_delegation_enabled	boolean	Specifies whether NFSv4.0 Read Delegation is enabled.
write_delegation_enabled	boolean	Specifies whether NFSv4.0 Write Delegation is enabled.

v41\_features

Name	Type	Description
acl_enabled	boolean	Specifies whether NFSv4.1 ACLs is enabled.
pnfs_enabled	boolean	Specifies whether NFSv4.1 Parallel NFS is enabled.
read_delegation_enabled	boolean	Specifies whether NFSv4.1 Read Delegation is enabled.
write_delegation_enabled	boolean	Specifies whether NFSv4.1 Write Delegation is enabled.

protocol

Name	Type	Description
v3_enabled	boolean	Specifies whether NFSv3 protocol is enabled.

Name	Type	Description
v40_enabled	boolean	Specifies whether NFSv4.0 protocol is enabled.
v40_features	<a href="#">v40_features</a>	
v41_enabled	boolean	Specifies whether NFSv4.1 protocol is enabled.
v41_features	<a href="#">v41_features</a>	
v4_id_domain	string	Specifies the domain portion of the string form of user and group names as defined by the NFSv4 protocol.

svm

SVM, applies only to SVM-scoped objects.

Name	Type	Description
_links	<a href="#">_links</a>	
name	string	The name of the SVM.
uuid	string	The unique identifier of the SVM.

transport

Name	Type	Description
tcp_enabled	boolean	Specifies whether TCP transports are enabled on the server.
udp_enabled	boolean	Specifies whether UDP transports are enabled on the server.

error\_arguments

Name	Type	Description
code	string	Argument code
message	string	Message argument

error

Name	Type	Description
arguments	array[ <a href="#">error_arguments</a> ]	Message arguments
code	string	Error code
message	string	Error message
target	string	The target parameter that caused the error.

## Update the NFS configuration for an SVM

PATCH /protocols/nfs/services/{svm.uuid}

Updates the NFS configuration of an SVM.

### Related ONTAP commands

- `vserver nfs modify`
- `vserver nfs on`
- `vserver nfs off`
- `vserver nfs start`
- `vserver nfs stop`

### Learn more

- [DOC /protocols/nfs/services](#)

### Parameters

Name	Type	In	Required	Description
svm.uuid	string	path	True	

### Request Body

Name	Type	Description
<a href="#">_links</a>	<a href="#">_links</a>	
enabled	boolean	Specifies if the NFS service is administratively enabled.
protocol	<a href="#">protocol</a>	

Name	Type	Description
state	string	Specifies the state of the NFS service on the SVM. The following values are supported: <ul style="list-style-type: none"> <li>• online - NFS server is ready to accept client requests.</li> <li>• offline - NFS server is not ready to accept client requests.</li> </ul>
svm	svm	SVM, applies only to SVM-scoped objects.
transport	transport	
vstorage_enabled	boolean	Specifies whether VMware vstorage feature is enabled.

### Example request

```
{
  "_links": {
    "self": {
      "href": "/api/resourcelink"
    }
  },
  "protocol": {
    "v4_id_domain": "string"
  },
  "state": "string",
  "svm": {
    "_links": {
      "self": {
        "href": "/api/resourcelink"
      }
    },
    "name": "svm1",
    "uuid": "02c9e252-41be-11e9-81d5-00a0986138f7"
  }
}
```

### Response

Status: 200, Ok

## Error

Status: Default

### ONTAP Error Response Codes

Error Code	Description
3276916	Vserver is not running
3277069	Cannot disable TCP because the SnapDiff RPC server is in the \"on\" state
3277087	Attempting to reduce the number of bits used for NFSv3 FSIDs and File IDs from 64 to 32 on Vserver. This could result in collisions between different File IDs and is not recommended
3277088	Attempting to increase the number of bits used for NFSv3 FSIDs and File IDs from 32 to 64 on Vserver. This could result in older client software no longer working with the volumes owned by Vserver
3277090	Attempting to disallow multiple FSIDs per mount point on Vserver. Since this Vserver currently uses 32-bit NFSv3 FSIDs and File IDs, this could result in collisions between different File IDs and is not recommended
3277099	Domain name contains invalid characters or its too short. Allowed characters are: alphabetical characters (A-Za-z), numeric characters (0-9), minus sign (-), and the period (.). The first character must be alphabetical or numeric, last character must not be a minus sign or a period. Minimum supported length: 2 characters, maximum of 256 characters

Name	Type	Description
error	<a href="#">error</a>	

## Example error

```
{
  "error": {
    "arguments": [
      {
        "code": "string",
        "message": "string"
      }
    ],
    "code": "4",
    "message": "entry doesn't exist",
    "target": "uuid"
  }
}
```

## Definitions



## See Definitions

href

Name	Type	Description
href	string	

\_links

Name	Type	Description
self	<a href="#">href</a>	

v40\_features

Name	Type	Description
acl_enabled	boolean	Specifies whether NFSv4.0 ACLs is enabled.
read_delegation_enabled	boolean	Specifies whether NFSv4.0 Read Delegation is enabled.
write_delegation_enabled	boolean	Specifies whether NFSv4.0 Write Delegation is enabled.

v41\_features

Name	Type	Description
acl_enabled	boolean	Specifies whether NFSv4.1 ACLs is enabled.
pnfs_enabled	boolean	Specifies whether NFSv4.1 Parallel NFS is enabled.
read_delegation_enabled	boolean	Specifies whether NFSv4.1 Read Delegation is enabled.
write_delegation_enabled	boolean	Specifies whether NFSv4.1 Write Delegation is enabled.

protocol

Name	Type	Description
v3_enabled	boolean	Specifies whether NFSv3 protocol is enabled.

Name	Type	Description
v40_enabled	boolean	Specifies whether NFSv4.0 protocol is enabled.
v40_features	<a href="#">v40_features</a>	
v41_enabled	boolean	Specifies whether NFSv4.1 protocol is enabled.
v41_features	<a href="#">v41_features</a>	
v4_id_domain	string	Specifies the domain portion of the string form of user and group names as defined by the NFSv4 protocol.

svm

SVM, applies only to SVM-scoped objects.

Name	Type	Description
<a href="#">_links</a>	<a href="#">_links</a>	
name	string	The name of the SVM.
uuid	string	The unique identifier of the SVM.

transport

Name	Type	Description
tcp_enabled	boolean	Specifies whether TCP transports are enabled on the server.
udp_enabled	boolean	Specifies whether UDP transports are enabled on the server.

nfs\_service

Name	Type	Description
<a href="#">_links</a>	<a href="#">_links</a>	
enabled	boolean	Specifies if the NFS service is administratively enabled.
protocol	<a href="#">protocol</a>	

Name	Type	Description
state	string	Specifies the state of the NFS service on the SVM. The following values are supported: <ul style="list-style-type: none"> <li>• online - NFS server is ready to accept client requests.</li> <li>• offline - NFS server is not ready to accept client requests.</li> </ul>
svm	<a href="#">svm</a>	SVM, applies only to SVM-scoped objects.
transport	<a href="#">transport</a>	
vstorage_enabled	boolean	Specifies whether VMware vstorage feature is enabled.

#### error\_arguments

Name	Type	Description
code	string	Argument code
message	string	Message argument

#### error

Name	Type	Description
arguments	array[ <a href="#">error_arguments</a> ]	Message arguments
code	string	Error code
message	string	Error message
target	string	The target parameter that caused the error.

## Copyright information

Copyright © 2024 NetApp, Inc. All Rights Reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means—graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system—without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

LIMITED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (b)(3) of the Rights in Technical Data -Noncommercial Items at DFARS 252.227-7013 (FEB 2014) and FAR 52.227-19 (DEC 2007).

Data contained herein pertains to a commercial product and/or commercial service (as defined in FAR 2.101) and is proprietary to NetApp, Inc. All NetApp technical data and computer software provided under this Agreement is commercial in nature and developed solely at private expense. The U.S. Government has a non-exclusive, non-transferrable, nonsublicensable, worldwide, limited irrevocable license to use the Data only in connection with and in support of the U.S. Government contract under which the Data was delivered. Except as provided herein, the Data may not be used, disclosed, reproduced, modified, performed, or displayed without the prior written approval of NetApp, Inc. United States Government license rights for the Department of Defense are limited to those rights identified in DFARS clause 252.227-7015(b) (FEB 2014).

## Trademark information

NETAPP, the NETAPP logo, and the marks listed at <http://www.netapp.com/TM> are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.