



View or delete a role

REST API reference

NetApp

February 06, 2026

This PDF was generated from https://docs.netapp.com/us-en/ontap-restapi/security_roles_owner.uuid_name_endpoint_overview.html on February 06, 2026. Always check docs.netapp.com for the latest.

Table of Contents

View or delete a role	1
View or delete a role	1
Overview	1
Examples	1
Delete a role	4
Required parameters	4
Related ONTAP commands	4
Learn more	4
Parameters	5
Response	5
Error	5
Definitions	6
Retrieve the details of a role	7
Related ONTAP commands	7
Learn more	7
Parameters	7
Response	8
Error	9
Definitions	10

View or delete a role

View or delete a role

Overview

This API is used to retrieve or delete a role. The role can be SVM-scoped or cluster-scoped.

Specify the owner UUID and the role name in the URI path. The owner UUID corresponds to the UUID of the SVM for which the role has been created and can be obtained from the response body of a GET call performed on one of the following APIs: `/api/security/roles` for all roles

`/api/security/roles/?scope=svm` for SVM-scoped roles

`/api/security/roles/?owner.name=<svm-name></i>` for roles in a specific SVM This API response contains the complete URI for each role that can be used for retrieving or deleting a role.`</svm-name>`



The pre-defined roles can be retrieved but cannot be deleted.

Examples

Retrieving the role configuration for a REST role

```
# The API:  
GET "/api/security/roles/{owner.uuid}/{name}"  
  
# The call:  
curl -X GET "https://<mgmt-ip>/api/security/roles/aaef7c38-4bd3-11e9-b238-  
0050568e2e25/secure_role"  
  
# The response:  
{  
  "owner": {  
    "uuid": "aaef7c38-4bd3-11e9-b238-0050568e2e25",  
    "name": "svm1",  
    "_links": {  
      "self": {  
        "href": "/api/svm/svms/aaef7c38-4bd3-11e9-b238-0050568e2e25"  
      }  
    }  
  },  
  "name": "secure_role",  
  "privileges": [  
    {  
      "path": "/api/security",  
      "access": "all",  
      "_links": {  
        "self": {  
          "href": "/api/security/roles/aaef7c38-4bd3-11e9-b238-0050568e2e25"  
        }  
      }  
    }  
  ]  
}
```

```

        "href": "/api/security/roles/aaef7c38-4bd3-11e9-b238-
0050568e2e25/secure_role/privileges/%2Fapi%2Fsecurity"
    }
}
},
{
"path": "/api/storage/volumes/651f7fdf-7752-11eb-8d4e-
0050568ed6bd/snapshots",
"access": "readonly",
"_links": {
"self": {
"href": "/api/security/roles/aaef7c38-4bd3-11e9-b238-
0050568e2e25/secure_role/privileges/%2Fapi%2Fstorage%2Fvolumes%2F651f7fdf-
7752-11eb-8d4e-0050568ed6bd%2Fsnapshots"
}
}
},
{
"path": "/api/storage/volumes/6dfeb406-9a16-11ec-819e-
005056bb1a7c/top-metrics/clients",
"access": "readonly",
"_links": {
"self": {
"href": "/api/security/roles/aaef7c38-4bd3-11e9-b238-
0050568e2e25/secure_role/privileges/%2Fapi%2Fstorage%2Fvolumes%2F6dfeb406-
9a16-11ec-819e-005056bb1a7c%2Ftop-metrics%2Fclients"
}
}
},
],
"builtin": false,
"scope": "svm",
"_links": {
"self": {
"href": "/api/security/roles/aaef7c38-4bd3-11e9-b238-
0050568e2e25/secure_role"
}
}
}

```

Retrieving the role configuration for a custom legacy role

```

# The API:
GET "/api/security/roles/{owner.uuid}/{name}"

```

```

# The call:
curl -X GET "https://<mgmt-ip>/api/security/roles/aaef7c38-4bd3-11e9-b238-
0050568e2e25/finVolNoDel"

# The response:
{
  "owner": {
    "uuid": "aaef7c38-4bd3-11e9-b238-0050568e2e25",
    "name": "svm1",
    "_links": {
      "self": {
        "href": "/api/svm/svms/aaef7c38-4bd3-11e9-b238-0050568e2e25"
      }
    }
  },
  "name": "finVolNoDel",
  "privileges": [
    {
      "path": "DEFAULT",
      "access": "none",
      "_links": {
        "self": {
          "href": "/api/security/roles/aaef7c38-4bd3-11e9-b238-
0050568e2e25/finVolNoDel/privileges/DEFAULT"
        }
      }
    },
    {
      "path": "volume",
      "access": "all",
      "_links": {
        "self": {
          "href": "/api/security/roles/aaef7c38-4bd3-11e9-b238-
0050568e2e25/finVolNoDel/privileges/volume"
        }
      }
    },
    {
      "path": "volume delete",
      "access": "none",
      "query": "-volume vol_fin*",
      "_links": {
        "self": {
          "href": "/api/security/roles/aaef7c38-4bd3-11e9-b238-
0050568e2e25/finVolNoDel/privileges/volume%20delete"
        }
      }
    }
  ]
}

```

```
        }
    }
],
"builtin": false,
"scope": "svm",
"_links": {
    "self": {
        "href": "/api/security/roles/aaef7c38-4bd3-11e9-b238-0050568e2e25/finVolNoDel"
    }
}
```

Deleting a custom role

```
# The API:
DELETE "/api/security/roles/{owner.uuid}/{name}"

# The call:
curl -X DELETE "https://<mgmt-ip>/api/security/roles/aaef7c38-4bd3-11e9-b238-0050568e2e25/svm_role1"
```

Delete a role

DELETE /security/roles/{owner.uuid}/{name}

Introduced In: 9.6

Deletes the specified role.

Required parameters

- `name` - Name of the role to be deleted.
- `owner.uuid` - UUID of the SVM housing the role.

Related ONTAP commands

- `security login rest-role delete`
- `security login role delete`

Learn more

- [DOC /security/roles/{owner.uuid}/{name}](#)
- [DOC /security/roles](#)

Parameters

Name	Type	In	Required	Description
owner.uuid	string	path	True	Role owner UUID
name	string	path	True	Role name to be deleted.

Response

Status: 200, Ok

Error

Status: Default

ONTAP Error Response Codes

Error Code	Description
1263347	Cannot modify pre-defined roles.
5636169	Specified URI path is invalid or not supported. Resource-qualified endpoints are not supported.
5636170	URI does not exist.
5636172	User accounts detected with this role assigned. Update or delete those accounts before deleting this role.
5636173	Features require an effective cluster version of 9.6 or later.
5636184	Expanded REST roles for granular resource control feature is currently disabled.
5636185	The specified UUID was not found.
5636186	Expanded REST roles for granular resource control requires an effective cluster version of 9.10.1 or later.
5636245	Failed to delete the role because it is part of the group role-mapping configuration.
5636246	Failed to delete the rest role because it is part of the group role-mapping configuration.
5636247	Failed to delete the rest role because it is part of the external-role-mapping configuration.

Error Code	Description
5636249	Failed to delete the role because it is part of the external-role-mapping configuration.
5636259	The specified child AIDE object was not found within the specified parent AIDE object.
5636261	The specified grandchild AIDE object was not found within the specified child AIDE object that belongs to the specified parent AIDE object.</personalities>
13434890	Vserver-ID failed for Vserver roles.
13434893	The SVM does not exist.

Also see the table of common errors in the [Response body](#) overview section of this documentation.

Name	Type	Description
error	returned_error	

Example error

```
{
  "error": {
    "arguments": [
      {
        "code": "string",
        "message": "string"
      }
    ],
    "code": "4",
    "message": "entry doesn't exist",
    "target": "uuid"
  }
}
```

Definitions

See Definitions

error_arguments

Name	Type	Description
code	string	Argument code
message	string	Message argument

returned_error

Name	Type	Description
arguments	array[error_arguments]	Message arguments
code	string	Error code
message	string	Error message
target	string	The target parameter that caused the error.

Retrieve the details of a role

GET /security/roles/{owner.uuid}/{name}

Introduced In: 9.6

Retrieves the details of the specified role.

Related ONTAP commands

- security login rest-role show
- security login role show

Learn more

- [DOC /security/roles/{owner.uuid}/{name}](#)
- [DOC /security/roles](#)

Parameters

Name	Type	In	Required	Description
owner.uuid	string	path	True	Role owner UUID

Name	Type	In	Required	Description
name	string	path	True	Role name
fields	array[string]	query	False	Specify the fields to return.

Response

Status: 200, Ok

Name	Type	Description
_links	_links	
builtin	boolean	Indicates if this is a built-in (pre-defined) role which cannot be modified or deleted.
name	string	Role name
owner	owner	Owner name and UUID that uniquely identifies the role.
privileges	array[role_privilege]	The list of privileges that this role has been granted.
scope	string	Scope of the entity. Set to "cluster" for cluster owned objects and to "svm" for SVM owned objects.

Example response

```
{  
  "_links": {  
    "self": {  
      "href": "/api/resourcelink"  
    }  
  },  
  "name": "admin",  
  "owner": {  
    "_links": {  
      "self": {  
        "href": "/api/resourcelink"  
      }  
    },  
    "name": "svml1",  
    "uuid": "02c9e252-41be-11e9-81d5-00a0986138f7"  
  },  
  "privileges": [  
    {  
      "_links": {  
        "self": {  
          "href": "/api/resourcelink"  
        }  
      },  
      "access": "all",  
      "path": "volume move start",  
      "query": "-vserver vs1|vs2|vs3 -destination-aggregate  
agg1|agg2"  
    }  
  ],  
  "scope": "string"  
}
```

Error

Status: Default, Error

Name	Type	Description
error	returned_error	

Example error

```
{  
  "error": {  
    "arguments": [  
      {  
        "code": "string",  
        "message": "string"  
      }  
    ],  
    "code": "4",  
    "message": "entry doesn't exist",  
    "target": "uuid"  
  }  
}
```

Definitions

See Definitions

href

Name	Type	Description
href	string	

_links

Name	Type	Description
self	href	

owner

Owner name and UUID that uniquely identifies the role.

Name	Type	Description
_links	_links	
name	string	The name of the SVM. This field cannot be specified in a PATCH method.
uuid	string	The unique identifier of the SVM. This field cannot be specified in a PATCH method.

role_privilege

A tuple containing a REST endpoint or a command/command directory path and the access level assigned to that endpoint or command/command directory. If the "path" attribute refers to a command/command directory path, the tuple could additionally contain an optional query. The REST endpoint can be a resource-qualified endpoint. At present, the only supported resource-qualified endpoints are the following

Snapshots APIs

- `/api/storage/volumes/{volume.uuid}/snapshots`

File System Analytics APIs

- `/api/storage/volumes/{volume.uuid}/files`
- `/api/storage/volumes/{volume.uuid}/top-metrics/clients`
- `/api/storage/volumes/{volume.uuid}/top-metrics/directories`
- `/api/storage/volumes/{volume.uuid}/top-metrics/files`
- `/api/storage/volumes/{volume.uuid}/top-metrics/users`
- `/api/svm/svms/{svm.uuid}/top-metrics/clients`
- `/api/svm/svms/{svm.uuid}/top-metrics/directories`

- `/api/svm/svms/{svm.uuid}/top-metrics/files`
- `/api/svm/svms/{svm.uuid}/top-metrics/users`
- `/api/protocols/s3/services/{svm.uuid}/users`

In the above APIs, wildcard character * could be used in place of `{volume.uuid}` or `{svm.uuid}` to denote *all* volumes or *all* SVMs, depending upon whether the REST endpoint references volumes or SVMs. The `{volume.uuid}` refers to the `-instance-uuid` field value in the "volume show" command output at diagnostic privilege level. It can also be fetched through REST endpoint `/api/storage/volumes`.

Name	Type	Description
<code>_links</code>	_links	
<code>access</code>	string	Access level for the REST endpoint or command/command directory path. If it denotes the access level for a command/command directory path, the only supported enum values are 'none','readonly' and 'all'.
<code>path</code>	string	Either of REST URI/endpoint OR command/command directory path.
<code>query</code>	string	Optional attribute that can be specified only if the "path" attribute refers to a command/command directory path. The privilege tuple implicitly defines a set of objects the role can or cannot access at the specified access level. The query further reduces this set of objects to a subset of objects that the role is allowed to access. The query attribute must be applicable to the command/command directory specified by the "path" attribute. It is defined using one or more parameters of the command/command directory path specified by the "path" attribute.

error_arguments

Name	Type	Description
<code>code</code>	string	Argument code

Name	Type	Description
message	string	Message argument

returned_error

Name	Type	Description
arguments	array[error_arguments]	Message arguments
code	string	Error code
message	string	Error message
target	string	The target parameter that caused the error.

Copyright information

Copyright © 2026 NetApp, Inc. All Rights Reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means—graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system—without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

LIMITED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (b)(3) of the Rights in Technical Data -Noncommercial Items at DFARS 252.227-7013 (FEB 2014) and FAR 52.227-19 (DEC 2007).

Data contained herein pertains to a commercial product and/or commercial service (as defined in FAR 2.101) and is proprietary to NetApp, Inc. All NetApp technical data and computer software provided under this Agreement is commercial in nature and developed solely at private expense. The U.S. Government has a non-exclusive, non-transferrable, nonsublicensable, worldwide, limited irrevocable license to use the Data only in connection with and in support of the U.S. Government contract under which the Data was delivered. Except as provided herein, the Data may not be used, disclosed, reproduced, modified, performed, or displayed without the prior written approval of NetApp, Inc. United States Government license rights for the Department of Defense are limited to those rights identified in DFARS clause 252.227-7015(b) (FEB 2014).

Trademark information

NETAPP, the NETAPP logo, and the marks listed at <http://www.netapp.com/TM> are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.