



Add SnapCenter Standard controller-based licenses

SnapCenter Software

Soumik Das, Archana
August 18, 2021

Table of Contents

- Add SnapCenter Standard controller-based licenses 1
 - Prerequisites to add controller-based license 1
 - Add controller-based license 5

Add SnapCenter Standard controller-based licenses

A SnapCenter Standard controller-based license is required if you are using FAS or AFF storage controllers.

The controller-based license has the following characteristics:

- SnapCenter Standard entitlement included with purchase of Premium or Flash Bundle (not with the base pack)
- Unlimited storage usage
- Enabled by adding it directly to the FAS or AFF storage controller by using either the ONTAP System Manager or the storage cluster command line



You do not enter any license information in the SnapCenter GUI for the SnapCenter controller-based licenses.

- Locked to the controller's serial number

For information on the licenses required, see [SnapCenter licenses](#).

Prerequisites to add controller-based license

Before you add a controller-based license, you should verify if the SnapManager Suite license is installed, identify the licenses installed on the controller, retrieve the serial number of the controller, and retrieve the serial number of the controller-based license.

Verify if the SnapManager Suite license is installed

You can use the SnapCenter GUI to view whether a SnapManager Suite license is installed on FAS or AFF primary storage systems, and to identify which storage systems might require SnapManager Suite licenses. SnapManager Suite licenses apply only to FAS and AFF SVMs or clusters on primary storage systems.



If you already have a SnapManager Suite license on your controller, SnapCenter Standard controller-based license entitlement is provided automatically. The names SnapManagerSuite license and SnapCenter Standard controller-based license are used interchangeably, but they refer to the same license.



Steps

1. In the left navigation pane, click **Storage Systems**.
2. On the Storage Systems page, from the **Type** drop-down, select whether to view all the SVMs or clusters that were added:
 - To view all of the SVMs that were added, select **ONTAP SVMs**.
 - To view all of the clusters that were added, select **ONTAP Clusters**.

When you click the cluster name, all of the SVMs that are part of the cluster are displayed in the Storage Virtual Machines section.

3. In the **Storage Connections** list, locate the Controller License column.

The Controller License column displays the following status:

-  indicates that a SnapManager Suite license is installed on a FAS or AFF primary storage system.
-  indicates that a SnapManager Suite license is not installed on a FAS or AFF primary storage system.
- Not applicable indicates that a SnapManager Suite license is not applicable because the storage controller is on Cloud Volumes ONTAP, ONTAP Select, or Secondary storage platforms.

Identify the licenses installed on the controller

You can use the ONTAP command line to view all the licenses installed on your controller. You should be a cluster administrator on the FAS or AFF system.



The SnapCenter Standard controller-based license is displayed as SnapManagerSuite license on the controller.

Steps

1. Log in to the NetApp controller using the ONTAP command line.
2. Enter the license show command, and then view the output to determine whether the SnapManagerSuite license is installed.

```

cluster1::> license show
(system license show)

Serial Number: 1-80-0000xx
Owner: cluster1
Package          Type      Description          Expiration
-----
Base             site     Cluster Base License -

Serial Number: 1-81-00000000000000000000000000xx
Owner: cluster1-01
Package          Type      Description          Expiration
-----
NFS              license  NFS License         -
CIFS             license  CIFS License        -
iSCSI           license  iSCSI License       -
FCP              license  FCP License         -
SnapRestore     license  SnapRestore License -
SnapMirror      license  SnapMirror License  -
FlexClone       license  FlexClone License   -
SnapVault       license  SnapVault License   -
SnapManagerSuite license  SnapManagerSuite License -

```

In the example, the SnapManagerSuite license is installed, therefore, no additional SnapCenter licensing action is required.

Retrieve the controller serial number

You need to have the controller serial number to retrieve the serial number of your controller-based license. You can retrieve the controller serial number using the ONTAP command line. You should be a cluster administrator on the FAS or AFF system.

Steps

1. Log in to the controller using the ONTAP command line.
2. Enter the system show -instance command, and then review the output to locate the controller serial number.

```
cluster1::> system show -instance
```

```
Node: fas8080-41-42-01
Owner:
Location: RTP 1.5
Model: FAS8080
Serial Number: 123451234511
Asset Tag: -
Uptime: 143 days 23:46
NVRAM System ID: xxxxxxxxxxx
System ID: xxxxxxxxxxx
Vendor: NetApp
Health: true
Eligibility: true
Differentiated Services: false
All-Flash Optimized: false
```

```
Node: fas8080-41-42-02
Owner:
Location: RTP 1.5
Model: FAS8080
Serial Number: 123451234512
Asset Tag: -
Uptime: 144 days 00:08
NVRAM System ID: xxxxxxxxxxx
System ID: xxxxxxxxxxx
Vendor: NetApp
Health: true
Eligibility: true
Differentiated Services: false
All-Flash Optimized: false
2 entries were displayed.
```

3. Record the serial numbers.

Retrieve the serial number of the controller-based license

If you are using FAS or AFF storage, you can retrieve the SnapCenter controller-based license from the NetApp Support Site before you can install it using the ONTAP command line.

What you will need

- You should have a valid NetApp Support Site login credentials.

If you do not enter valid credentials, no information is returned for your search.

- You should have the controller serial number.

Steps

1. Log in to the NetApp Support Site at mysupport.netapp.com.
2. Navigate to **Systems > Software Licenses**.
3. In the Selection Criteria area, ensure Serial Number (located on back of unit) is selected, enter the controller serial number, and then click **Go!**.

Software Licenses

Selection Criteria

Choose a method by which to search

▶ Serial Number (located on back of unit) ▾ Enter Value: Go!

Enter the Cluster Serial Number value without dashes.

- OR -

▶ Show Me All: Serial Numbers with Licenses ▾ For Company: Go!

A list of licenses for the specified controller is displayed.

4. Locate and record the SnapCenter Standard or SnapManagerSuite license.

Add controller-based license

You can use the ONTAP command line to add a SnapCenter controller-based license when you are using FAS or AFF systems, and you have a SnapCenter Standard or SnapManagerSuite license.

What you will need

- You should be a cluster administrator on the FAS or AFF system.
- You should have the SnapCenter Standard or SnapManagerSuite license.

About this task

If you want to install SnapCenter on a trial basis with FAS or AFF storage, you can obtain a Premium Bundle evaluation license to install on your controller.

If you want to install SnapCenter on a trial basis, you should contact your sales representative to obtain a Premium Bundle evaluation license to install on your controller.

Steps

1. Log in to the NetApp cluster using the ONTAP command line.
2. Add the SnapManagerSuite license key:

```
system license add -license-code license_key
```

This command is available at the admin privilege level.

3. Verify that the SnapManagerSuite license is installed:

```
license show
```

Remove the trial license

If you are using a controller-based SnapCenter Standard license and need to remove the capacity-based trial license (serial number ending with “50”), you should use MySQL commands to remove the trial license manually. The trial license cannot be deleted using the SnapCenter GUI.



Removing a trial license manually is only required if you are using a SnapCenter Standard controller-based license. If you procured a SnapCenter Standard capacity-based license and add it in the SnapCenter GUI, the trial license gets overwritten automatically.

Steps

1. On the SnapCenter Server, open a PowerShell window to reset the MySQL password.
 - a. Run the `Open-SmConnection` cmdlet to initiate a connection session with the SnapCenter Server for a `SnapCenterAdmin` account.
 - b. Run the `Set-SmRepositoryPassword` to reset the MySQL password.

For information about the cmdlets, see [SnapCenter Software Cmdlet Reference Guide](#).

2. Open the command prompt and run `mysql -u root -p` to log into MySQL.

MySQL prompts you for the password. Enter the credentials you provided while resetting the password.

3. Remove the trial license from the database:

```
use nsm; ``DELETE FROM nsm_License WHERE nsm_License_Serial_Number='510000050';
```


Copyright Information

Copyright © 2021 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system- without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP "AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at <http://www.netapp.com/TM> are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.