



# Setting up access control permission

## Snapdrive for Unix

Ivana Devine  
January 21, 2021

# Table of Contents

Setting up access control permission ..... 1

# Setting up access control permission

You can set up access control permission in SnapDrive for UNIX by creating a special directory and file in the root volume of the storage system.

Ensure that you are logged in as a root user.

## Steps

1. Create the directory `sdprbac` in the root volume of the target storage system.

One way to make the root volume accessible is to mount the volume using NFS.

2. Create the permissions file in the `sdprbac` directory. Ensure the following statements are true:
  - The file must be named `sdhost-name.prbac` where `host-name` is the name of the host for which you are specifying access permissions.
  - The file must be read-only to ensure that SnapDrive for UNIX can read it, but that it cannot be modified.

To give a host named `dev-sun1` access permission, you would create the following file on the storage system: `/vol/vol1/sdprbac/sddev-sun1.prbac`

3. Set the permissions in the file for that host.

You must use the following format for the file:

- You can specify only one level of permissions. To give the host full access to all operations, enter the string `ALL ACCESS`.
- The permission string must be the first thing in the file. The file format is invalid if the permission string is not in the first line.
- Permission strings are case-insensitive.
- No white space can precede the permission string.
- No comments are allowed.

These valid permission strings allow the following access levels:

- `NONE`—The host has no access to the storage system.
- `SNAP CREATE`—The host can create Snapshot copies.
- `SNAP USE`—The host can delete and rename Snapshot copies.
- `SNAP ALL`—The host can create, restore, delete, and rename Snapshot copies.
- `STORAGE CREATE DELETE`—The host can create, resize, and delete storage.
- `STORAGE USE`—The host can connect and disconnect storage, and also perform clone split estimate and clone split start on storage.
- `STORAGE ALL`—The host can create, delete, connect, and disconnect storage, and also perform clone split estimate and clone split start on storage.
- `ALL ACCESS`—The host has access to all the preceding SnapDrive for UNIX operations.

Each of these permission strings is discrete. If you specify `SNAP USE`, the host can delete or rename Snapshot copies, but it cannot create Snapshot copies or restore or perform any storage provisioning

operations.

Regardless of the permissions you set, the host can perform show and list operations.

4. Verify the access permissions by entering the following command:

```
snapdrive config access show filer_name
```

## Copyright Information

Copyright © 2021 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system- without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP "AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

## Trademark Information

NETAPP, the NETAPP logo, and the marks listed at <http://www.netapp.com/TM> are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.