



About the `broadcast.log`

StorageGRID

NetApp
October 03, 2025

This PDF was generated from <https://docs.netapp.com/us-en/storagegrid-115/monitor/file-rotation-for-broadcast-log.html> on October 03, 2025. Always check docs.netapp.com for the latest.

Table of Contents

About the bycast.log	1
File rotation for bycast.log	1
Messages in bycast.log	1
Message severities in bycast.log	2
Error codes in bycast.log	2

About the `bycast.log`

The file `/var/local/log/bycast.log` is the primary troubleshooting file for the StorageGRID software. There is a `bycast.log` file for every grid node. The file contains messages specific to that grid node.

The file `/var/local/log/bycast-err.log` is a subset of `bycast.log`. It contains messages of severity `ERROR` and `CRITICAL`.

File rotation for `bycast.log`

When the `bycast.log` file reaches 1 GB, the existing file is saved, and a new log file is started.

The saved file is renamed `bycast.log.1`, and the new file is named `bycast.log`. When the new `bycast.log` reaches 1 GB, `bycast.log.1` is renamed and compressed to become `bycast.log.2.gz`, and `bycast.log` is renamed `bycast.log.1`.

The rotation limit for `bycast.log` is 21 files. When the 22nd version of the `bycast.log` file is created, the oldest file is deleted.

The rotation limit for `bycast-err.log` is seven files.



If a log file has been compressed, you must not uncompress it to the same location in which it was written. Uncompressing the file to the same location can interfere with the log rotation scripts.

Related information

[Collecting log files and system data](#)

Messages in `bycast.log`

Messages in `bycast.log` are written by the ADE (Asynchronous Distributed Environment). ADE is the runtime environment used by each grid node's services.

This is an example of an ADE message:

```
May 15 14:07:11 um-sec-rg1-agn3 ADE: |12455685 0357819531
SVMR EVHR 2019-05-05T27T17:10:29.784677| ERROR 0906 SVMR: Health
check on volume 3 has failed with reason 'TOUT'
```

ADE messages contain the following information:

Message segment	Value in example
Node ID	12455685

Message segment	Value in example
ADE process ID	0357819531
Module name	SVMR
Message identifier	EVHR
UTC system time	2019-05-05T27T17:10:29.784677 (YYYY-MM-DDTHH:MM:SS.uuuuuu)
Severity level	ERROR
Internal tracking number	0906
Message	SVMR: Health check on volume 3 has failed with reason 'TOUT'

Message severities in `broadcast.log`

The messages in `broadcast.log` are assigned severity levels.

For example:

- **NOTICE** — An event that should be recorded has occurred. Most log messages are at this level.
- **WARNING** — An unexpected condition has occurred.
- **ERROR** — A major error has occurred that will impact operations.
- **CRITICAL** — An abnormal condition has occurred that has stopped normal operations. You should address the underlying condition immediately. Critical messages are also displayed in the Grid Manager. Select **Support > Tools > Grid Topology**. Then select **Site > Node > SSM > Events**.

Error codes in `broadcast.log`

Most of the error messages in `broadcast.log` contain error codes.

The following table lists common non-numerical codes in `broadcast.log`. The exact meaning of a non-numerical code depends on the context in which it is reported.

Error code	Meaning
SUCS	No error
GERR	Unknown
CANC	Canceled

Error code	Meaning
ABRT	Aborted
TOUT	Timeout
INVL	Invalid
NFND	Not found
VERS	Version
CONF	Configuration
FAIL	Failed
ICPL	Incomplete
DONE	Done
SUNV	Service unavailable

The following table lists the numerical error codes in `broadcast.log`.

Error number	Error code	Meaning
001	EPERM	Operation not permitted
002	ENOENT	No such file or directory
003	ESRCH	No such process
004	EINTR	Interrupted system call
005	EIO	I/O error
006	ENXIO	No such device or address
007	E2BIG	Argument list too long
008	ENOEXEC	Exec format error
009	EBADF	Bad file number
010	ECHILD	No child processes

Error number	Error code	Meaning
011	EAGAIN	Try again
012	ENOMEM	Out of memory
013	EACCES	Permission denied
014	EFAULT	Bad address
015	ENOTBLK	Block device required
016	EBUSY	Device or resource busy
017	EEXIST	File exists
018	EXDEV	Cross-device link
019	ENODEV	No such device
020	ENOTDIR	Not a directory
021	EISDIR	Is a directory
022	EINVAL	Invalid argument
023	ENFILE	File table overflow
024	EMFILE	Too many open files
025	ENOTTY	Not a typewriter
026	ETXTBSY	Text file busy
027	EFBIG	File too large
028	ENOSPC	No space left on device
029	ESPIPE	Illegal seek
030	EROFS	Read-only file system
031	EMLINK	Too many links
032	EPIPE	Broken pipe

Error number	Error code	Meaning
033	EDOM	Math argument out of domain of func
034	ERANGE	Math result not representable
035	EDEADLK	Resource deadlock would occur
036	ENAMETOOLONG	File name too long
037	ENOLCK	No record locks available
038	ENOSYS	Function not implemented
039	ENOTEMPTY	Directory not empty
040	ELOOP	Too many symbolic links encountered
041		
042	ENOMSG	No message of desired type
043	EIDRM	Identifier removed
044	ECHRNG	Channel number out of range
045	EL2NSYNC	Level 2 not synchronized
046	EL3HLT	Level 3 halted
047	EL3RST	Level 3 reset
048	ELNRNG	Link number out of range
049	EUNATCH	Protocol driver not attached
050	ENOCSI	No CSI structure available
051	EL2HLT	Level 2 halted
052	EBADE	Invalid exchange
053	EBADR	Invalid request descriptor

Error number	Error code	Meaning
054	EXFULL	Exchange full
055	ENOANO	No anode
056	EBADRQC	Invalid request code
057	EBADSLT	Invalid slot
058		
059	EBFONT	Bad font file format
060	ENOSTR	Device not a stream
061	ENODATA	No data available
062	ETIME	Timer expired
063	ENOSR	Out of streams resources
064	ENONET	Machine is not on the network
065	ENOPKG	Package not installed
066	EREMOTE	Object is remote
067	ENOLINK	Link has been severed
068	EADV	Advertise error
069	ESRMNT	Srmount error
070	ECOMM	Communication error on send
071	EPROTO	Protocol error
072	EMULTIHOP	Multihop attempted
073	EDOTDOT	RFS specific error
074	EBADMSG	Not a data message

Error number	Error code	Meaning
075	EOVERFLOW	Value too large for defined data type
076	ENOTUNIQ	Name not unique on network
077	EBADFD	File descriptor in bad state
078	EREMCHG	Remote address changed
079	ELIBACC	Cannot access a needed shared library
080	ELIBBAD	Accessing a corrupted shared library
081	ELIBSCN	
082	ELIBMAX	Attempting to link in too many shared libraries
083	ELIBEXEC	Cannot exec a shared library directly
084	EILSEQ	Illegal byte sequence
085	ERESTART	Interrupted system call should be restarted
086	ESTRPIPE	Streams pipe error
087	EUSERS	Too many users
088	ENOTSOCK	Socket operation on non-socket
089	EDESTADDRREQ	Destination address required
090	EMSGSIZE	Message too long
091	EPROTOTYPE	Protocol wrong type for socket
092	ENOPROTOOPT	Protocol not available
093	EPROTONOSUPPORT	Protocol not supported

Error number	Error code	Meaning
094	ESOCKTNOSUPPORT	Socket type not supported
095	EOPNOTSUPP	Operation not supported on transport endpoint
096	EPFNOSUPPORT	Protocol family not supported
097	EAFNOSUPPORT	Address family not supported by protocol
098	EADDRINUSE	Address already in use
099	EADDRNOTAVAIL	Cannot assign requested address
100	ENETDOWN	Network is down
101	ENETUNREACH	Network is unreachable
102	ENETRESET	Network dropped connection because of reset
103	ECONNABORTED	Software caused connection abort
104	ECONNRESET	Connection reset by peer
105	ENOBUFS	No buffer space available
106	EISCONN	Transport endpoint is already connected
107	ENOTCONN	Transport endpoint is not connected
108	ESHUTDOWN	Cannot send after transport endpoint shutdown
109	ETOOMANYREFS	Too many references: cannot splice
110	ETIMEDOUT	Connection timed out
111	ECONNREFUSED	Connection refused
112	EHOSTDOWN	Host is down

Error number	Error code	Meaning
113	EHOSTUNREACH	No route to host
114	EALREADY	Operation already in progress
115	EINPROGRESS	Operation now in progress
116		
117	EUCLEAN	Structure needs cleaning
118	ENOTNAM	Not a XENIX named type file
119	ENAVAIL	No XENIX semaphores available
120	EISNAM	Is a named type file
121	EREMOTEIO	Remote I/O error
122	EDQUOT	Quota exceeded
123	ENOMEDIUM	No medium found
124	EMEDIUMTYPE	Wrong medium type
125	ECANCELED	Operation Canceled
126	EНОKEY	Required key not available
127	EKEYEXPIRED	Key has expired
128	EKEYREVOKED	Key has been revoked
129	EKEYREJECTED	Key was rejected by service
130	EOWNERDEAD	For robust mutexes: Owner died
131	ENOTRECOVERABLE	For robust mutexes: State not recoverable

Copyright information

Copyright © 2025 NetApp, Inc. All Rights Reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means—graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system—without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

LIMITED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (b)(3) of the Rights in Technical Data -Noncommercial Items at DFARS 252.227-7013 (FEB 2014) and FAR 52.227-19 (DEC 2007).

Data contained herein pertains to a commercial product and/or commercial service (as defined in FAR 2.101) and is proprietary to NetApp, Inc. All NetApp technical data and computer software provided under this Agreement is commercial in nature and developed solely at private expense. The U.S. Government has a non-exclusive, non-transferrable, nonsublicensable, worldwide, limited irrevocable license to use the Data only in connection with and in support of the U.S. Government contract under which the Data was delivered. Except as provided herein, the Data may not be used, disclosed, reproduced, modified, performed, or displayed without the prior written approval of NetApp, Inc. United States Government license rights for the Department of Defense are limited to those rights identified in DFARS clause 252.227-7015(b) (FEB 2014).

Trademark information

NETAPP, the NETAPP logo, and the marks listed at <http://www.netapp.com/TM> are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.