



Configuring DNS servers

StorageGRID

NetApp

October 03, 2025

This PDF was generated from <https://docs.netapp.com/us-en/storagegrid-115/maintain/modifying-dns-configuration-for-single-grid-node.html> on October 03, 2025. Always check docs.netapp.com for the latest.

Table of Contents

Configuring DNS servers	1
Modifying the DNS configuration for a single grid node	1

Configuring DNS servers

You can add, remove, and update domain name system (DNS) servers, so that you can use fully qualified domain name (FQDN) hostnames rather than IP addresses.

What you'll need

- You must be signed in to the Grid Manager using a supported browser.
- You must have the Maintenance or Root Access permission.
- You must have the IP addresses of the DNS servers to configure.

About this task

Specifying DNS server information allows you to use fully qualified domain name (FQDN) hostnames rather than IP addresses for email or SNMP notifications and AutoSupport. Specifying at least two DNS servers is recommended.

 Provide between two to six IP addresses for DNS servers. In general, select DNS servers that each site can access locally in the event of network islanding. This is to ensure an islanded site continues to have access to the DNS service. After configuring the grid-wide DNS server list, you can further customize the DNS server list for each node.

Modifying the DNS configuration for a single grid node

If the DNS server information is omitted or incorrectly configured, a DNST alarm is triggered on each grid node's SSM service. The alarm clears when DNS is configured correctly and the new server information has reached all grid nodes.

Steps

1. Select **Maintenance > Network > DNS Servers**.
2. In the Servers section, add update, or remove DNS server entries, as necessary.

The best practice is to specify at least two DNS servers per site. You can specify up to six DNS servers.

3. Click **Save**.

Modifying the DNS configuration for a single grid node

Rather than configure the Domain Name System (DNS) globally for the entire deployment, you can run a script to configure DNS differently for each grid node.

In general, you should use the **Maintenance > Network > DNS Servers** option on the Grid Manager to configure DNS servers. Only use the following script if you need to use different DNS servers for different grid nodes.

1. Log in to the primary Admin Node:
 - a. Enter the following command: `ssh admin@primary_Admin_Node_IP`
 - b. Enter the password listed in the `Passwords.txt` file.
 - c. Enter the following command to switch to root: `su -`

d. Enter the password listed in the `Passwords.txt` file.

When you are logged in as root, the prompt changes from `$` to `#`.

e. Add the SSH private key to the SSH agent. Enter: `ssh-add`

f. Enter the SSH Access Password listed in the `Passwords.txt` file.

2. Log in to the node you want to update with a custom DNS configuration: `ssh node_IP_address`

3. Run the DNS setup script: `setup_resolv.rb`.

The script responds with the list of supported commands.

```
Tool to modify external name servers

available commands:
  add search <domain>
    add a specified domain to search list
    e.g.> add search netapp.com
  remove search <domain>
    remove a specified domain from list
    e.g.> remove search netapp.com
  add nameserver <ip>
    add a specified IP address to the name server list
    e.g.> add nameserver 192.0.2.65
  remove nameserver <ip>
    remove a specified IP address from list
    e.g.> remove nameserver 192.0.2.65
  remove nameserver all
    remove all nameservers from list
  save
    write configuration to disk and quit
  abort
    quit without saving changes
  help
    display this help message
```

Current list of name servers:

192.0.2.64

Name servers inherited from global DNS configuration:

192.0.2.126

192.0.2.127

Current list of search entries:

netapp.com

```
Enter command [`add search <domain>|remove search <domain>|add
nameserver <ip>`]
[`remove nameserver <ip>|remove nameserver
all|save|abort|help`]
```

4. Add the IPv4 address of a server that provides domain name service for your network: `add <nameserver IP_address>`
5. Repeat the `add nameserver` command to add name servers.
6. Follow instructions as prompted for other commands.
7. Save your changes and exit the application: `save`
8. Close the command shell on the server: `exit`
9. For each grid node, repeat the steps from [logging into the node](#) through [closing the command shell](#).
10. When you no longer require passwordless access to other servers, remove the private key from the SSH agent. Enter: `ssh-add -D`

Copyright information

Copyright © 2025 NetApp, Inc. All Rights Reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means—graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system—without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

LIMITED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (b)(3) of the Rights in Technical Data -Noncommercial Items at DFARS 252.227-7013 (FEB 2014) and FAR 52.227-19 (DEC 2007).

Data contained herein pertains to a commercial product and/or commercial service (as defined in FAR 2.101) and is proprietary to NetApp, Inc. All NetApp technical data and computer software provided under this Agreement is commercial in nature and developed solely at private expense. The U.S. Government has a non-exclusive, non-transferrable, nonsublicensable, worldwide, limited irrevocable license to use the Data only in connection with and in support of the U.S. Government contract under which the Data was delivered. Except as provided herein, the Data may not be used, disclosed, reproduced, modified, performed, or displayed without the prior written approval of NetApp, Inc. United States Government license rights for the Department of Defense are limited to those rights identified in DFARS clause 252.227-7015(b) (FEB 2014).

Trademark information

NETAPP, the NETAPP logo, and the marks listed at <http://www.netapp.com/TM> are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.