



License management

Cloud Volumes ONTAP

NetApp
February 27, 2026

Table of Contents

- License management 1
 - Manage capacity-based licensing for Cloud Volumes ONTAP 1
 - How licenses are added to NetApp Console 1
 - View the consumed capacity in your account 1
 - Viewing package details 2
 - Change charging methods 3
 - Download usage reports 5
 - Manage Keystone subscriptions for Cloud Volumes ONTAP through NetApp Console 6
 - Authorize your account 6
 - Link a subscription 7
 - Request more or less committed capacity 7
 - Monitor usage 7
 - Unlink a subscription 7
 - Manage node-based licensing for Cloud Volumes ONTAP 8
 - Manage PAYGO licenses 8
 - Manage BYOL licenses 9
 - Change between PAYGO and BYOL 13

License management

Manage capacity-based licensing for Cloud Volumes ONTAP

Manage your capacity-based licenses from the NetApp Console to ensure that your NetApp account has enough capacity for your Cloud Volumes ONTAP systems.

Capacity-based licenses enable you to pay for Cloud Volumes ONTAP per TiB of capacity.

You can manage capacity-based Cloud Volumes ONTAP licenses from the NetApp Console.



While the actual usage and metering for the products and services managed in the Console are always calculated in GiB and TiB, the terms GB/GiB and TB/TiB are used interchangeably. This is reflected in the Cloud Marketplace listings, price quotes, listing descriptions, and in other supporting documentation

[Learn more about Cloud Volumes ONTAP licenses.](#)

How licenses are added to NetApp Console

After you purchase a license from your NetApp sales representative, NetApp will send you an email with the serial number and additional licensing details.

In the meantime, the Console automatically queries NetApp's licensing service to obtain details about the licenses associated with your NetApp Support Site account. If there are no errors, it adds the licenses.


If the Console can't add the license, you'll need to manually add them. For example, if the Console agent is installed at a location that doesn't have internet access, you'll need to add the licenses yourself. [Learn how to add purchased licenses to your account.](#)

View the consumed capacity in your account

The Console shows you the total consumed capacity in your account and the consumed capacity by licensing package. This can help you understand how you're being charged and whether you need to purchase additional capacity.

Steps

1. From the left navigation pane, select **Administration > Licenses and subscriptions**.
2. On the **Overview** tab, the Cloud Volumes ONTAP tile displays the current capacity provisioned for your account.



- *Direct license* is the total provisioned capacity of all Cloud Volumes ONTAP systems in your NetApp account. The charging is based on each volume's provisioned size, regardless of local, used, stored, or effective space within the volume.
- *Annual contract* is the total licensed capacity (bring your own license (BYOL) or Marketplace Contract) that you purchased from NetApp.
- *PAYGO* is the total provisioned capacity using cloud marketplace subscriptions. Charging via PAYGO is used only if the consumed capacity is higher than the licensed capacity or if there is no BYOL license available in the Console.

3. Select **View** to see the consumed capacity for each of your licensing packages.
4. Select the **Licenses** tab to see details for each package license that you have purchased.

To better understand the capacities that display for the Essentials package, you should be familiar with how charging works. [Learn about charging for the Essentials package.](#)

5. Select the **Subscriptions** tab to see the consumed capacity by license consumption model. This tab includes both PAYGO and annual contract licenses.

You'll only see the subscriptions that are associated with the organization that you are that you're currently viewing.

6. As you view the information about your subscriptions, you can interact with the details in the table. Expand a row to view more details.
 - Select  to choose which columns appear in the table. Note that the Term and Auto Renew columns don't appear by default. The Auto Renew column displays renewal information for Azure contracts only.

Viewing package details

You can view details about the capacity used per package by switching to legacy mode on the Cloud Volumes ONTAP page.

1. From the left navigation pane, select **Administration > Licenses and subscriptions**.
2. On the **Overview** tab, the Cloud Volumes ONTAP tile displays the current capacity provisioned for your account.
3. Select **View** to see the provisioned capacity for each of your licensing packages.

4. Select **Switch** to advanced view.

Cloud Volumes ONTAP

Usage report ⓘ [Switch to advanced View](#)

Marketplace annual con... (2) 0 | 48 TiB | Marketplace PAYGO (0) 0 TiB | Direct license (0) 0 | 0 TiB

Subscriptions (2) Licenses (0)

Cloud Volumes ONTAP subscriptions (2)

Provider	Name	Type	Start date	End date	Status	
	DWdemoAnnualSmall123	Annual Contract	Jan 22, 2025	Jan 21, 2026	Subscribed	⋮ ↓
	cvo_team_bycap_bynode_annual	Annual Contract	Mar 12, 2025	Mar 11, 2026	Subscribed	⋮ ↓

5. View the details of the package you want to see.

Cloud Volumes ONTAP

[Switch to standard View](#)

Cloud Volumes ONTAP Packages Summary ⓘ [Usage report ⓘ](#)

0 TiB Total consumed capacity | 48 TiB Total precommitted capacity | 0 TiB Total PAYGO

Essentials Secondary Single Node ⓘ

0 TiB Consumed Capacity | 6 TiB Precommitted capacity | 0 TiB PAYGO

BYOL 0 TiB | Marketplace Contracts 6 TiB

Professional ⓘ

0 TiB Consumed Capacity | 6 TiB Precommitted capacity | 0 TiB PAYGO

BYOL 0 TiB | Marketplace Contracts 6 TiB

Change charging methods

Capacity-based licensing is available in the form of a *package*. When you create a Cloud Volumes ONTAP system, you can choose from several licensing packages based on your business needs. If your needs change after you create the system, you can change the package at any time. For example, you might change from the Essentials package to the Professional package.

[Learn more about capacity-based licensing packages.](#)

About this task

- Changing the charging method doesn't affect whether you're charged through a license purchased from NetApp (BYOL) or from your cloud provider's marketplace pay-as-you-go (PAYGO) subscription.

The Console always attempts to charge against a license first. If a license isn't available, it charges against a marketplace subscription. You don't have to convert a BYOL subscription to marketplace subscription or vice versa.

- If you have a private offer or contract from your cloud provider's marketplace, changing to a charging method that's not included in your contract will result in charging against BYOL (if you purchased a license from NetApp) or PAYGO.

Steps

1. From the left navigation pane, select **Administration > Licenses and subscriptions**.
2. Select the **Overview** tab.
3. On the Cloud Volumes ONTAP tile, select **View**.
4. Select **Switch to advanced view**.

The screenshot shows the 'Cloud Volumes ONTAP' overview page. At the top, there are three summary cards: 'Marketplace annual con... (2)' with 0 | 48 TiB, 'Marketplace PAYGO (0)' with 0 TiB, and 'Direct license (0)' with 0 | 0 TiB. Below these is a 'Subscriptions (2)' section with a table of two subscriptions. The table has columns for Provider, Name, Type, Start date, End date, and Status. Both subscriptions are 'Annual Contract' and 'Subscribed'.

Provider	Name	Type	Start date	End date	Status
	DWdemoAnnualSmall123	Annual Contract	Jan 22, 2025	Jan 21, 2026	Subscribed
	cvo_team_bycap_bynode_annual	Annual Contract	Mar 12, 2025	Mar 11, 2026	Subscribed

5. Scroll down to the **Capacity-based license** table and select **Change charging method**.

The screenshot shows the 'Cloud Volumes ONTAP licenses (0)' page. The table is empty, displaying 'No licenses'. A red box highlights the 'Change charging method' button in the top right corner of the table area.

Serial number	Package type	Package sub-type	Type	Consumed capacity
No licenses				

6. On the **Change charging method** pop-up, select a Cloud Volumes ONTAP system, choose the new charging method, and then confirm your understanding that changing the package type will affect service charges.
7. Select **Change charging method**.

Download usage reports

You can download four usage reports from the Console. These usage reports provide capacity details of your subscriptions and tell you how you're being charged for the resources in your Cloud Volumes ONTAP subscriptions. The downloadable reports capture data at a point in time and can be easily shared with others.



The following reports are available for download. Capacity values shown are in TiB.

- **High-level usage:** This report includes the following information:
 - Total consumed capacity
 - Total precommitted capacity
 - Total BYOL capacity
 - Total Marketplace contracts capacity
 - Total PAYGO capacity
- **Cloud Volumes ONTAP package usage:** This report includes the following information for each package:
 - Total consumed capacity
 - Total precommitted capacity
 - Total BYOL capacity
 - Total Marketplace contracts capacity
 - Total PAYGO capacity
- **Storage VMs usage:** This report shows how charged capacity is broken down across Cloud Volumes ONTAP systems and storage virtual machines (SVMs). This information is only available in the report. It contains the following information:
 - System ID and name (appears as the UUID)
 - Cloud
 - NetApp account ID
 - System configuration
 - SVM name
 - Provisioned capacity
 - Charged capacity roundup
 - Marketplace billing term
 - Cloud Volumes ONTAP package or feature
 - Charging SaaS Marketplace subscription name
 - Charging SaaS Marketplace subscription ID
 - Workload type

- **Volumes usage:** This report shows how charged capacity is broken down by volumes in a Cloud Volumes ONTAP system. This information is not available on any screen in the Console. It includes the following information:
 - System ID and name (appears as the UUID)
 - SVN name
 - Volume ID
 - Volume type
 - Volume provisioned capacity



FlexClone volumes aren't included in this report because these types of volumes don't incur charges.

Steps

1. From the left navigation pane, select **Administration > Licenses and subscriptions**.
2. On the **Overview** tab, select **View** from the Cloud Volumes ONTAP tile.
3. Select **Usage report**.

The usage report downloads.

4. Open the downloaded file to access the reports.

Manage Keystone subscriptions for Cloud Volumes ONTAP through NetApp Console

Manage your Keystone subscriptions in the NetApp Console by enabling subscriptions for use with Cloud Volumes ONTAP and by requesting changes to the committed capacity for your subscription's service levels. Requesting additional capacity for a service level provides more storage for Cloud Volumes ONTAP systems.

NetApp Keystone is a flexible pay-as-you-grow subscription-based service that delivers a hybrid cloud experience for customers who prefer OpEx to CapEx or leasing.

[Learn more about Keystone](#)

Authorize your account

Before you can use and manage Keystone subscriptions in the Console, you need to contact NetApp to authorize your Console account with your Keystone subscriptions.

Steps

1. From the NetApp Console menu, select **Administration > Licenses and subscriptions**.
2. Select **Keystone Subscriptions**.
3. If you see the **Welcome to NetApp Keystone** page, send an email to the address listed on the page.

A NetApp representative will process your request by authorizing your account to access the subscriptions.

4. Come back to the **Keystone Subscriptions** tab to view your subscriptions.

Link a subscription

After NetApp authorizes your account, you can link Keystone subscriptions for use with Cloud Volumes ONTAP. This action enables users to select the subscription as the charging method for new Cloud Volumes ONTAP systems.

Steps

1. From the NetApp Console menu, select **Administration > Licenses and subscriptions**.
2. Select **Keystone Subscriptions**.
3. For the subscription that you want to link, click **...** and select **Link**.

Result

The subscription is now linked to your Console organization or account and available to select when creating a Cloud Volumes ONTAP working environment.

Request more or less committed capacity

If you want to change the committed capacity for your subscription's service levels, you can send a request to NetApp directly from the Console. Requesting additional capacity for a service level provides more storage for Cloud Volumes ONTAP systems.

Steps

1. From the NetApp Console menu, select **Administration > Licenses and subscriptions**.
2. Select **Keystone Subscriptions**.
3. For the subscription that you want to adjust the capacity, click **...** and select **View detail and edit**.
4. Enter the requested committed capacity for one or more subscriptions.
5. Scroll down, enter any additional details for the request, and then click **Submit**.

Result

Your request creates a ticket in NetApp's system for processing.

Monitor usage

The Digital Advisor dashboard enables you to monitor Keystone subscription usage and generate reports.

[Learn more about monitoring subscription usage](#)

Unlink a subscription

If you no longer want to use a Keystone subscription with the Console, you can unlink the subscription. Note that you can only unlink a subscription that isn't attached to an existing Cloud Volumes ONTAP subscription.

Steps

1. From the NetApp Console menu, select **Administration > Licenses and subscriptions**.
2. Select **Keystone**.
3. For the subscription that you want to unlink, click **...** and select **Unlink**.

Result

The subscription is unlinked from your Console organization or account and no longer available to select when

creating a Cloud Volumes ONTAP working environment.

Manage node-based licensing for Cloud Volumes ONTAP

Manage node-based licenses in the NetApp Console to ensure that each Cloud Volumes ONTAP system has a valid license with the required capacity.

Node-based licenses are the previous generation licensing model (and not available for new customers):

- Bring your own license (BYOL) licenses purchased from NetApp
- Hourly pay-as-you-go (PAYGO) subscriptions from your cloud provider's marketplace

You can manage node-based Cloud Volumes ONTAP licenses licenses from the NetApp Console.


[Learn more about Cloud Volumes ONTAP licenses.](#)

Manage PAYGO licenses

The Licenses and subscriptions menu enables you to view details about each of your PAYGO Cloud Volumes ONTAP systems, including the serial number and PAYGO license type.

Steps

1. From the left navigation pane, select **Administration > Licenses and subscriptions**.
2. Select the **Overview** tab.
3. On the Cloud Volumes ONTAP tile, select **View**.
4. Select **Node Based Licenses** from the drop-down.
5. Click **PAYGO**.
6. View details in the table about each of your PAYGO licenses.



The screenshot displays the 'License Distribution' overview in the NetApp console. It features a donut chart showing 5 total licenses, with a breakdown: 1 BYOL License, 4 PAYGO Licenses, 0 Free Trial, and 0 Eval. Below the chart are tabs for 'BYOL (1)', 'PAYGO (4)', and 'EVAL (0)'. The 'PAYGO (4)' tab is selected, showing a table of licenses.

Cloud Volumes ONTAP Name	Type	Serial Number	Package	
 CVOPAYGO	Single Node	9092013000000001043	standard	Manage PAYGO License
 CVOPAYGO2	High Availability	Node 1 : 90920140000000001010 Node 2 : 90920140000000001011	standard	Manage PAYGO License
 cvopaygo3	Single Node	90920130000000001045	premium	Manage PAYGO License

7. If needed, click **Manage PAYGO License** to change the PAYGO license or to change the instance type.

Manage BYOL licenses

Manage licenses that you purchased directly from NetApp by adding and removing system licenses and extra capacity licenses.



NetApp has restricted the purchase, extension, and renewal of BYOL licensing. For more information, refer to [Restricted availability of BYOL licensing for Cloud Volumes ONTAP](#).

Add unassigned licenses

Add a node-based license to the Console so that you can select the license when you create a new Cloud Volumes ONTAP system. The Console identifies these licenses as *unassigned*.

Steps

1. From the left navigation pane, select **Administration > Licenses and subscriptions**.
2. Select the **Overview** tab.
3. On the Cloud Volumes ONTAP tile, select **View**.
4. Select **Node Based Licenses** from the drop-down.
5. Click **Unassigned**.
6. Click **Add Unassigned Licenses**.
7. Enter the serial number of the license or upload the license file.

If you don't have the license file yet, refer to the section below.

8. Click **Add License**.

Result

The Console adds the license. The license will be identified as unassigned until you associate it with a new Cloud Volumes ONTAP system. After that happens, the license moves to the **BYOL** tab in **Licenses and subscriptions**.

Exchange unassigned node-based licenses

If you have an unassigned node-based license for Cloud Volumes ONTAP that you haven't used, you can exchange the license by converting it to a NetApp Backup and Recovery license, a NetApp Data Classification license, or a NetApp Cloud Tiering license.

Exchanging the license revokes the Cloud Volumes ONTAP license and creates a dollar-equivalent license for the service:

- Licensing for a Cloud Volumes ONTAP HA pair is converted to a 51 TiB direct license
- Licensing for a Cloud Volumes ONTAP single node is converted to a 32 TiB direct license

The converted license has the same expiration date as the Cloud Volumes ONTAP license.

[View walkthrough of how to exchange node-based licenses.](#)

Steps

1. From the left navigation pane, select **Administration > Licenses and subscriptions**.
2. Select the **Overview** tab.

3. On the Cloud Volumes ONTAP tile, select **View**.
4. Select **Node Based Licenses** from the drop-down.
5. Click **Unassigned**.
6. Click **Exchange License**.

Serial Number	Type	Cloud Provider	License Expiry	Status	
012345678901234567890	Single Node	All Providers	April 20, 2022	Unassigned	Exchange License ▾
012345678901234567891	Single Node	Azure	April 20, 2022	Unassigned	Exchange License ▾
012345678901234567892	Single Node	AWS	January 1, 2022	Exchanged to Cloud Tiering on August 1, 2021	

7. Select the service that you'd like to exchange the license with.
8. If you're prompted, select an additional license for the HA pair.
9. Read the legal consent and click **Agree**.

Result

The Console converts the unassigned license to the service that you selected. You can view the new license in the **Data Services Licenses** tab.

Obtain a system license file

In most cases, the Console can automatically obtain your license file using your NetApp Support Site account. But if it can't, then you'll need to manually upload the license file. If you don't have the license file, you can obtain it from netapp.com.

Steps

1. Go to the [NetApp License File Generator](#) and log in using your NetApp Support Site credentials.
2. Enter your password, choose your product, enter the serial number, confirm that you have read and accepted the privacy policy, and then click **Submit**.

Example

License Generator

The following fields are pre-populated based on the NetApp SSO login provided.
To download the corresponding NetApp license file, re-enter your SSO password along with the correct Product Line and Product Serial number.

First Name	<input type="text" value="Ben"/>
Last Name	<input type="text"/>
Company	<input type="text" value="Network Appliance, Inc"/>
Email Address	<input type="text"/>
Username	<input type="text"/>

Product Line*

- ONTAP Select - Standard
- ONTAP Select - Premium
- ONTAP Select - Premium XL
- Cloud Volumes ONTAP for AWS (single node)
- Cloud Volumes ONTAP for AWS (HA)
- Cloud Volumes ONTAP for GCP (single node or HA)
- Cloud Volumes ONTAP for Microsoft Azure (single node)
- Cloud Volumes ONTAP for Microsoft Azure (HA)
- Service Level Manager - SLO Advanced
- StorageGRID Webscale
- StorageGRID WhiteBox
- SnapCenter Standard (capacity-based)

Not only is protecting your data required by

I have read NetApp's new **Global Data** may use my personal data.

3. Choose whether you want to receive the serialnumber.NLF JSON file through email or direct download.

Update a system license

When you renew a BYOL subscription by contacting a NetApp representative, the Console automatically obtains the new license from NetApp and installs it on the Cloud Volumes ONTAP system. If the Console can't access the license file over the secure internet connection, you can obtain the file yourself and then manually upload the file.

Steps

1. From the left navigation pane, select **Administration > Licenses and subscriptions**.
2. Select the **Overview** tab.
3. On the Cloud Volumes ONTAP tile, select **View**.
4. Select **Node Based Licenses** from the drop-down.
5. In the **BYOL** tab, expand the details for a Cloud Volumes ONTAP system.
6. Click the action menu next to the system license and select **Update License**.
7. Upload the license file (or files if you have an HA pair).
8. Click **Update License**.

Result

The Console updates the license on the Cloud Volumes ONTAP system.

Manage extra capacity licenses

You can purchase extra capacity licenses for a Cloud Volumes ONTAP BYOL system to allocate more than the 368 TiB of capacity that's provided with a BYOL system license. For example, you might purchase one extra license capacity to allocate up to 736 TiB of capacity to Cloud Volumes ONTAP. Or you could purchase three extra capacity licenses to get up to 1.4 PiB.

The number of licenses that you can purchase for a single-node system or HA pair is unlimited.

Add capacity licenses

Purchase an extra capacity license by contacting us through the chat icon in the lower-right of the Console. After you purchase the license, you can apply it to a Cloud Volumes ONTAP system.

Steps

1. From the left navigation pane, select **Administration > Licenses and subscriptions**.
2. Select the **Overview** tab.
3. On the Cloud Volumes ONTAP tile, select **View**.
4. Select **Node Based Licenses** from the drop-down.
5. In the **BYOL** tab, expand the details for a Cloud Volumes ONTAP system.
6. Click **Add Capacity License**.
7. Enter the serial number or upload the license file (or files if you have an HA pair).
8. Click **Add Capacity License**.

Update capacity licenses

If you extended the term of an extra capacity license, you'll need to update the license in the Console.

Steps

1. From the left navigation pane, select **Administration > Licenses and subscriptions**.
2. Select the **Overview** tab.
3. On the Cloud Volumes ONTAP tile, select **View**.
4. Select **Node Based Licenses** from the drop-down.
5. In the **BYOL** tab, expand the details for a Cloud Volumes ONTAP system.
6. Click the action menu next to the capacity license and select **Update License**.
7. Upload the license file (or files if you have an HA pair).
8. Click **Update License**.

Remove capacity licenses

If an extra capacity license expired and is no longer in use, then you can remove it at any time.

Steps

1. From the left navigation pane, select **Administration > Licenses and subscriptions**.
2. Select the **Overview** tab.
3. On the Cloud Volumes ONTAP tile, select **View**.

4. Select **Node Based Licenses** from the drop-down.
5. In the **BYOL** tab, expand the details for a Cloud Volumes ONTAP system.
6. Click the action menu next to the capacity license and select **Remove License**.
7. Click **Remove**.

Change between PAYGO and BYOL

Converting a system from PAYGO by-node licensing to BYOL by-node licensing (and vice versa) isn't supported. If you want to switch between a pay-as-you-go subscription and a BYOL subscription, then you need to deploy a new system and replicate data from the existing system to the new system.

Steps

1. Create a new Cloud Volumes ONTAP system.
2. Set up a one-time data replication between the systems for each volume that you need to replicate.

[Learn how to replicate data between systems](#)

3. Terminate the Cloud Volumes ONTAP system that you no longer need by deleting the original system.

[Learn how to delete a Cloud Volumes ONTAP system.](#)

Related links

<https://docs.netapp.com/us-en/storage-management-cloud-volumes-ontap/concept-licensing.html#end-of-availability-of-node-based-licenses>
[Convert node-based licenses to capacity based](#)

Copyright information

Copyright © 2026 NetApp, Inc. All Rights Reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means—graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system—without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

LIMITED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (b)(3) of the Rights in Technical Data -Noncommercial Items at DFARS 252.227-7013 (FEB 2014) and FAR 52.227-19 (DEC 2007).

Data contained herein pertains to a commercial product and/or commercial service (as defined in FAR 2.101) and is proprietary to NetApp, Inc. All NetApp technical data and computer software provided under this Agreement is commercial in nature and developed solely at private expense. The U.S. Government has a non-exclusive, non-transferrable, nonsublicensable, worldwide, limited irrevocable license to use the Data only in connection with and in support of the U.S. Government contract under which the Data was delivered. Except as provided herein, the Data may not be used, disclosed, reproduced, modified, performed, or displayed without the prior written approval of NetApp, Inc. United States Government license rights for the Department of Defense are limited to those rights identified in DFARS clause 252.227-7015(b) (FEB 2014).

Trademark information

NETAPP, the NETAPP logo, and the marks listed at <http://www.netapp.com/TM> are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.