



volume snaplock commands

ONTAP 9.8 commands

NetApp
February 12, 2024

Table of Contents

- volume snaplock commands 1
 - volume snaplock modify 1
 - volume snaplock prepare-to-downgrade 3
 - volume snaplock show 4

volume snaplock commands

volume snaplock modify

Modify SnapLock attributes of a SnapLock volume

Availability: This command is available to *cluster* and *Vserver* administrators at the *admin* privilege level.

Description

The `` volume snaplock modify `` command modifies one or more SnapLock attributes of a SnapLock volume.

Parameters

-vserver <vserver name> - Vserver

This specifies the vservers which owns the required SnapLock volume.

-volume <volume name> - Volume

This specifies the SnapLock volume whose attribute needs to be modified.

{ [-minimum-retention-period {{<integer> seconds|minutes|hours|days|months|years} | infinite}}] - Minimum Retention Period

Specifies the minimum allowed retention period for files committed to WORM state on the volume. Any files committed with a retention period shorter than this minimum value, is assigned this minimum value.

If this option value is *infinite*, then every file committed to the volume will have a retention period that never expires.

Otherwise, the retention period is specified as a number followed by a suffix. The valid suffixes are seconds, minutes, hours, days, months, and years. For example, a value of 6months represents a retention period of 6 months. The maximum allowed retention period is 70 years. This option is not applicable while extending retention period of an already committed WORM file.

[-default-retention-period {{<integer> seconds|minutes|hours|days|months|years} | min | max | infinite | unspecified}}] - Default Retention Period

Specifies the default retention period that is applied to files while committing to WORM state without an associated retention period.

If this option value is *min*, then minimum-retention-period is used as the default retention period. If this option value is *max*, then maximum-retention-period is used as the default retention period. If this option value is *infinite*, then a retention period that never expires will be used as the default retention period. If this option value is *unspecified*, then the file will be retained forever; however, the retention time can be changed to an absolute value.

The retention period can also be explicitly specified as a number followed by a suffix. The valid suffixes are seconds, minutes, hours, days, months, and years. For example, a value of 6months represents a retention period of 6 months. The maximum valid retention period is 70 years.

`[-maximum-retention-period {{<integer> seconds|minutes|hours|days|months|years} | infinite}] - Maximum Retention Period`

Specifies the maximum allowed retention period for files committed to WORM state on the volume. Any files committed with a retention period longer than this maximum value, is assigned this maximum value.

If this option value is *infinite* , then files that have retention period that never expires might be committed to the volume.

Otherwise, the retention period is specified as a number followed by a suffix. The valid suffixes are seconds, minutes, hours, days, months, and years. For example, a value of 6months represents a retention period of 6 months. The maximum allowed retention period is 70 years. This option is not applicable while extending retention period of an already committed WORM file.

`[-autocommit-period {{<integer> minutes|hours|days|months|years} | none}] - Autocommit Period`

Specifies the autocommit period for SnapLock volume. All files which are not modified for a period greater the autocommit period of the volume are committed to WORM state.

The autocommit period option is specified as a number followed by a suffix. The valid suffixes for autocommit period are hours, minutes, days, months and years. For example, a value of 2hours represents an autocommit period of 2 hours. The minimum allowed autocommit period is 5 minutes and the maximum allowed autocommit period is 10 years.

If this option value is *none* , then autocommit is disabled on the SnapLock volume.

`[-is-volume-append-mode-enabled {true|false}] - Is Volume Append Mode Enabled`

Specifies if the volume append mode is enabled or disabled.

It can be modified only when the volume is not mounted and does not have any data or Snapshot copies.

The volume append mode is not supported on SnapLock audit log volumes.

When it is enabled, all the files created with write permissions on the volume are WORM appendable files by default. All the WORM appendable files that are not modified for a period greater than the autocommit period of the volume are also committed to the WORM read-only state.

If it is set to *true* , then the volume append mode is enabled.

If it is set to *false* , then the volume append mode is disabled.

Volume append mode is disabled by default when the volume is created.

`[-privileged-delete {disabled|enabled|permanently-disabled}] - Privileged Delete }`

Specifies the privileged-delete attribute of a SnapLock volume. This parameter must be specified alone.

If it is set to *enabled* then the privileged-delete operation can be performed using the [volume file privileged-delete](#) command.

If it is set to *disabled* , then the privileged-delete operation is not supported.

Once it is set to *permanently-disabled* , then neither the privileged-delete operation nor any change in the volume privileged-delete attribute is permitted.

Examples

The following command sets `-default-retention-period` of a given SnapLock volume:

```
cluster1::> volume snaplock modify -volume vol_slc -default-retention
-period 2years

cluster1::>
```

The following command sets `-maximum-retention-period` of a given SnapLock volume to *infinite*:

```
cluster1::> volume snaplock modify -volume vol_slc -maximum-retention
-period infinite

cluster1::>
```

The following command enables the privileged-delete operation on a SnapLock volume.

```
cluster1::> volume snaplock modify -vserver vs1 -volume vol_sle
-privileged-delete enabled
[Job 38] Job succeeded: Privileged-delete Attribute Change for Volume
"vs1:vol_sle" Completed.
cluster1::>
cluster1::>volume snaplock show -vserver vs1 -volume vol_sle -fields
privileged-delete
vserver volume    privileged-delete
-----
vs1      vol_sle  enabled

cluster1::>
```

Related Links

- [volume file privileged-delete](#)

volume snaplock prepare-to-downgrade

Prepares the system for downgrade

Availability: This command is available to *cluster* administrators at the *advanced* privilege level.

Description

The `volume snaplock prepare-to-downgrade` command prepares nodes to downgrade to a release without SnapLock volume append mode feature. Prior to disabling the feature, the command disables volume

append mode on all SnapLock volumes in the cluster.

Examples

The following example disables the SnapLock volume append mode feature in the local cluster:

```
cluster1::> volume snaplock prepare-to-downgrade
```

volume snaplock show

Display SnapLock attributes of a SnapLock volume

Availability: This command is available to *cluster* and *Vserver* administrators at the *admin* privilege level.

Description

The `volume snaplock show` command displays following information :

- Vserver name
- Volume name
- SnapLock Type of the volume
- Minimum retention period applicable of the volume
- Default retention period applicable of the volume
- Maximum retention period applicable of the volume
- Autocommit period of the volume
- Volume Append Mode attribute of the volume
- Privileged Delete attribute of the volume
- Litigation count on the volume
- Volume expiry time of the volume
- Volume ComplianceClock
- SnapLock audit log volume
- Unspecified retention file count on the volume

This command is applicable only for SnapLock volumes.

Parameters

`{ [-fields <fieldname>,...]`

If you specify the `-fields <fieldname>, ...` parameter, the command output also includes the specified field or fields. You can use `'-fields ?'` to display the fields to specify.

[`-instance`] }

If you specify the `-instance` parameter, the command displays detailed information about all fields.

[`-vserver <vserver name>`] - Vserver

If this parameter is specified, the command displays information for all the SnapLock volumes that match the specified `-vserver` value.

[`-volume <volume name>`] - Volume

If this parameter is specified, the command displays information for the specified `-volume` value.

[`-type {non-snaplock|compliance|enterprise}`] - SnapLock Type

If this parameter is specified, the command displays all the volumes that match the specified `-type` value.

[`-minimum-retention-period {{<integer> seconds|minutes|hours|days|months|years} | infinite}`] - Minimum Retention Period

If this parameter is specified, the command displays all the volumes that match the specified `-minimum-retention-period` value.

[`-default-retention-period {{<integer> seconds|minutes|hours|days|months|years} | min | max | infinite | unspecified}`] - Default Retention Period

If this parameter is specified, the command displays all the volumes that match the specified `-default-retention-period` value.

[`-maximum-retention-period {{<integer> seconds|minutes|hours|days|months|years} | infinite}`] - Maximum Retention Period

If this parameter is specified, the command displays all the volumes that match the specified `-maximum-retention-period` value.

[`-autocommit-period {{<integer> minutes|hours|days|months|years} | none}`] - Autocommit Period

If this parameter is specified, the command displays all the volumes that match the specified `-autocommit-period` value.

[`-is-volume-append-mode-enabled {true|false}`] - Is Volume Append Mode Enabled

If this parameter is specified, the command displays all the volumes that match the specified `-is-volume-append-mode-enabled` value.

[`-privileged-delete {disabled|enabled|permanently-disabled}`] - Privileged Delete

If this parameter is specified, the command displays all the volumes that match the specified `-privileged-delete` value.

[`-expiry-time <text>`] - Expiry Time

If this parameter is specified, the command displays all the volumes that match the specified `-expiry-time` value.

[`-compliance-clock-time <text>`] - ComplianceClock Time

If this parameter is specified, the command displays all the volumes that match the specified `-compliance-clock-time` value.

[-litigation-count <integer>] - Litigation Count

If this parameter is specified, the command displays all the volumes that match the specified `-litigation-count` value.

[-is-audit-log-volume {true|false}] - Is SnapLock Audit Log Volume

If this parameter is specified, the command displays all the volumes that match the specified `-is-audit-log-volume` value.

[-unspecified-retention-file-count <integer>] - Unspecified Retention File Count

If this parameter is specified, the command displays all the volumes that match the specified `-unspecified-retention-file-count` value.

Examples

The following command shows summary of SnapLock volumes on a vserver:

```
cluster1::> volume snaplock show
Vserver      Volume      SnapLock Type ComplianceClock Time
-----
vs1          vol_slc      compliance  Mon Jan 19 14:12:34 IST 2015
+05:30
vs1          vol_sle      enterprise  Mon Jan 19 14:12:34 IST 2015
+05:30
2 entries were displayed.

cluster1::>
```

The following commands lists the complete SnapLock attributes of two given SnapLock volumes:


```
cluster1::> volume snaplock show -vserver vs1 -volume vol_slc
Vserver Name: vs1
      Volume Name: vol_slc
      SnapLock Type: compliance
      Minimum Retention Period: 1 years
      Default Retention Period: max
      Maximum Retention Period: 30 years
      Autocommit Period: 12 hours
Is Volume Append Mode Enabled: false
      Privileged Delete: permanently-disabled
      Expiry Time: Thu May 11 14:37:21 GMT 2017
      ComplianceClock Time: Wed May 11 20:08:41 IST 2016 +05:30
      Litigation Count: 0
Is SnapLock Audit Log Volume: false
Unspecified Retention File Count: 0
```

```
cluster1::>
```

```
cluster1::> volume snaplock show -vserver vs1 -volume vol_sle
Vserver Name: vs1
      Volume Name: vol_sle
      SnapLock Type: enterprise
      Minimum Retention Period: 6 months
      Default Retention Period: min
      Maximum Retention Period: infinite
      Autocommit Period: none
Is Volume Append Mode Enabled: false
      Privileged Delete: enabled
      Expiry Time: infinite
      ComplianceClock Time: Wed May 11 20:08:44 IST 2016 +05:30
      Litigation Count: 0
Is SnapLock Audit Log Volume: false
Unspecified Retention File Count: 0
```

Copyright information

Copyright © 2024 NetApp, Inc. All Rights Reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means—graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system—without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

LIMITED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (b)(3) of the Rights in Technical Data -Noncommercial Items at DFARS 252.227-7013 (FEB 2014) and FAR 52.227-19 (DEC 2007).

Data contained herein pertains to a commercial product and/or commercial service (as defined in FAR 2.101) and is proprietary to NetApp, Inc. All NetApp technical data and computer software provided under this Agreement is commercial in nature and developed solely at private expense. The U.S. Government has a non-exclusive, non-transferrable, nonsublicensable, worldwide, limited irrevocable license to use the Data only in connection with and in support of the U.S. Government contract under which the Data was delivered. Except as provided herein, the Data may not be used, disclosed, reproduced, modified, performed, or displayed without the prior written approval of NetApp, Inc. United States Government license rights for the Department of Defense are limited to those rights identified in DFARS clause 252.227-7015(b) (FEB 2014).

Trademark information

NETAPP, the NETAPP logo, and the marks listed at <http://www.netapp.com/TM> are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.