



## **Supported configurations**

Cloud Volumes ONTAP release notes

NetApp

February 10, 2026

# Table of Contents

Supported configurations .....	1
Supported configurations for Cloud Volumes ONTAP in AWS .....	1
Supported number of nodes .....	1
Supported storage .....	1
Supported EC2 compute .....	3
Supported regions .....	6
Supported configurations for Cloud Volumes ONTAP in Azure .....	7
Supported configurations by license .....	7
Supported disk sizes .....	18
Supported regions .....	18
Supported configurations for Cloud Volumes ONTAP in Google Cloud .....	18
Supported configurations by license .....	19
Supported disk sizes .....	22
Supported regions .....	23

# Supported configurations

## Supported configurations for Cloud Volumes ONTAP in AWS

Several Cloud Volumes ONTAP configurations are supported in AWS.

### Supported number of nodes

Cloud Volumes ONTAP is available in AWS as a single node system and as a high-availability (HA) pair of nodes for fault tolerance and nondisruptive operations.

Upgrading a single node system to an HA pair is not supported. If you want to switch between a single node system and an HA pair, then you need to deploy a new system and replicate data from the existing system to the new system.

### Supported storage

Cloud Volumes ONTAP supports several types of EBS disks, and S3 object storage for data tiering. The maximum storage capacity is determined by the license that you choose.

#### Storage support by license

Each license supports a different maximum system capacity. The maximum system capacity includes disk-based storage plus object storage used for data tiering. NetApp doesn't support exceeding this limit.

## Capacity-based licenses

	Freemium	Capacity-based license
<b>Maximum system capacity</b> (disks + object storage) <sup>1</sup>	500 GiB	Flexible <sup>2</sup>
<b>Supported disk types</b>	<ul style="list-style-type: none"> <li>General Purpose SSD (gp3 and gp2)<sup>3,5</sup></li> <li>Provisioned IOPS SSD (io1)<sup>3</sup></li> <li>Throughput Optimized HDD (st1)<sup>4</sup></li> </ul>	
<b>Cold data tiering to S3</b>	Supported	

Notes:

1. For an HA pair, the capacity limit is for the entire HA pair. It's not per node. For example, if you use the Premium license, you can have up to 368 TiB of capacity between both nodes.
2. For some configurations, disk limits prevent you from reaching the capacity limit by using disks alone. In those cases, you can reach the capacity limit by [tiering inactive data to object storage](#). For information about disk limits, refer to [storage limits](#).

With capacity-based licensing, each Cloud Volumes ONTAP system supports tiering to object storage. The total tiered capacity can scale up to the cloud provider's bucket limit. While the license does not impose capacity restrictions, you should follow the [FabricPool Best Practices](#) to ensure optimal performance, reliability, and cost efficiency when configuring and managing tiering.

3. Enhanced write performance is enabled when using SSDs with all Cloud Volumes ONTAP configurations.
4. Tiering data to object storage is not recommended when using Throughput Optimized HDDs (st1).
5. Cloud Volumes ONTAP configurations in AWS Local Zones only support the General Purpose SSD (gp2) disk type. No other disk types are supported in Cloud Volumes ONTAP in AWS Local Zones.

## Node-based licenses

	PAYGO Explore	PAYGO Standard	PAYGO Premium	Node-based BYOL
<b>Maximum system capacity</b> (disks + object storage)	2 TiB	10 TiB	368 TiB <sup>2</sup>	368 TiB per license
<b>Supported disk types</b>	<ul style="list-style-type: none"> <li>General Purpose SSD (gp3 and gp2)<sup>3,5</sup></li> <li>Provisioned IOPS SSD (io1)<sup>3</sup></li> <li>Throughput Optimized HDD (st1)<sup>4</sup></li> </ul>			
<b>Cold data tiering to S3</b>	Not supported	Supported		

Notes:

1. For an HA pair, the capacity limit is for the entire HA pair. It's not per node. For example, if you use the Premium license, you can have up to 368 TiB of capacity between both nodes.
2. For some configurations, disk limits prevent you from reaching the capacity limit by using disks alone. In those cases, you can reach the capacity limit by [tiering inactive data to object storage](#). For information about disk limits, refer to [storage limits](#).
3. Enhanced write performance is enabled when using SSDs with all Cloud Volumes ONTAP configurations, except for PAYGO Explore.
4. Tiering data to object storage is not recommended when using Throughput Optimized HDDs (st1).
5. Cloud Volumes ONTAP configurations in AWS Local Zones only support the General Purpose SSD (gp2) disk type.

## Supported disk sizes

In AWS, an aggregate can contain up to 6 disks that are all the same size. But if you have a configuration that supports the Amazon EBS Elastic Volumes feature, then an aggregate can contain up to 8 disks. [Learn more about support for Elastic Volumes](#)

General Purpose SSDs (gp3 and gp2)	Provisioned IOPS SSDs (io1)	Throughput Optimized HDDs (st1)
<ul style="list-style-type: none"> <li>• 100 GiB</li> <li>• 500 GiB</li> <li>• 1 TiB</li> <li>• 2 TiB</li> <li>• 4 TiB</li> <li>• 6 TiB</li> <li>• 8 TiB</li> <li>• 16 TiB</li> </ul>	<ul style="list-style-type: none"> <li>• 100 GiB</li> <li>• 500 GiB</li> <li>• 1 TiB</li> <li>• 2 TiB</li> <li>• 4 TiB</li> <li>• 6 TiB</li> <li>• 8 TiB</li> <li>• 16 TiB</li> </ul>	<ul style="list-style-type: none"> <li>• 500 GiB</li> <li>• 1 TiB</li> <li>• 2 TiB</li> <li>• 4 TiB</li> <li>• 6 TiB</li> <li>• 8 TiB</li> <li>• 16 TiB</li> </ul>

## Supported EC2 compute

Each Cloud Volumes ONTAP license supports different EC2 instance types. For your convenience, the table below shows the vCPU, RAM, and bandwidth for each supported instance type. [You should refer to AWS for the latest and complete details about EC2 instance types](#).

Cloud Volumes ONTAP can run on either a Reserved or On-demand EC2 instance. Solutions that use other instance types aren't supported.

The bandwidths shown in the table below match the documented AWS limits for each instance type. These limits don't completely align with what Cloud Volumes ONTAP can provide. For the expected performance, refer to [NetApp Technical Report 4383: Performance Characterization of Cloud Volumes ONTAP in Amazon Web Services with Application Workloads](#).

License	Supported instance	vCPU	RAM	Flash Cache <sup>1</sup>	Network bandwidth (Gbps)	EBS bandwidth (Mbps)	High write speed <sup>2</sup>
<b>Explore or any other license</b>	m5.xlarge <sup>6</sup>	4	16	Not supported	Up to 10	Up to 4,750	Supported (single node only)
<b>Standard or any other license</b>	r5.xlarge <sup>6</sup>	4	32	Not supported	Up to 10	Up to 4,750	Supported (single node only)
	m5a.2xlarge	8	32	Not supported	Up to 10	Up to 2,880	Supported
	m5.2xlarge <sup>6</sup>	8	32	Not supported	Up to 10	Up to 4,750	Supported

License	Supported instance	vCPU	RAM	Flash Cache <sup>1</sup>	Network bandwidth (Gbps)	EBS bandwidth (Mbps)	High write speed <sup>2</sup>
Premium or any other license							

				supported			
	r5.12xlarge <sup>3</sup>	48	384	Not supported	10	9,500	Supported
License	Supported instance type	vCPU	RAM	Flash Cache	Network bandwidth (Gbps)	EBS bandwidth (Mbps)	High write speed
	m6id.32xlarge	64 <sup>4</sup>	512	Supported	50	40,000	Supported

1. Some instance types include local NVMe storage, which Cloud Volumes ONTAP uses as *Flash Cache*. Flash Cache speeds access to data through real-time intelligent caching of recently read user data and NetApp metadata. It's effective for random read-intensive workloads, including databases, email, and file services. Compression must be disabled on all volumes to take advantage of the Flash Cache performance improvements. [Learn more about Flash Cache](#).
2. Cloud Volumes ONTAP supports high write speed with most instance types when using an HA pair. High write speed is supported with all instance types when using a single node system. [Learn more about choosing a write speed](#).
3. The r5.12xlarge instance type has a known limitation with supportability. If a node unexpectedly reboots due to a panic, the system might not collect core files used to troubleshoot and root cause the problem. The customer accepts the risks and limited support terms and bears all support responsibility if this condition occurs. This limitation affects newly deployed HA pairs and HA pairs upgraded from 9.8. The limitation does not affect newly deployed single node systems.
4. While these EC2 instance types support more than 64 vCPUs, Cloud Volumes ONTAP only supports up to 64 vCPUs.
5. When you choose an EC2 instance type, you can specify whether it is a shared instance or a dedicated instance.
6. AWS Local Zones are supported in the following EC2 instance type families with sizes xlarge to 4xlarge: M5, C5, C5d, R5, and R5d. [You should refer to AWS for the latest and complete details about supported EC2 instance types in Local Zones](#).

High write speed isn't supported with these instance types in AWS Local Zones.

## c4, m4, and r4 instances no longer supported

Cloud Volumes ONTAP no longer supports the c4, m4, and r4 EC2 instance types in AWS. If your system runs on a c4, m4, or r4 instance, change to a c5, m5, or r5 instance. You can't upgrade to this release until you change the instance type.

[Learn how to change the EC2 instance type for Cloud Volumes ONTAP](#).

For more information, refer to:

- [Knowledge base \(KB\) article: Converting an AWS Xen CVO instance to Nitro KVM](#)
- [KB article: Unable to change the instance type from r4 to r5 with disk count error](#)
- [Learn more about the end of availability and support for these instance types](#)

## Supported regions

For AWS region support, see [Cloud Volumes Global Regions](#).

# Supported configurations for Cloud Volumes ONTAP in Azure

Several Cloud Volumes ONTAP configurations are supported in Azure.

## Supported configurations by license

Cloud Volumes ONTAP is available in Azure as a single node system and as a high-availability (HA) pair of nodes for fault tolerance and nondisruptive operations.

Upgrading a single node system to an HA pair is not supported. If you want to switch between a single node system and an HA pair, then you need to deploy a new system and replicate data from the existing system to the new system.

Cloud Volumes ONTAP can run on either a Reserved or On-demand VM instance from your cloud provider. Solutions that use other VM instance types aren't supported.

For supported instances specifications, refer to the [Microsoft Azure documentation](#).

### Single node systems

You can choose from the following capacity-based or node-based licensing configurations when deploying Cloud Volumes ONTAP as a single-node system in Azure.

Cloud Volumes ONTAP can run on either a Reserved or On-demand VM instance from your cloud provider. Solutions that use other VM instance types aren't supported.

## Capacity-based licenses

	Freemium	Optimized <sup>5</sup>	Capacity-based license (Essentials and Professional)
<b>Maximum system capacity (disks + object storage)</b>	500 GiB	With capacity-based licensing, each Cloud Volumes ONTAP system supports tiering to object storage. The total tiered capacity can scale up to the cloud provider's bucket limit. While the license does not impose capacity restrictions, you should follow the <a href="#">FabricPool Best Practices</a> to ensure optimal performance, reliability, and cost efficiency when configuring and managing tiering.	

	Freemium	Optimized <sup>5</sup>	Capacity-based license (Essentials and Professional)
<b>Supported virtual machine types</b>	<ul style="list-style-type: none"> <li>• DS4_v2 <sup>1</sup></li> <li>• DS5_v2 <sup>1</sup></li> <li>• DS13_v2 <sup>1</sup></li> <li>• DS14_v2 <sup>1</sup></li> <li>• DS15_v2 <sup>1</sup></li> <li>• E4s_v3 <sup>1</sup></li> <li>• E8s_v3 <sup>1</sup></li> <li>• E32s_v3 <sup>1,3</sup></li> <li>• E48s_v3 <sup>1,3</sup></li> <li>• E64is_v3 <sup>1,3</sup></li> <li>• E4ds_v4</li> <li>• E8ds_v4</li> <li>• E32ds_v4 <sup>3</sup></li> <li>• E48ds_v4 <sup>3</sup></li> <li>• E80ids_v4 <sup>3</sup></li> <li>• E4ds_v5</li> <li>• E8ds_v5</li> <li>• E20ds_v5 <sup>3</sup></li> <li>• E32ds_v5 <sup>3</sup></li> <li>• E48ds_v5 <sup>3</sup></li> <li>• E64ds_v5 <sup>3</sup></li> <li>• E4ds_v6 <sup>6</sup></li> <li>• E20ds_v6 <sup>6</sup></li> <li>• E32ds_v6 <sup>6</sup></li> <li>• E48ds_v6 <sup>6</sup></li> <li>• E64ds_v6 <sup>6</sup></li> <li>• L8s_v3 <sup>2</sup></li> <li>• L16s_v3 <sup>2</sup></li> <li>• L32s_v3 <sup>2</sup></li> <li>• L48s_v3 <sup>2</sup></li> <li>• L64s_v3 <sup>2</sup></li> </ul>	<ul style="list-style-type: none"> <li>• DS4_v2 <sup>1</sup></li> <li>• DS13_v2 <sup>1</sup></li> <li>• E4s_v3 <sup>1</sup></li> <li>• E8s_v3 <sup>1</sup></li> <li>• E4ds_v4 <sup>3</sup></li> <li>• E8ds_v4 <sup>3</sup></li> <li>• E4ds_v5</li> <li>• E8ds_v5</li> <li>• E20ds_v5 <sup>3</sup></li> <li>• E32ds_v5 <sup>3</sup></li> <li>• E48ds_v5 <sup>3</sup></li> <li>• E64ds_v5 <sup>3</sup></li> <li>• E4ds_v6 <sup>6</sup></li> <li>• E20ds_v6 <sup>6</sup></li> <li>• E32ds_v6 <sup>6</sup></li> <li>• E48ds_v6 <sup>6</sup></li> <li>• E64ds_v6 <sup>6</sup></li> <li>• L8s_v3 <sup>2</sup></li> <li>• L16s_v3 <sup>2</sup></li> <li>• L32s_v3 <sup>2</sup></li> <li>• L48s_v3 <sup>2</sup></li> <li>• L64s_v3 <sup>2</sup></li> </ul>	<ul style="list-style-type: none"> <li>• DS4_v2 <sup>1</sup></li> <li>• DS5_v2 <sup>1</sup></li> <li>• DS13_v2 <sup>1</sup></li> <li>• DS14_v2 <sup>1</sup></li> <li>• DS15_v2 <sup>1</sup></li> <li>• E4s_v3 <sup>1</sup></li> <li>• E8s_v3 <sup>1</sup></li> <li>• E32s_v3 <sup>1,3</sup></li> <li>• E48s_v3 <sup>1,3</sup></li> <li>• E64is_v3 <sup>1,3</sup></li> <li>• E4ds_v4 <sup>3</sup></li> <li>• E8ds_v4 <sup>3</sup></li> <li>• E32ds_v4 <sup>3</sup></li> <li>• E48ds_v4 <sup>3</sup></li> <li>• E80ids_v4 <sup>3</sup></li> <li>• E4ds_v5</li> <li>• E8ds_v5</li> <li>• E20ds_v5 <sup>3</sup></li> <li>• E32ds_v5 <sup>3</sup></li> <li>• E48ds_v5 <sup>3</sup></li> <li>• E64ds_v5 <sup>3</sup></li> <li>• E4ds_v6 <sup>6</sup></li> <li>• E20ds_v6 <sup>6</sup></li> <li>• E32ds_v6 <sup>6</sup></li> <li>• E48ds_v6 <sup>6</sup></li> <li>• E64ds_v6 <sup>6</sup></li> <li>• L8s_v3 <sup>2</sup></li> <li>• L16s_v3 <sup>2</sup></li> <li>• L32s_v3 <sup>2</sup></li> <li>• L48s_v3 <sup>2</sup></li> <li>• L64s_v3 <sup>2</sup></li> </ul>
<b>Supported disk types <sup>4</sup></b>	Standard HDD Managed Disks, Standard SSD Managed Disks, Premium SSD Managed Disks, and Premium SSD v2 Managed Disks.		

Notes:

- 1 The DS\_v2 and Es\_v3 machine families are no longer available for selection on the NetApp Console when deploying new instances of Cloud Volumes ONTAP in Azure. These families will be retained and supported only in older, existing systems. New deployments of Cloud Volumes ONTAP are supported in Azure only from the 9.12.1 release. We recommend that you switch to either Es\_v4 or any other series compatible with Cloud Volumes ONTAP 9.12.1 and later. The DS\_v2 and Es\_v3 series machines, however, will be available for new deployments made through the API.
- 2 This VM type includes local NVMe storage, which Cloud Volumes ONTAP uses as *Flash Cache*. Flash Cache speeds access to data through real-time intelligent caching of recently read user data and NetApp metadata. It is effective for random read-intensive workloads, including databases, email, and file services. [Learn more](#).

The minimum ONTAP version required for configuring Flash Cache on Azure is 9.13.1 GA.

- 3 These VM types use an [Ultra SSD](#) for VNVRAM, which provides better write performance.

If you choose any of these VM types when you deploy a new Cloud Volumes ONTAP system, you can't change to another VM type that *doesn't* use an Ultra SSD for VNVRAM. For example, you can't change from E8ds\_v4 to E8s\_v3, but you can change from E8ds\_v4 to E32ds\_v4 because both of those VM types use Ultra SSDs. Conversely, if you deployed Cloud Volumes ONTAP using any other VM type, you won't be able to change to another that uses an Ultra SSD for VNVRAM. For example, you can't change E8s\_v3, which *doesn't* use Ultra SSD for VNVRAM, to E8ds\_v4 that does.

Similarly, if you choose Premium SSD Managed Disks for an environment that fulfils the [criteria](#) for Premium SSD v2 Managed Disks, the Console automatically deploys Premium SSD v2 Managed Disks. You cannot switch to Premium SSD v1 Managed Disks.

- 4 For information about the supported disk types in single node deployments, refer to [Azure \(single node\)](#). High write speed is supported with all instance types when using a single node system. You can enable high write speed from the Console during deployment or any time after. [Learn more about choosing a write speed](#). Enhanced write performance is enabled when using SSDs.
- 5 Beginning on August 11, 2025, the Cloud Volumes ONTAP Optimized license is deprecated and will no longer be available for purchase or renewal in the Azure marketplace for pay-as-you-go (PAYGO) subscriptions. For more information, refer to [End of availability of Optimized licenses](#).
- 6 Edsv6 VM types are supported for new deployments of Cloud Volumes ONTAP 9.17.1 and later. You cannot switch an existing deployment with any other VM type, for example, from Edsv5 to Edsv6; only size changes among Edsv6 variants (for example E20ds\_v6 → E32ds\_v6) are supported. For information about this VM type, refer to the [Azure documentation: Edsv6 sizes series](#).

#### Node-based licenses

	PAYGO Explore	PAYGO Standard	PAYGO Premium	Node-based BYOL
<b>Maximum system capacity (disks + object storage)</b>	2 TiB <sup>5</sup>	10 TiB	368 TiB	368 TiB per license

	PAYGO Explore	PAYGO Standard	PAYGO Premium	Node-based BYOL
<b>Supported virtual machine types</b>	<ul style="list-style-type: none"> <li>• E4s_v3 <sup>1</sup></li> <li>• E4ds_v4 <sup>3</sup></li> <li>• E4ds_v5</li> <li>• E4ds_v6 <sup>6</sup></li> </ul>	<ul style="list-style-type: none"> <li>• DS4_v2 <sup>1</sup></li> <li>• DS13_v2 <sup>1</sup></li> <li>• E8s_v3 <sup>1</sup></li> <li>• E8ds_v4 <sup>3</sup></li> <li>• E8ds_v5</li> <li>• L8s_v3 <sup>2</sup></li> </ul>	<ul style="list-style-type: none"> <li>• DS5_v2 <sup>1</sup></li> <li>• DS14_v2 <sup>1</sup></li> <li>• DS15_v2 <sup>1</sup></li> <li>• E32s_v3 <sup>1,3</sup></li> <li>• E48s_v3 <sup>1,3</sup></li> <li>• E64is_v3 <sup>1,3</sup></li> <li>• E32ds_v4 <sup>3</sup></li> <li>• E48ds_v4 <sup>3</sup></li> <li>• E80ids_v4 <sup>3</sup></li> <li>• E20ds_v5 <sup>3</sup></li> <li>• E32ds_v5 <sup>3</sup></li> <li>• E48ds_v5 <sup>3</sup></li> <li>• E64ds_v5 <sup>3</sup></li> <li>• E20ds_v6 <sup>6</sup></li> <li>• E32ds_v6 <sup>6</sup></li> <li>• E48ds_v6 <sup>6</sup></li> <li>• E64ds_v6 <sup>6</sup></li> </ul>	<ul style="list-style-type: none"> <li>• DS4_v2 <sup>1</sup></li> <li>• DS5_v2 <sup>1</sup></li> <li>• DS13_v2 <sup>1</sup></li> <li>• DS14_v2 <sup>1</sup></li> <li>• DS15_v2 <sup>1</sup></li> <li>• E4s_v3 <sup>1</sup></li> <li>• E8s_v3 <sup>1</sup></li> <li>• E32s_v3 <sup>1,3</sup></li> <li>• E48s_v3 <sup>1,3</sup></li> <li>• E64is_v3 <sup>1,3</sup></li> <li>• E4ds_y4 <sup>3</sup></li> <li>• E8ds_y4 <sup>3</sup></li> <li>• E32ds_v4 <sup>3</sup></li> <li>• E48ds_v4 <sup>3</sup></li> <li>• E80ids_v4 <sup>3</sup></li> <li>• E4ds_v5</li> <li>• E8ds_v5</li> <li>• E20ds_v5 <sup>3</sup></li> <li>• E32ds_v5 <sup>3</sup></li> <li>• E48ds_v5 <sup>3</sup></li> <li>• E64ds_v5 <sup>3</sup></li> <li>• E4ds_v6 <sup>6</sup></li> <li>• E20ds_v6 <sup>6</sup></li> <li>• E32ds_v6 <sup>6</sup></li> <li>• E48ds_v6 <sup>6</sup></li> <li>• E64ds_v6 <sup>6</sup></li> <li>• L8s_v3 <sup>2</sup></li> <li>• L16s_v3 <sup>2</sup></li> <li>• L32s_v3 <sup>2</sup></li> <li>• L48s_v3 <sup>2</sup></li> <li>• L64s_v3 <sup>2</sup></li> </ul>
<b>Supported disk types</b> <sup>4</sup>	Standard HDD Managed Disks, Standard SSD Managed Disks, and Premium SSD Managed Disks			

Notes:

1. <sup>1</sup> The DS\_v2 and Es\_v3 machine families are no longer available for selection on the Console when

deploying new instances of Cloud Volumes ONTAP in Azure. These families will be retained and supported only in older, existing systems. New deployments of Cloud Volumes ONTAP are supported in Azure only from the 9.12.1 release. We recommend that you switch to either Es\_v4 or any other series compatible with Cloud Volumes ONTAP 9.12.1 and later. The DS\_v2 and Es\_v3 series machines, however, will be available for new deployments made through the API.

2. <sup>2</sup> This VM type includes local NVMe storage, which Cloud Volumes ONTAP uses as *Flash Cache*. Flash Cache speeds access to data through real-time intelligent caching of recently read user data and NetApp metadata. It is effective for random read-intensive workloads, including databases, email, and file services. [Learn more](#).
3. <sup>3</sup> These VM types use an [Ultra SSD](#) for VNVRAM, which provides better write performance.

If you choose any of these VM types when you deploy a new Cloud Volumes ONTAP system, you can't change to another VM type that *doesn't* use an Ultra SSD for VNVRAM. For example, you can't change from E8ds\_v4 to E8s\_v3, but you can change from E8ds\_v4 to E32ds\_v4 because both of those VM types use Ultra SSDs. Conversely, if you deployed Cloud Volumes ONTAP using any other VM type, you won't be able to change to another that uses an Ultra SSD for VNVRAM. For example, you can't change E8s\_v3, which *doesn't* use Ultra SSD for VNVRAM, to E8ds\_v4 that does.

Similarly, if you choose Premium SSD Managed Disks for an environment that fulfils the [criteria](#) for Premium SSD v2 Managed Disks, the Console automatically deploys Premium SSD v2 Managed Disks. You cannot switch to Premium SSD v1 Managed Disks.

4. <sup>4</sup> High write speed is supported with all instance types when using a single node system. You can enable high write speed from the Console during deployment or any time after. [Learn more about choosing a write speed](#). Enhanced write performance is enabled when using SSDs.
5. <sup>5</sup>Data tiering to Azure Blob storage isn't supported with PAYGO Explore.
6. <sup>6</sup> Edsv6 VM types are supported for new deployments of Cloud Volumes ONTAP 9.17.1 and later. You cannot switch an existing deployment with any other VM type, for example, from Edsv5 to Edsv6; only size changes among Edsv6 variants (for example E20ds\_v6 → E32ds\_v6) are supported. For information about this VM type, refer to the [Azure documentation: Edsv6 sizes series](#).

## HA pairs

You can choose from the following configurations when deploying Cloud Volumes ONTAP as an HA pair in Azure.

### HA pairs with shared managed disks

You can choose from the following configurations when deploying Cloud Volumes ONTAP as an HA pair in Azure.

## Capacity-based licenses

	Freemium	Optimized <sup>7</sup>	Capacity-based license (Essentials and Professional)
<b>Maximum system capacity (disks + object storage)</b>	500 GiB	With capacity-based licensing, each Cloud Volumes ONTAP system supports tiering to object storage. The total tiered capacity can scale up to the cloud provider's bucket limit. While the license does not impose capacity restrictions, you should follow the <a href="#">FabricPool Best Practices</a> to ensure optimal performance, reliability, and cost efficiency when configuring and managing tiering.	
<b>Supported virtual machine types</b>	<ul style="list-style-type: none"> <li>• E8ds_v4</li> <li>• E32ds_v4 <sup>1</sup></li> <li>• E48ds_v4 <sup>1</sup></li> <li>• E80ids_v4 <sup>1,2</sup></li> <li>• E8ds_v5 <sup>4</sup></li> <li>• E20ds_v5 <sup>1,4</sup></li> <li>• E32ds_v5 <sup>1,4</sup></li> <li>• E48ds_v5 <sup>1,4</sup></li> <li>• E64ds_v5 <sup>1,4</sup></li> <li>• E20ds_v6 <sup>8</sup></li> <li>• E32ds_v6 <sup>8</sup></li> <li>• E48ds_v6 <sup>8</sup></li> <li>• E64ds_v6 <sup>8</sup></li> <li>• L8s_v3 <sup>1,3,5</sup></li> <li>• L16s_v3 <sup>1,3,5</sup></li> <li>• L32s_v3 <sup>1,3,5</sup></li> <li>• L48s_v3 <sup>1,3,5</sup></li> <li>• L64s_v3 <sup>1,3,5</sup></li> </ul>	<ul style="list-style-type: none"> <li>• E8ds_v4</li> <li>• E8ds_v5 <sup>4</sup></li> </ul>	<ul style="list-style-type: none"> <li>• E8ds_v4</li> <li>• E32ds_v4 <sup>1</sup></li> <li>• E48ds_v4 <sup>1</sup></li> <li>• E80ids_v4 <sup>1,2</sup></li> <li>• E8ds_v5 <sup>4</sup></li> <li>• E20ds_v5 <sup>1,4</sup></li> <li>• E32ds_v5 <sup>1,4</sup></li> <li>• E48ds_v5 <sup>1,4</sup></li> <li>• E64ds_v5 <sup>1,4</sup></li> <li>• E20ds_v6 <sup>8</sup></li> <li>• E32ds_v6 <sup>8</sup></li> <li>• E48ds_v6 <sup>8</sup></li> <li>• E64ds_v6 <sup>8</sup></li> <li>• L8s_v3 <sup>1,3,5</sup></li> <li>• L16s_v3 <sup>1,3,5</sup></li> <li>• L32s_v3 <sup>1,3,5</sup></li> <li>• L48s_v3 <sup>1,3,5</sup></li> <li>• L64s_v3 <sup>1,3,5</sup></li> </ul>
<b>Supported disk types <sup>6</sup></b>	Premium SSD Managed Disks or Premium SSD v2 Managed Disks.		

Notes:

- 1 Cloud Volumes ONTAP supports high write speed with these VM types when using an HA pair. You can enable high write speed from the Console during deployment or any time after. [Learn more about choosing a write speed](#).
- 2 This VM is recommended only when Azure maintenance control is needed. It's not recommended for any other use case due to the higher pricing.
- 3 Multiple availability zone support starts from ONTAP version 9.13.1.

4. <sup>4</sup> Multiple availability zone support starts from ONTAP version 9.14.1 RC1.
5. <sup>5</sup> This VM type includes local NVMe storage, which Cloud Volumes ONTAP uses as *Flash Cache*. Flash Cache speeds access to data through real-time intelligent caching of recently read user data and NetApp metadata. It is effective for random read-intensive workloads, including databases, email, and file services. [Learn more](#).
6. <sup>6</sup> If you choose Premium SSD Managed Disks for an environment that fulfills the [criteria](#) for Premium SSD v2 Managed Disks, the Console automatically deploys Premium SSD v2 Managed Disks. You cannot switch to Premium SSD v1 Managed Disks. For information about the internal disks for system data for HA deployments single and multiple availability zones, refer to [Azure \(HA pair\)](#).
7. <sup>7</sup> Beginning on August 11, 2025, the Cloud Volumes ONTAP Optimized license is deprecated and will no longer be available for purchase or renewal in the Azure marketplace for pay-as-you-go (PAYGO) subscriptions. [End of availability of Optimized licenses](#).
8. <sup>8</sup> Edsv6 VM types are supported for new deployments of Cloud Volumes ONTAP 9.17.1 and later. You cannot switch an existing deployment with any other VM type, for example, from Edsv5 to Edsv6; only size changes among Edsv6 variants (for example E20ds\_v6 → E32ds\_v6) are supported. For information about this VM type, refer to the [Azure documentation: Edsv6 sizes series](#).

#### Node-based licenses

	PAYGO Standard	PAYGO Premium	Node-based BYOL
<b>Maximum system capacity (disks + object storage)</b>	10 TiB	368 TiB	368 TiB per license
<b>Supported virtual machine types</b>	<ul style="list-style-type: none"> <li>• E8ds_v4 <sup>4</sup></li> <li>• E8ds_v5</li> <li>• L8s_v3 <sup>4,5</sup></li> </ul>	<ul style="list-style-type: none"> <li>• E32ds_v4 <sup>1,4</sup></li> <li>• E48ds_v4 <sup>1,4</sup></li> <li>• E80ids_v4 <sup>1,2,4</sup></li> <li>• E20ds_v5 <sup>1</sup></li> <li>• E32ds_v5 <sup>1</sup></li> <li>• E48ds_v5 <sup>1</sup></li> <li>• E64ds_v5 <sup>1</sup></li> <li>• E20ds_v6 <sup>6</sup></li> <li>• E32ds_v6 <sup>6</sup></li> <li>• E48ds_v6 <sup>6</sup></li> <li>• E64ds_v6 <sup>6</sup></li> <li>• L16s_v3 <sup>1,4,5</sup></li> <li>• L32s_v3 <sup>1,4,5</sup></li> <li>• L48s_v3 <sup>1,4,5</sup></li> <li>• L64s_v3 <sup>1,4,5</sup></li> </ul>	<ul style="list-style-type: none"> <li>• E8ds_v4 <sup>4</sup></li> <li>• E32ds_v4 <sup>1,4</sup></li> <li>• E48ds_v4 <sup>1,4</sup></li> <li>• E80ids_v4 <sup>1,2,4</sup></li> <li>• E20ds_v5 <sup>1</sup></li> <li>• E32ds_v5 <sup>1</sup></li> <li>• E48ds_v5 <sup>1</sup></li> <li>• E64ds_v5 <sup>1</sup></li> <li>• E20ds_v6 <sup>6</sup></li> <li>• E32ds_v6 <sup>6</sup></li> <li>• E48ds_v6 <sup>6</sup></li> <li>• E64ds_v6 <sup>6</sup></li> <li>• L16s_v3 <sup>1,4,5</sup></li> <li>• L32s_v3 <sup>1,4,5</sup></li> <li>• L48s_v3 <sup>1,4,5</sup></li> <li>• L64s_v3 <sup>1,4,5</sup></li> </ul>
<b>Supported disk types</b>	Premium SSD Managed Disks or Premium SSD v2 Managed Disks.		

## Notes:

- 1 Cloud Volumes ONTAP supports high write speed with these VM types when using an HA pair. You can enable high write speed from the Console during deployment or any time after. [Learn more about choosing a write speed](#).
- 2 This VM is recommended only when Azure maintenance control is needed. It's not recommended for any other use case due to the higher pricing.
- 3 These VM types are only supported for HA pairs in a single availability zone configuration running on shared managed disks.
- 4 These VM types are supported for HA pairs in single availability zone and multiple availability zone configurations running on shared managed disks. For Ls\_v3 VM types, multiple availability zone support starts from ONTAP version 9.13.1. For Eds\_v5 VM types, multiple availability zone support starts from ONTAP version 9.14.1 RC1.
- 5 This VM type includes local NVMe storage, which Cloud Volumes ONTAP uses as *Flash Cache*. Flash Cache speeds access to data through real-time intelligent caching of recently read user data and NetApp metadata. It is effective for random read-intensive workloads, including databases, email, and file services. [Learn more](#).
- 6 Edsv6 VM types are supported for new deployments of Cloud Volumes ONTAP 9.17.1 and later. You cannot switch an existing deployment with any other VM type, for example, from Edsv5 to Edsv6; only size changes among Edsv6 variants (for example E20ds\_v6 → E32ds\_v6) are supported. For information about this VM type, refer to the [Azure documentation: Edsv6 sizes series](#).

## HA pairs with page blob

You can use the following configurations with the existing Cloud Volumes ONTAP HA page blob deployments in Azure.



Azure page blobs are not supported for any new deployment.

## Capacity-based licenses

	Freemium	Optimized <sup>4</sup>	Capacity-based license (Essentials and Professional)
<b>Maximum system capacity (disks + object storage)</b>	500 GiB	With capacity-based licensing, each Cloud Volumes ONTAP system supports tiering to object storage. The total tiered capacity can scale up to the cloud provider's bucket limit. While the license does not impose capacity restrictions, you should follow the <a href="#">FabricPool Best Practices</a> to ensure optimal performance, reliability, and cost efficiency when configuring and managing tiering.	
<b>Supported virtual machine types</b>	<ul style="list-style-type: none"> <li>• DS4_v2</li> <li>• DS5_v2 <sup>1</sup></li> <li>• DS13_v2</li> <li>• DS14_v2 <sup>1</sup></li> <li>• DS15_v2 <sup>1</sup></li> <li>• E8s_v3</li> <li>• E48s_v3 <sup>1</sup></li> <li>• E8ds_v4 <sup>3</sup></li> <li>• E32ds_v4 <sup>1,3</sup></li> <li>• E48ds_v4 <sup>1,3</sup></li> <li>• E80ids_v4 <sup>1,2,3</sup></li> <li>• E8ds_v5</li> <li>• E20ds_v5 <sup>1</sup></li> <li>• E32ds_v5 <sup>1</sup></li> <li>• E48ds_v5 <sup>1</sup></li> <li>• E64ds_v5 <sup>1</sup></li> </ul>	<ul style="list-style-type: none"> <li>• DS4_v2</li> <li>• DS13_v2</li> <li>• E8s_v3</li> <li>• E8ds_v4 <sup>3</sup></li> <li>• E32ds_v4 <sup>1,3</sup></li> <li>• E48ds_v4 <sup>1,3</sup></li> <li>• E80ids_v4 <sup>1,2,3</sup></li> <li>• E8ds_v5</li> <li>• E20ds_v5 <sup>1</sup></li> <li>• E32ds_v5 <sup>1</sup></li> <li>• E48ds_v5 <sup>1</sup></li> <li>• E64ds_v5 <sup>1</sup></li> </ul>	<ul style="list-style-type: none"> <li>• DS4_v2</li> <li>• DS5_v2 <sup>1</sup></li> <li>• DS13_v2</li> <li>• DS14_v2 <sup>1</sup></li> <li>• DS15_v2 <sup>1</sup></li> <li>• E8s_v3</li> <li>• E48s_v3 <sup>1</sup></li> <li>• E8ds_v4 <sup>3</sup></li> <li>• E32ds_v4 <sup>1,3</sup></li> <li>• E48ds_v4 <sup>1,3</sup></li> <li>• E80ids_v4 <sup>1,2,3</sup></li> <li>• E8ds_v5</li> <li>• E20ds_v5 <sup>1</sup></li> <li>• E32ds_v5 <sup>1</sup></li> <li>• E48ds_v5 <sup>1</sup></li> <li>• E64ds_v5 <sup>1</sup></li> </ul>
<b>Supported disk types</b>	Page blobs		

### Notes:

1. <sup>1</sup> Cloud Volumes ONTAP supports high write speed with these VM types when using an HA pair. You can enable high write speed from the Console during deployment or any time after. [Learn more about choosing a write speed](#).
2. <sup>2</sup> This VM is recommended only when Azure maintenance control is needed. It's not recommended for any other use case due to the higher pricing.
3. <sup>3</sup> These VMs are only supported in deployments of Cloud Volumes ONTAP 9.11.1 or earlier. With these VM types you can upgrade an existing page blob deployment from Cloud Volumes ONTAP 9.11.1 to 9.12.1. You cannot perform new page blob deployments with Cloud Volumes ONTAP 9.12.1 or above.

4. <sup>4</sup> Beginning on August 11, 2025, the Cloud Volumes ONTAP Optimized license is deprecated and will no longer be available for purchase or renewal in the Azure marketplace for pay-as-you-go (PAYGO) subscriptions. For more information, refer to [End of availability of Optimized licenses](#).

#### Node-based licenses

	PAYGO Standard	PAYGO Premium	Node-based BYOL
<b>Maximum system capacity (disks + object storage)</b>	10 TiB	368 TiB	368 TiB per license
<b>Supported virtual machine types</b>	<ul style="list-style-type: none"> <li>• DS4_v2</li> <li>• DS13_v2</li> <li>• E8s_v3</li> <li>• E8ds_v4 <sup>3</sup></li> <li>• E8ds_v5</li> </ul>	<ul style="list-style-type: none"> <li>• DS5_v2 <sup>1</sup></li> <li>• DS14_v2 <sup>1</sup></li> <li>• DS15_v2 <sup>1</sup></li> <li>• E48s_v3 <sup>1</sup></li> <li>• E32ds_v4 <sup>1,3</sup></li> <li>• E48ds_v4 <sup>1,3</sup></li> <li>• E80ids_v4 <sup>1,2,3</sup></li> <li>• E20ds_v5 <sup>1</sup></li> <li>• E32ds_v5 <sup>1</sup></li> <li>• E48ds_v5 <sup>1</sup></li> <li>• E64ds_v5 <sup>1</sup></li> </ul>	<ul style="list-style-type: none"> <li>• DS4_v2</li> <li>• DS5_v2 <sup>1</sup></li> <li>• DS13_v2</li> <li>• DS14_v2 <sup>1</sup></li> <li>• DS15_v2 <sup>1</sup></li> <li>• E8s_v3</li> <li>• E48s_v3 <sup>1</sup></li> <li>• E8ds_v4 <sup>3</sup></li> <li>• E32ds_v4 <sup>1,3</sup></li> <li>• E48ds_v4 <sup>1,3</sup></li> <li>• E80ids_v4 <sup>1,2,3</sup></li> <li>• E4ds_v5</li> <li>• E8ds_v5</li> <li>• E20ds_v5 <sup>1</sup></li> <li>• E32ds_v5 <sup>1</sup></li> <li>• E48ds_v5 <sup>1</sup></li> <li>• E64ds_v5 <sup>1</sup></li> </ul>
<b>Supported data disk types</b>	Page blobs		

#### Notes:

1. <sup>1</sup> Cloud Volumes ONTAP supports high write speed with these VM types when using an HA pair. You can enable high write speed from the Console during deployment or any time after. [Learn more about choosing a write speed](#).
2. <sup>2</sup> This VM is recommended only when Azure maintenance control is needed. It's not recommended for any other use case due to the higher pricing.
3. <sup>3</sup> These VMs are only supported in deployments of Cloud Volumes ONTAP 9.11.1 or earlier. With these VM types you can upgrade an existing page blob deployment from Cloud Volumes ONTAP 9.11.1 to 9.12.1. You cannot perform new page blob deployments with Cloud Volumes ONTAP 9.12.1 or above.

## Supported disk sizes

In Azure, an aggregate can contain up to 12 disks that are all the same type and size.

### Single node systems

Single node systems use Azure Managed Disks. The following disk sizes are supported:

Premium SSD	Standard SSD	Standard HDD
<ul style="list-style-type: none"><li>• 500 GiB</li><li>• 1 TiB</li><li>• 2 TiB</li><li>• 4 TiB</li><li>• 8 TiB</li><li>• 16 TiB</li><li>• 32 TiB</li></ul>	<ul style="list-style-type: none"><li>• 100 GiB</li><li>• 500 GiB</li><li>• 1 TiB</li><li>• 2 TiB</li><li>• 4 TiB</li><li>• 8 TiB</li><li>• 16 TiB</li><li>• 32 TiB</li></ul>	<ul style="list-style-type: none"><li>• 100 GiB</li><li>• 500 GiB</li><li>• 1 TiB</li><li>• 2 TiB</li><li>• 4 TiB</li><li>• 8 TiB</li><li>• 16 TiB</li><li>• 32 TiB</li></ul>

### HA pairs

HA pairs use Azure Managed Disks. The following disk type and sizes are supported.

(Page blobs are supported with HA pairs deployed before the 9.12.1 release.)

### Premium SSD

- 500 GiB
- 1 TiB
- 2 TiB
- 4 TiB
- 8 TiB
- 16 TiB (managed disks only)
- 32 TiB (managed disks only)

## Supported regions

For Azure region support, see [Cloud Volumes Global Regions](#).

## Supported configurations for Cloud Volumes ONTAP in Google Cloud

Several Cloud Volumes ONTAP configurations are supported in Google Cloud.

## Supported configurations by license

Cloud Volumes ONTAP is available in Google Cloud as a single node system and as a high-availability (HA) pair of nodes for fault tolerance and nondisruptive operations.

Upgrading a single node system to an HA pair isn't supported. If you want to switch between a single node system and an HA pair, then you need to deploy a new system and replicate data from the existing system to the new system.

Cloud Volumes ONTAP can run on either a Reserved or On-demand VM instance from your cloud provider. Solutions that use other VM instance types aren't supported.

## Capacity-based licenses

	Freemium	Optimized <sup>4</sup>	Capacity-based license (Essentials and Professional)
<b>Maximum system capacity (disks + object storage)</b>	500 GiB	With capacity-based licensing, each Cloud Volumes ONTAP system supports tiering to object storage. The total tiered capacity can scale up to the cloud provider's bucket limit. While the license does not impose capacity restrictions, you should follow the <a href="#">FabricPool Best Practices</a> to ensure optimal performance, reliability, and cost efficiency when configuring and managing tiering.	
<b>Supported machine types <sup>1</sup></b>	<ul style="list-style-type: none"> <li>• n1-standard-8 <sup>1</sup></li> <li>• n1-standard-32 <sup>1</sup></li> <li>• n2-standard-4</li> <li>• n2-standard-8</li> <li>• n2-standard-16</li> <li>• n2-standard-32</li> <li>• n2-standard-48</li> <li>• n2-standard-64</li> </ul>	<ul style="list-style-type: none"> <li>• n2-standard-4</li> <li>• n2-standard-8</li> </ul>	<ul style="list-style-type: none"> <li>• n1-standard-8 <sup>1</sup></li> <li>• n1-standard-32 <sup>1</sup></li> <li>• n2-standard-4</li> <li>• n2-standard-8</li> <li>• n2-standard-16</li> <li>• n2-standard-32</li> <li>• n2-standard-48</li> <li>• n2-standard-64</li> </ul>
<b>Supported disk types <sup>2</sup></b>	Balanced persistent disks <sup>3</sup> , Performance (SSD) persistent disks <sup>3</sup> , and Standard (HDD) persistent disks.		

Notes:

- <sup>1</sup> The n1 series machines are no longer available for selection on the NetApp Console when deploying new instances of Cloud Volumes ONTAP in Google Cloud. The n1 series machines will be retained and supported only in older, existing systems. New deployments of Cloud Volumes ONTAP are supported in Google Cloud only from the 9.8 release. We recommend that you switch to the n2 series machines that are compatible with Cloud Volumes ONTAP 9.8 and later. The n1 series machines, however, will be available for new deployments made through the API.

The custom-4-16384 machine type is no longer supported with new Cloud Volumes ONTAP systems. If you have an existing system running on this machine type, you can keep using it, but we recommend switching to the n2-standard-4 machine type.

- <sup>2</sup> Disk limits can prevent you from reaching the maximum system capacity limit by using disks alone. You can reach the capacity limit by [tiering inactive data to object storage](#).

[Learn more about disk limits in Google Cloud.](#)

- <sup>3</sup> Enhanced write performance is enabled when using Balanced persistent disks and Performance (SSD) persistent disks.

Beginning with Cloud Volumes ONTAP 9.13.0, *Flash Cache*, high write speed, and a higher maximum transmission unit (MTU) of 8,896 bytes, are available for the following HA pair deployment instances:

- n2-standard-16
- n2-standard-32
- n2-standard-48
- n2-standard-64

You can enable *Flash Cache*, and high write speed when deploying an eligible instance type. To enable the higher maximum transmission unit of 8,896 bytes, you must chose VPC-1, VPC-2, or VPC-3 for the deployment. The higher MTU enables higher network throughput. For more information on launching one of these deployments, see [Launching an HA pair in Google Cloud](#).



*Flash cache*, high write mode, and an MTU of 8,896 are feature-dependent and cannot be disabled individually within a configured instance.

- 4 Beginning on August 11, 2025, the Cloud Volumes ONTAP Optimized license is deprecated and will no longer be available for purchase or renewal in the Google Cloud marketplace for pay-as-you-go (PAYGO) subscriptions. For information, refer to [What's new in Cloud Volumes ONTAP](#).

#### Node-based licenses

	PAYGO Explore	PAYGO Standard	PAYGO Premium	Node-based BYOL
<b>Maximum system capacity (disks + object storage)</b>	2 TB <sup>2</sup>	10 TiB	368 TiB	368 TiB per license
<b>Supported machine types <sup>3</sup></b>	• n2-standard-4	• n1-standard-8 <sup>3</sup> • n2-standard-8	• n1-standard-32 • n2-standard-16 • n2-standard-32 • n2-standard-48 • n2-standard-64	• n1-standard-8 <sup>3</sup> • n1-standard-32 • n2-standard-4 • n2-standard-8 • n2-standard-16 • n2-standard-32 • n2-standard-48 • n2-standard-64
<b>Supported disk types</b>	Balanced persistent disks <sup>4</sup> , Performance (SSD) persistent disks <sup>4</sup> , and Standard (HDD) persistent disks.			

#### Notes:

- 1 Disk limits can prevent you from reaching the maximum system capacity limit by using disks alone. You can reach the capacity limit by [tiering inactive data to object storage](#).
 

[Learn more about disk limits in Google Cloud](#).
- 2 Data tiering to Google Cloud Storage isn't supported with PAYGO Explore.
- 3 The n1 series machines are no longer available for selection on the Console when deploying new instances of Cloud Volumes ONTAP in Google Cloud. The n1 series machines will be retained and supported only in older, existing systems. New deployments of Cloud Volumes ONTAP are supported

in Google Cloud only from the 9.8 release. We recommend that you switch to the n2 series machines that are compatible with Cloud Volumes ONTAP 9.8 and later. The n1 series machines, however, will be available for new deployments performed through the API.

The custom-4-16384 machine type is no longer supported with new Cloud Volumes ONTAP systems. If you have an existing system running on this machine type, you can keep using it, but we recommend switching to the n2-standard-4 machine type.

4. <sup>4</sup> Enhanced write performance is enabled when using Balanced persistent disks and Performance (SSD) persistent disks.

The Console shows an additional supported machine type for Standard and BYOL: n1-highmem-4. However, this machine type isn't meant for production environments. We've made it available for a specific lab environment only.

Starting with Cloud Volumes ONTAP software version 9.13.0, *Flash Cache*, high write speed, and a higher maximum transmission unit (MTU) of 8,896 bytes, are available for the following HA pair deployment instances:

- n2-standard-16
- n2-standard-32
- n2-standard-48
- n2-standard-64

You can enable *Flash Cache*, and high write speed when deploying an eligible instance type. To enable the higher maximum transmission unit of 8,896 bytes, you must choose VPC-1, VPC-2, or VPC-3 for the deployment. The higher MTU enables higher network throughput. For more information on launching one of these deployments, see [Launching an HA pair in Google Cloud](#).



*Flash cache*, high write mode, and an MTU of 8,896 are feature-dependent and cannot be disabled individually within a configured instance.

For more information about specific machine types, refer to the Google Cloud documentation:

- [n1 series general-purpose machine types](#)
- [N2 series general-purpose machine types](#)

## Supported disk sizes

In Google Cloud, an aggregate can contain up to 6 disks that are all the same type and size. The following disk sizes are supported:

- 100 GB
- 500 GB
- 1 TB
- 2 TB
- 4 TB
- 8 TB
- 16 TB

- 64 TB

## Supported regions

For Google Cloud region support, see [Cloud Volumes Global Regions](#).

## Copyright information

Copyright © 2026 NetApp, Inc. All Rights Reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means—graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system—with prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

**LIMITED RIGHTS LEGEND:** Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (b)(3) of the Rights in Technical Data -Noncommercial Items at DFARS 252.227-7013 (FEB 2014) and FAR 52.227-19 (DEC 2007).

Data contained herein pertains to a commercial product and/or commercial service (as defined in FAR 2.101) and is proprietary to NetApp, Inc. All NetApp technical data and computer software provided under this Agreement is commercial in nature and developed solely at private expense. The U.S. Government has a non-exclusive, non-transferrable, nonsublicensable, worldwide, limited irrevocable license to use the Data only in connection with and in support of the U.S. Government contract under which the Data was delivered. Except as provided herein, the Data may not be used, disclosed, reproduced, modified, performed, or displayed without the prior written approval of NetApp, Inc. United States Government license rights for the Department of Defense are limited to those rights identified in DFARS clause 252.227-7015(b) (FEB 2014).

## Trademark information

NETAPP, the NETAPP logo, and the marks listed at <http://www.netapp.com/TM> are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.