



# **FSx ONTAP for MLOps**

NetApp artificial intelligence solutions

NetApp  
August 18, 2025

# Table of Contents

- FSx ONTAP for MLOps ..... 1
  - Amazon FSx for NetApp ONTAP (FSx ONTAP) for MLOps. .... 1
  - Part 1 - Integrating Amazon FSx for NetApp ONTAP (FSx ONTAP) as a private S3 bucket into AWS
    - SageMaker ..... 1
      - Introduction ..... 1
      - User Guide ..... 1
      - Useful debugging checklist ..... 14
      - FAQ (As of Sep 27, 2023) ..... 15
    - Part 2 - Leveraging AWS Amazon FSx for NetApp ONTAP (FSx ONTAP) as a Data Source for Model Training in SageMaker ..... 15
      - Introduction ..... 15
      - What is FSx ONTAP ..... 15
      - Prerequisite ..... 15
      - Integration Overview ..... 16
      - Step-by-Step Integration ..... 17
  - Part 3 - Building A Simplified MLOps Pipeline (CI/CT/CD). .... 24
    - Introduction ..... 24
    - Manifest ..... 24
    - Prerequisite ..... 25
    - Architecture ..... 25
    - Step-by-Step Configuration ..... 25

# FSx ONTAP for MLOps

## Amazon FSx for NetApp ONTAP (FSx ONTAP) for MLOps

This section delves into the practical application of AI infrastructure development, providing an end-to-end walkthrough of constructing an MLOps pipeline using FSx ONTAP. Comprising three comprehensive examples, it guides you to meet your MLOps needs via this powerful data management platform.

These articles focus on:

1. [Part 1 - Integrating Amazon FSx for NetApp ONTAP \(FSx ONTAP\) as a private S3 bucket into AWS SageMaker](#)
2. [Part 2 - Leveraging Amazon FSx for NetApp ONTAP \(FSx ONTAP\) as a Data Source for Model Training in SageMaker](#)
3. [Part 3 - Building A Simplified MLOps Pipeline \(CI/CT/CD\)](#)

By the end of this section, you will have gained a solid understanding of how to use FSx ONTAP to streamline MLOps processes.

## Part 1 - Integrating Amazon FSx for NetApp ONTAP (FSx ONTAP) as a private S3 bucket into AWS SageMaker

This section provides a guide on configuring FSx ONTAP as a private S3 bucket using AWS SageMaker.

### Introduction

Using SageMaker as an example, this page provides guidance on configuring FSx ONTAP as a private S3 bucket.


For more information about FSx ONTAP, please take a look at this presentation ([Video Link](#))

### User Guide


#### Server creation

##### Create a SageMaker Notebook Instance

1. Open AWS console. In the search panel, search SageMaker and click the service **Amazon SageMaker**.



2. Open the **Notebook instances** under Notebook tab, click the orange button **Create notebook instance**.



3. In the creation page,  
Enter the **Notebook instance name**  
Expand the **Network** panel  
Leave other entries default and select a **VPC**, **Subnet**, and **Security group(s)**. (This **VPC** and **Subnet** will be used to create FSx ONTAP file system later)  
Click the orange button **Create notebook instance** at the bottom right.

Amazon SageMaker > Notebook instances > Create notebook instance

## Create notebook instance

Amazon SageMaker provides pre-built fully managed notebook instances that run Jupyter notebooks. The notebook instances include example code for common model training and hosting exercises. [Learn more](#)

### Notebook instance settings

Notebook instance name  
fsxn-demo

Maximum of 63 alphanumeric characters. Can include hyphens (-), but not spaces. Must be unique within your account in an AWS Region.

Notebook instance type  
ml.t3.medium

Elastic Inference [Learn more](#)  
none

Platform identifier [Learn more](#)  
Amazon Linux 2, Jupyter Lab 3

► Additional configuration

### Permissions and encryption

IAM role  
Notebook instances require permissions to call other services including SageMaker and S3. Choose a role or let us create a role with the [AmazonSageMakerFullAccess](#) IAM policy attached.

AmazonSageMakerServiceCatalogProductsUseRole

Create role using the role creation wizard

Root access - optional  
☒ Enable - Give users root access to the notebook.  
☐ Disable - Don't give users root access to the notebook.  
 Lifecycle configurations always have root access.

Encryption key - optional  
 Encrypt your notebook data. Choose an existing KMS key or enter a key's ARN.

No Custom Encryption

### ▼ Network - optional

VPC - optional  
Default vpc-0df3956ab1fca2ec9 (172.31.0.0/16)

Subnet  
 Choose a subnet in an availability zone supported by Amazon SageMaker.

subnet-00060df0d9f562672 (172.31.16.0/20) | us-east-1a

Security group(s)  
sg-0a39b3985770e9256 (default) X

Direct internet access  
☒ Enable — Access the internet directly through Amazon SageMaker.  
☐ Disable — Access the internet through a VPC.  
 To train or host models from a notebook, you need internet access. To enable internet access, make sure that your VPC has a NAT gateway and your security group allows outbound connections. [Learn more](#)


► Git repositories - optional

► Tags - optional


Cancel Create notebook instance

## Create an FSx ONTAP File System


1. Open AWS console. In the search panel, search Fsx and click the service **FSx**.




2. Click **Create file system**.



3. Select the first card **FSx ONTAP** and click **Next**.



4. In the details configuration page.
- a. Select the **Standard create** option.



- b. Enter the **File system name** and the **SSD storage capacity**.

## File system details

File system name - optional [Info](#)

fsxn-demo

Maximum of 256 Unicode letters, whitespace, and numbers, plus + - = . \_ : /

Deployment type [Info](#)

- ☒ Multi-AZ  
☐ Single-AZ

SSD storage capacity [Info](#)

1024

GiB

Minimum 1024 GiB; Maximum 192 TiB.

Provisioned SSD IOPS

Amazon FSx provides 3 IOPS per GiB of storage capacity. You can also provision additional SSD IOPS as needed.

- ☒ Automatic (3 IOPS per GiB of SSD storage)  
☐ User-provisioned

Throughput capacity [Info](#)

The sustained speed at which the file server hosting your file system can serve data. The file server can also burst to higher speeds for periods of time.

- ☒ Recommended throughput capacity  
128 MB/s  
☐ Specify throughput capacity

c. Make sure to use the **VPC** and **subnet** same to the **SageMaker Notebook** instance.



## Network & security

### Virtual Private Cloud (VPC) [Info](#)

Specify the VPC from which your file system is accessible.

vpc-0df3956ab1fca2ec9 (CIDR: 172.31.0.0/16) ▼

### VPC Security Groups [Info](#)

Specify VPC Security Groups to associate with your file system's network interfaces.

Choose VPC security group(s) ▼

sg-0a39b3985770e9256 (default) ✕

### Preferred subnet [Info](#)

Specify the preferred subnet for your file system.

subnet-00060df0d0f562672 (us-east-1a | use1-az4) ▼

### Standby subnet

subnet-02b029f24d03a4af2 (us-east-1b | use1-az6) ▼

### VPC route tables [Info](#)

Specify the VPC route tables to associate with your file system.

☒ VPC's main route table

☐ Select one or more VPC route tables

### Endpoint IP address range [Info](#)

Specify the IP address range in which the endpoints to access your file system will be created

☒ Unallocated IP address range from your VPC

Simplest option for access from other AWS services or peered / on-premises networks

☐ Floating IP address range outside your VPC

☐ Enter an IP address range

- d. Enter the **Storage virtual machine** name and **Specify a password** for your SVM (storage virtual machine).

### Default storage virtual machine configuration

Storage virtual machine name

Info

fsxn-svm-demo

SVM administrative password

Password for this SVM's "vsadmin" user, which you can use to access the ONTAP CLI or REST API. You can provide a password later if you don't provide one now.

☐ Don't specify a password

☒ Specify a password

Password

.....

Confirm password

.....

Volume security style

The security style of the volume determines whether preference is given to NTFS or UNIX ACLs for multi-protocol access. The MIXED mode is not required for multi-protocol access and is only recommended for advanced users.

Unix (Linux)

Active Directory

Joining an Active Directory enables access from Windows and MacOS clients over the SMB protocol.

☒ Do not join an Active Directory

☐ Join an Active Directory

e. Leave other entries default and click the orange button **Next** at the bottom right.

► Backup and maintenance - optional

► Tags - optional


Cancel

Back


Next

f. Click the orange button **Create file system** at the bottom right of the review page.

8




5. It may takes about **20-40 minutes** to spin up the FSx file system.



## Server Configuration

### ONTAP Configuration

1. Open the created FSx file system. Please make sure the status is **Available**.



2. Select the **Administration** tab and keep the **Management endpoint - IP address** and **ONTAP administrator username**.

**Amazon FSx** ×

File systems  
Volumes  
Caches  
Backups

▼ **ONTAP**  
Storage virtual machines

▼ **OpenZFS**  
Snapshots

FSx on Service Quotas [🔗](#)

[FSx](#) > [File systems](#) > fs-08b2dec260faeca07

**fsxn-demo (fs-08b2dec260faeca07)** Attach Actions ▼

▼ **Summary**

File system ID fs-08b2dec260faeca07 <a href="#">🔗</a>	SSD storage capacity 1024 GiB <span>Update</span>	Availability Zones us-east-1a (Preferred) <a href="#">🔗</a> us-east-1b (Standby) <a href="#">🔗</a>
Lifecycle state 🕒 Creating	Throughput capacity 128 MB/s <span>Update</span>	Creation time 2023-09-28T14:41:50-07:00
File system type ONTAP	Provisioned IOPS 3072 <span>Update</span>	
Deployment type Multi-AZ		

< [Network & security](#) | [Monitoring & performance](#) | **[Administration](#)** | [Storage virtual machines](#) >

**ONTAP administration**

Management endpoint - DNS name management.fs-08b2dec260faeca07.fsx.us-east-1.amazonaws.com <a href="#">🔗</a>	Management endpoint - IP address 172.31.255.250 <a href="#">🔗</a>	ONTAP administrator username fsxadmin <a href="#">🔗</a>
Inter-cluster endpoint - DNS name intercluster.fs-08b2dec260faeca07.fsx.us-east-1.amazonaws.com <a href="#">🔗</a>	Inter-cluster endpoint - IP address 172.31.31.157 <a href="#">🔗</a> 172.31.32.38 <a href="#">🔗</a>	ONTAP administrator password <span>Update</span>

3. Open the created **SageMaker Notebook instance** and click **Open JupyterLab**.

**Amazon SageMaker** ×


Getting started  
Studio  
Studio Lab [🔗](#)  
Canvas  
RStudio  
TensorBoard

[Amazon SageMaker](#) > Notebook instances


**Notebook instances** [Info](#) 🔄 Actions ▼ Create notebook instance

	Name ▼	Instance	Creation time ▼	Last updated	Status ▼	Lifecycle config	Actions
<input type="radio"/>	fsxn-demo	ml.t3.medium	9/28/2023, 1:47:27 PM	9/28/2023, 1:50:28 PM	InService		<a href="#">Open Jupyter</a>   <a href="#">Open JupyterLab</a>

4. In the Jupyter Lab page, open a new **Terminal**.



- Enter the ssh command `ssh <admin user name>@<ONTAP server IP>` to login to the FSx ONTAP file system. (The user name and IP address are retrieved from the step 2)  
Please use the password used when creating the **Storage virtual machine**.



- Execute the commands in the following order.  
We use **fsxn-ontap** as the name for the **FSx ONTAP private S3 bucket name**.  
Please use the **storage virtual machine name** for the **-vserver** argument.

```
vserver object-store-server create -vserver fsxn-svm-demo -object-store
-server fsx_s3 -is-http-enabled true -is-https-enabled false

vserver object-store-server user create -vserver fsxn-svm-demo -user
s3user

vserver object-store-server group create -name s3group -users s3user
-policies FullAccess

vserver object-store-server bucket create fsxn-ontap -vserver fsxn-svm-
demo -type nas -nas-path /vol1
```

```

sh-4.2$ ssh fsxadmin@172.31.255.250
Password:
Last login time: 9/28/2023 22:29:34
FsxId08b2dec260faeca07::> vserver object-store-server create -vserver fsxn-svm-demo -object-store-server fsx_s3 -is-http-enabled true -is-https-enabled false
FsxId08b2dec260faeca07::> vserver object-store-server user create -vserver fsxn-svm-demo -user s3user
FsxId08b2dec260faeca07::> vserver object-store-server group create -name s3group -users s3user -policies FullAccess
FsxId08b2dec260faeca07::> vserver object-store-server bucket create fsxn-ontap -vserver fsxn-svm-demo -type nas -nas-path /voll
FsxId08b2dec260faeca07::>

```

7. Execute the below commands to retrieve the endpoint IP and credentials for FSx ONTAP private S3.

```

network interface show -vserver fsxn-svm-demo -lif nfs_smb_management_1

set adv

vserver object-store-server user show

```

8. Keep the endpoint IP and credential for future use.

```

sh-4.2$ ssh fsxadmin@172.31.255.250
Password:
Last login time: 9/28/2023 22:32:42
FsxId08b2dec260faeca07::> network interface show -vserver fsxn-svm-demo -lif nfs_smb_management_1

Vserver Name: fsxn-svm-demo
Logical Interface Name: nfs_smb_management_1
Service Policy: default-data-files
Service List: data-core, data-nfs, data-cifs,
management-ssh, management-https,
data-s3-server, data-dns-server
(DEPRECATED)-Role: data
Data Protocol: nfs, cifs, s3
Network Address: 172.31.255.192
Netmask: 255.255.255.192
Bits in the Netmask: 26
Is VIP LIF: false
Subnet Name: -
Home Node: FsxId08b2dec260faeca07-01
Home Port: e0e
Current Node: FsxId08b2dec260faeca07-01
Current Port: e0e
Operational Status: up
Extended Status: -
Is Home: true
Administrative Status: up
Failover Policy: system-defined
(DEPRECATED)-Firewall Policy: data
Auto Revert: true
Fully Qualified DNS Zone Name: none
DNS Query Listen Enable: false
Failover Group Name: Fsxn
FCP WWPN: -
Address family: ipv4
Comment: -
IPspace of LIF: Default
Is Dynamic DNS Update Enabled?: true
Probe-port for Cloud Load Balancer: -
Broadcast Domain: Fsxn
Vserver Type: data
Required RDMA offload protocols: -

FsxId08b2dec260faeca07::> set adv

Warning: These advanced commands are potentially dangerous; use them only when directed to do so by NetApp personnel.
Do you want to continue? {y|n}: y

FsxId08b2dec260faeca07::> vserver object-store-server user show
Vserver  User      ID      Access Key      Secret Key
-----  -
fsxn-svm-demo
  root      0      -              -
  Comment: Root User
fsxn-svm-demo
  s3user    1      AWS Access Key Id  AWS Secret Access Key


2 entries were displayed.

FsxId08b2dec260faeca07::>

```

## Client Configuration

1. In SageMaker Notebook instance, create a new Jupyter notebook.



2. Use the below code as a work around solution to upload files to FSx ONTAP private S3 bucket. For a comprehensive code example please refer to this notebook.

[fsxn\\_demo.ipynb](#)

```
# Setup configurations
# ----- Manual configurations -----
seed: int = 77 # Random
seed
bucket_name: str = 'fsxn-ontap' # The bucket
name in ONTAP
aws_access_key_id = '<Your ONTAP bucket key id>' # Please get
this credential from ONTAP
aws_secret_access_key = '<Your ONTAP bucket access key>' # Please get
this credential from ONTAP
fsx_endpoint_ip: str = '<Your FSx ONTAP IP address>' # Please get
this IP address from FSx ONTAP
# ----- Manual configurations -----

# Workaround
## Permission patch
!mkdir -p vol1
!sudo mount -t nfs $fsx_endpoint_ip:/vol1 /home/ec2-user/SageMaker/vol1
!sudo chmod 777 /home/ec2-user/SageMaker/vol1

## Authentication for FSx ONTAP as a Private S3 Bucket
!aws configure set aws_access_key_id $aws_access_key_id
```

```

!aws configure set aws_secret_access_key $aws_secret_access_key

## Upload file to the FSx ONTAP Private S3 Bucket
%%capture
local_file_path: str = <Your local file path>

!aws s3 cp --endpoint-url http://$fsx_endpoint_ip /home/ec2-user
/SageMaker/$local_file_path s3://$bucket_name/$local_file_path

# Read data from FSx ONTAP Private S3 bucket
## Initialize a s3 resource client
import boto3

# Get session info
region_name = boto3.session.Session().region_name

# Initialize Fsx S3 bucket object
# --- Start integrating SageMaker with FSXN ---
# This is the only code change we need to incorporate SageMaker with
FSXN
s3_client: boto3.client = boto3.resource(
    's3',
    region_name=region_name,
    aws_access_key_id=aws_access_key_id,
    aws_secret_access_key=aws_secret_access_key,
    use_ssl=False,
    endpoint_url=f'http://{fsx_endpoint_ip}',
    config=boto3.session.Config(
        signature_version='s3v4',
        s3={'addressing_style': 'path'}
    )
)
# --- End integrating SageMaker with FSXN ---

## Read file byte content
bucket = s3_client.Bucket(bucket_name)

binary_data = bucket.Object(data.filename).get()['Body']

```

This concludes the integration between FSx ONTAP and the SageMaker instance.

## Useful debugging checklist

- Ensure that the SageMaker Notebook instance and FSx ONTAP file system are in the same VPC.
- Remember to run the **set dev** command on ONTAP to set the privilege level to **dev**.



## FAQ (As of Sep 27, 2023)

Q: Why am I getting the error "**An error occurred (NotImplemented) when calling the CreateMultipartUpload operation: The s3 command you requested is not implemented**" when uploading files to FSx ONTAP?

A: As a private S3 bucket, FSx ONTAP supports uploading files up to 100MB. When using the S3 protocol, files larger than 100MB are divided into 100MB chunks, and the 'CreateMultipartUpload' function is called. However, the current implementation of FSx ONTAP private S3 does not support this function.

Q: Why am I getting the error "**An error occurred (AccessDenied) when calling the PutObject operations: Access Denied**" when uploading files to FSx ONTAP?

A: To access the FSx ONTAP private S3 bucket from a SageMaker Notebook instance, switch the AWS credentials to the FSx ONTAP credentials. However, granting write permission to the instance requires a workaround solution that involves mounting the bucket and running the 'chmod' shell command to change the permissions.

Q: How can I integrate the FSx ONTAP private S3 bucket with other SageMaker ML services?

A: Unfortunately, the SageMaker services SDK does not provide a way to specify the endpoint for the private S3 bucket. As a result, FSx ONTAP S3 is not compatible with SageMaker services such as Sagemaker Data Wrangler, Sagemaker Clarify, Sagemaker Glue, Sagemaker Athena, Sagemaker AutoML, and others.

## Part 2 - Leveraging AWS Amazon FSx for NetApp ONTAP (FSx ONTAP) as a Data Source for Model Training in SageMaker

This article is a tutorial on using Amazon FSx for NetApp ONTAP (FSx ONTAP) for training PyTorch models in SageMaker, specifically for a tire quality classification project.

### Introduction


This tutorial offers a practical example of a computer vision classification project, providing hands-on experience in building ML models that utilize FSx ONTAP as the data source within the SageMaker environment. The project focuses on using PyTorch, a deep learning framework, to classify tire quality based on tire images. It emphasizes the development of machine learning models using FSx ONTAP as the data source in Amazon SageMaker.

### What is FSx ONTAP

Amazon FSx ONTAP is indeed a fully managed storage solution offered by AWS. It leverages NetApp's ONTAP file system to provide reliable and high-performance storage. With support for protocols like NFS, SMB, and iSCSI, it allows seamless access from different compute instances and containers. The service is designed to deliver exceptional performance, ensuring fast and efficient data operations. It also offers high availability and durability, ensuring that your data remains accessible and protected. Additionally, the storage capacity of Amazon FSx ONTAP is scalable, allowing you to easily adjust it according to your needs.

### Prerequisite

## Network Environment




FSx ONTAP (Amazon FSx ONTAP) is an AWS storage service. It includes a file system running on the NetApp ONTAP system and an AWS-managed system virtual machine (SVM) that connects to it. In the provided diagram, the NetApp ONTAP server managed by AWS is located outside the VPC. The SVM serves as the intermediary between SageMaker and the NetApp ONTAP system, receiving operation requests from SageMaker and forwarding them to the underlying storage. To access FSx ONTAP, SageMaker must be placed within the same VPC as the FSx ONTAP deployment. This configuration ensures communication and data access between SageMaker and FSx ONTAP.

## Data Access

In real-world scenarios, data scientists typically utilize the existing data stored in FSx ONTAP to build their machine learning models. However, for demonstration purposes, since the FSx ONTAP file system is initially empty after creation, it is necessary to manually upload the training data. This can be achieved by mounting FSx ONTAP as a volume to SageMaker. Once the file system is successfully mounted, you can upload your dataset to the mounted location, making it accessible for training your models within the SageMaker environment. This approach allows you to leverage the storage capacity and capabilities of FSx ONTAP while working with SageMaker for model development and training.

The data reading process involves configuring FSx ONTAP as a private S3 bucket. To learn the detailed configuration instructions, please refer to [Part 1 - Integrating Amazon FSx for NetApp ONTAP \(FSx ONTAP\) as a private S3 bucket into AWS SageMaker](#)

## Integration Overview



The workflow of using training data in FSx ONTAP to build a deep learning model in SageMaker can be summarized into three main steps: data loader definition, model training, and deployment. At a high level, these steps form the foundation of an MLOps pipeline. However, each step involves several detailed sub-steps for a comprehensive implementation. These sub-steps encompass various tasks such as data preprocessing, dataset splitting, model configuration, hyperparameter tuning, model evaluation, and model deployment. These steps ensure a thorough and effective process for building and deploying deep learning models using training data from FSx ONTAP within the SageMaker environment.

## Step-by-Step Integration

### Data Loader

In order to train a PyTorch deep learning network with data, a data loader is created to facilitate the feeding of data. The data loader not only defines the batch size but also determines the procedure for reading and preprocessing each record within the batch. By configuring the data loader, we can handle the processing of data in batches, enabling training of the deep learning network.

The data loader consists of 3 parts.

### Preprocessing Function

```
from torchvision import transforms

preprocess = transforms.Compose([
    transforms.ToTensor(),
    transforms.Resize((224,224)),
    transforms.Normalize(
        mean=[0.485, 0.456, 0.406],
        std=[0.229, 0.224, 0.225]
    )
])
```

The above code snippet demonstrates the definition of image preprocessing transformations using the **torchvision.transforms** module. In this tutorial, the **preprocess** object is created to apply a series of transformations. Firstly, the **ToTensor()** transformation converts the image into a tensor representation. Subsequently, the **Resize 224,224** transformation resizes the image to a fixed size of 224x224 pixels. Finally, the **Normalize()** transformation normalizes the tensor values by subtracting the mean and dividing by the standard deviation along each channel. The mean and standard deviation values used for normalization are

commonly employed in pre-trained neural network models. Overall, this code prepares the image data for further processing or input into a pre-trained model by converting it to a tensor, resizing it, and normalizing the pixel values.

### The PyTorch Dataset Class

```
import torch
from io import BytesIO
from PIL import Image

class FSxNImageDataset(torch.utils.data.Dataset):
    def __init__(self, bucket, prefix='', preprocess=None):
        self.image_keys = [
            s3_obj.key
            for s3_obj in list(bucket.objects.filter(Prefix=prefix).all())
        ]
        self.preprocess = preprocess

    def __len__(self):
        return len(self.image_keys)

    def __getitem__(self, index):
        key = self.image_keys[index]
        response = bucket.Object(key)

        label = 1 if key[13:].startswith('defective') else 0

        image_bytes = response.get()['Body'].read()
        image = Image.open(BytesIO(image_bytes))
        if image.mode == 'L':
            image = image.convert('RGB')

        if self.preprocess is not None:
            image = self.preprocess(image)
        return image, label
```

This class provides functionality to obtain the total number of records in the dataset and defines the method for reading data for each record. Within the **getitem** function, the code utilizes the boto3 S3 bucket object to retrieve the binary data from FSx ONTAP. The code style for accessing data from FSx ONTAP is similar to reading data from Amazon S3. The subsequent explanation delves into the creation process of the private S3 object **bucket**.

### FSx ONTAP as a private S3 repository

```

seed = 77 # Random seed
bucket_name = '<Your ONTAP bucket name>' # The bucket
name in ONTAP
aws_access_key_id = '<Your ONTAP bucket key id>' # Please get
this credential from ONTAP
aws_secret_access_key = '<Your ONTAP bucket access key>' # Please get
this credential from ONTAP
fsx_endpoint_ip = '<Your FSx ONTAP IP address>' # Please
get this IP address from FSXN

```

```

import boto3

# Get session info
region_name = boto3.session.Session().region_name

# Initialize Fsx S3 bucket object
# --- Start integrating SageMaker with FSXN ---
# This is the only code change we need to incorporate SageMaker with FSXN
s3_client: boto3.client = boto3.resource(
    's3',
    region_name=region_name,
    aws_access_key_id=aws_access_key_id,
    aws_secret_access_key=aws_secret_access_key,
    use_ssl=False,
    endpoint_url=f'http://{fsx_endpoint_ip}',
    config=boto3.session.Config(
        signature_version='s3v4',
        s3={'addressing_style': 'path'}
    )
)
# s3_client = boto3.resource('s3')
bucket = s3_client.Bucket(bucket_name)
# --- End integrating SageMaker with FSXN ---

```

To read data from FSx ONTAP in SageMaker, a handler is created that points to the FSx ONTAP storage using the S3 protocol. This allows FSx ONTAP to be treated as a private S3 bucket. The handler configuration includes specifying the IP address of the FSx ONTAP SVM, the bucket name, and the necessary credentials. For a comprehensive explanation on obtaining these configuration items, please refer to the document at [Part 1 - Integrating Amazon FSx for NetApp ONTAP \(FSx ONTAP\) as a private S3 bucket into AWS SageMaker](#).

In the example mentioned above, the bucket object is used to instantiate the PyTorch dataset object. The dataset object will be further explained in the subsequent section.

## The PyTorch Data Loader

```
from torch.utils.data import DataLoader
torch.manual_seed(seed)

# 1. Hyperparameters
batch_size = 64

# 2. Preparing for the dataset
dataset = FSxNImageDataset(bucket, 'dataset/tyre', preprocess=preprocess)

train, test = torch.utils.data.random_split(dataset, [1500, 356])

data_loader = DataLoader(dataset, batch_size=batch_size, shuffle=True)
```

In the example provided, a batch size of 64 is specified, indicating that each batch will contain 64 records. By combining the PyTorch **Dataset** class, the preprocessing function, and the training batch size, we obtain the data loader for training. This data loader facilitates the process of iterating through the dataset in batches during the training phase.

## Model Training

```
from torch import nn

class TyreQualityClassifier(nn.Module):
    def __init__(self):
        super().__init__()
        self.model = nn.Sequential(
            nn.Conv2d(3, 32, (3, 3)),
            nn.ReLU(),
            nn.Conv2d(32, 32, (3, 3)),
            nn.ReLU(),
            nn.Conv2d(32, 64, (3, 3)),
            nn.ReLU(),
            nn.Flatten(),
            nn.Linear(64 * (224 - 6) * (224 - 6), 2)
        )
    def forward(self, x):
        return self.model(x)
```

```

import datetime

num_epochs = 2
device = torch.device('cuda' if torch.cuda.is_available() else 'cpu')

model = TyreQualityClassifier()
fn_loss = torch.nn.CrossEntropyLoss()
optimizer = torch.optim.Adam(model.parameters(), lr=1e-3)

model.to(device)
for epoch in range(num_epochs):
    for idx, (X, y) in enumerate(data_loader):
        X = X.to(device)
        y = y.to(device)

        y_hat = model(X)

        loss = fn_loss(y_hat, y)
        optimizer.zero_grad()
        loss.backward()
        optimizer.step()
        current_time = datetime.datetime.now().strftime("%Y-%m-%d
%H:%M:%S")
        print(f"Current Time: {current_time} - Epoch [{epoch+1}]/
{num_epochs}] - Batch [{idx + 1}] - Loss: {loss}", end='\n')

```

This code implements a standard PyTorch training process. It defines a neural network model called **TyreQualityClassifier** using convolutional layers and a linear layer to classify tire quality. The training loop iterates over data batches, computes the loss, and updates the model's parameters using backpropagation and optimization. Additionally, it prints the current time, epoch, batch, and loss for monitoring purposes.

## Model Deployment

### Deployment

```

import io
import os
import tarfile
import sagemaker

# 1. Save the PyTorch model to memory
buffer_model = io.BytesIO()
traced_model = torch.jit.script(model)
torch.jit.save(traced_model, buffer_model)

# 2. Upload to AWS S3
sagemaker_session = sagemaker.Session()
bucket_name_default = sagemaker_session.default_bucket()
model_name = f'tyre_quality_classifier.pth'

# 2.1. Zip PyTorch model into tar.gz file
buffer_zip = io.BytesIO()
with tarfile.open(fileobj=buffer_zip, mode="w:gz") as tar:
    # Add PyTorch pt file
    file_name = os.path.basename(model_name)
    file_name_with_extension = os.path.splitext(file_name)[-1]
    tarinfo = tarfile.TarInfo(file_name_with_extension)
    tarinfo.size = len(buffer_model.getbuffer())
    buffer_model.seek(0)
    tar.addfile(tarinfo, buffer_model)

# 2.2. Upload the tar.gz file to S3 bucket
buffer_zip.seek(0)
boto3.resource('s3') \
    .Bucket(bucket_name_default) \
    .Object(f'pytorch/{model_name}.tar.gz') \
    .put(Body=buffer_zip.getvalue())

```

The code saves the PyTorch model to **Amazon S3** because SageMaker requires the model to be stored in S3 for deployment. By uploading the model to **Amazon S3**, it becomes accessible to SageMaker, allowing for the deployment and inference on the deployed model.

```

import time
from sagemaker.pytorch import PyTorchModel
from sagemaker.predictor import Predictor
from sagemaker.serializers import IdentitySerializer
from sagemaker.deserializers import JSONDeserializer

class TyreQualitySerializer(IdentitySerializer):

```



```

CONTENT_TYPE = 'application/x-torch'

def serialize(self, data):
    transformed_image = preprocess(data)
    tensor_image = torch.Tensor(transformed_image)

    serialized_data = io.BytesIO()
    torch.save(tensor_image, serialized_data)
    serialized_data.seek(0)
    serialized_data = serialized_data.read()

    return serialized_data

class TyreQualityPredictor(Predictor):
    def __init__(self, endpoint_name, sagemaker_session):
        super().__init__(
            endpoint_name,
            sagemaker_session=sagemaker_session,
            serializer=TyreQualitySerializer(),
            deserializer=JSONDeserializer(),
        )

sagemaker_model = PyTorchModel(
    model_data=f's3://{bucket_name_default}/pytorch/{model_name}.tar.gz',
    role=sagemaker.get_execution_role(),
    framework_version='2.0.1',
    py_version='py310',
    predictor_cls=TyreQualityPredictor,
    entry_point='inference.py',
    source_dir='code',
)

timestamp = int(time.time())
pytorch_endpoint_name = '{}-{}-{}'.format('tyre-quality-classifier', 'pt',
timestamp)
sagemaker_predictor = sagemaker_model.deploy(
    initial_instance_count=1,
    instance_type='ml.p3.2xlarge',
    endpoint_name=pytorch_endpoint_name
)

```

This code facilitates the deployment of a PyTorch model on SageMaker. It defines a custom serializer, **TyreQualitySerializer**, which preprocesses and serializes input data as a PyTorch tensor. The **TyreQualityPredictor** class is a custom predictor that utilizes the defined serializer and a **JSONDeserializer**. The code also creates a **PyTorchModel** object to specify the model's S3 location, IAM role, framework version, and entry point for inference. The code generates a timestamp and constructs an endpoint name based on the

model and timestamp. Finally, the model is deployed using the deploy method, specifying the instance count, instance type, and generated endpoint name. This enables the PyTorch model to be deployed and accessible for inference on SageMaker.

**Inference**

```
image_object = list(bucket.objects.filter('dataset/tyre'))[0].get()
image_bytes = image_object['Body'].read()

with Image.open(with Image.open(BytesIO(image_bytes)) as image:
    predicted_classes = sagemaker_predictor.predict(image)

print(predicted_classes)
```

This is the example of using the deployed endpoint to do the inference.

### Part 3 - Building A Simplified MLOps Pipeline (CI/CT/CD)

This article provides a guide to building an MLOps pipeline with AWS services, focusing on automated model retraining, deployment, and cost optimization.

**Introduction**

In this tutorial, you will learn how to leverage various AWS services to construct a simple MLOps pipeline that encompasses Continuous Integration (CI), Continuous Training (CT), and Continuous Deployment (CD). Unlike traditional DevOps pipelines, MLOps requires additional considerations to complete the operational cycle. By following this tutorial, you will gain insights into incorporating CT into the MLOps loop, enabling continuous training of your models and seamless deployment for inference. The tutorial will guide you through the process of utilizing AWS services to establish this end-to-end MLOps pipeline.

**Manifest**


Functionality	Name	Comment
Data storage	AWS FSx ONTAP	Refer to <a href="#">Part 1 - Integrating Amazon FSx for NetApp ONTAP (FSx ONTAP) as a private S3 bucket into AWS SageMaker</a> .
Data science IDE	AWS SageMaker	This tutorial is based on the Jupyter notebook presented in <a href="#">Part 2 - Leveraging Amazon FSx for NetApp ONTAP (FSx ONTAP) as a Data Source for Model Training in SageMaker</a> .
Function to trigger the MLOps pipeline	AWS Lambda function	-
Cron job trigger	AWS EventBridge	-
Deep learning framework	PyTorch	-

Functionality	Name	Comment
AWS Python SDK	boto3	-
Programming Language	Python	v3.10

## Prerequisite

- An pre-configured FSx ONTAP file system. This tutorial utilizes data stored in FSx ONTAP for the training process.
- A **SageMaker Notebook instance** that is configured to share the same VPC as the FSx ONTAP file system mentioned above.
- Before triggering the **AWS Lambda function**, ensure that the **SageMaker Notebook instance** is in **stopped** status.
- The **ml.g4dn.xlarge** instance type is required to leverage the GPU acceleration necessary for the computations of deep neural networks.

## Architecture



This MLOps pipeline is a practical implementation that utilizes a cron job to trigger a serverless function, which in turn executes an AWS service registered with a lifecycle callback function. The **AWS EventBridge** acts as the cron job. It periodically invokes an **AWS Lambda function** responsible for retraining and redeploying the model. This process involves spinning up the **AWS SageMaker Notebook instance** to perform the necessary tasks.

## Step-by-Step Configuration

### Lifecycle configurations

To configure the lifecycle callback function for the AWS SageMaker Notebook instance, you would utilize **Lifecycle configurations**. This service allow you to define the necessary actions to be performed during when spinning up the notebook instance. Specifically, a shell script can be implemented within the **Lifecycle configurations** to automatically shut down the notebook instance once the training and deployment processes are completed. This is a required configuration as the cost is one of the major consideration in MLOps.

It's important to note that the configuration for **Lifecycle configurations** needs to be set up in advance. Therefore, it is recommended to prioritize configuring this aspect before proceeding with the other MLOps pipeline setup.

1. To set up a Lifecycle configurations, open the **Sagemaker** panel and navigate to **Lifecycle configurations** under the section **Admin configurations**.

aws

Services

Search

S3

Amazon SageMaker

×

Getting started

Studio

Studio Lab

Canvas

RStudio

TensorBoard

Profiler

▼ Admin configurations

Domains

Role manager

Images

Lifecycle configurations

SageMaker dashboard

Search

► JumpStart

Amazon SageMaker > Domains

Domains

Info

A domain includes an associated Amazon SageMaker Studio notebook instance. Each domain receives a personal and private Amazon SageMaker endpoint.

► Domain structure diagram


Domains (4)

Info

Find domain name

	Name
<input type="radio"/>	rdsm1-east-1
<input type="radio"/>	rdsm1-east-2
<input type="radio"/>	rdsm1-east-3
<input type="radio"/>	rdsm1-east-4

2. Select the **Notebook Instance** tab and click the **Create configuration** button



3. Paste the below code to the entry area.

```
#!/bin/bash

set -e
sudo -u ec2-user -i <<'EOF'
# 1. Retraining and redeploying the model
NOTEBOOK_FILE=/home/ec2-user/SageMaker/tyre_quality_classification_local_training.ipynb
echo "Activating conda env"
source /home/ec2-user/anaconda3/bin/activate pytorch_p310
nohup jupyter nbconvert "$NOTEBOOK_FILE"
--ExecutePreprocessor.kernel_name=python --execute --to notebook &
nbconvert_pid=$!
conda deactivate

# 2. Scheduling a job to shutdown the notebook to save the cost
PYTHON_DIR='/home/ec2-user/anaconda3/envs/JupyterSystemEnv/bin/python3.10'
echo "Starting the autostop script in cron"
(crontab -l 2>/dev/null; echo "*/5 * * * * bash -c 'if ps -p
$nbconvert_pid > /dev/null; then echo \"Notebook is still running.\" >>
/var/log/jupyter.log; else echo \"Notebook execution completed.\" >>
/var/log/jupyter.log; $PYTHON_DIR -c \"import boto3;boto3.client(
\'sagemaker\').stop_notebook_instance(NotebookInstanceName=get_notebook_
name())\" >> /var/log/jupyter.log; fi')\" | crontab -
EOF
```

4. This script executes the Jupyter Notebook, which handles the retraining and redeployment of the model for inference. After the execution is complete, the notebook will automatically shut down within 5 minutes. To learn more about the problem statement and the code implementation, please refer to [Part 2 - Leveraging Amazon FSx for NetApp ONTAP \(FSx ONTAP\) as a Data Source for Model Training in SageMaker](#).

aws Services Search [Option+S]

S3

Amazon SageMaker > Lifecycle configurations > Create lifecycle configuration

## Create lifecycle configuration

### Configuration setting

Name

fsxn-demo-lifecycle-callback

Alphanumeric characters and "-", no spaces. Maximum 63 characters.

### Scripts

**Start notebook** | Create notebook


This script will be run each time an associated notebook instance is started, including during initial creation. If the associated notebook instance is already started, it will be run the next time it is stopped and started. [a curated list of sample scripts](#)

```
1 #!/bin/bash
2
3 set -e
4 sudo -u ec2-user -i <<'EOF'
5 # 1. Retraining and redeploying the model
6 NOTEBOOK_FILE=/home/ec2-user/SageMaker/tyre_quality_classification_local_training.ipynb
7 echo "Activating conda env"
8 source /home/ec2-user/anaconda3/bin/activate pytorch_p310
9 nohup jupyter nbconvert "$NOTEBOOK_FILE" --ExecutePreprocessor.kernel_name=python --execute --to n
10 nbconvert_pid=$!
11 conda deactivate
12
13 # 2. Scheduling a job to shutdown the notebook to save the cost
14 PYTHON_DIR='/home/ec2-user/anaconda3/envs/JupyterSystemEnv/bin/python3.10'
15 echo "Starting the autostop script in cron"
16 (crontab -l 2>/dev/null; echo "*/5 * * * * bash -c 'if ps -p $nbconvert_pid > /dev/null; then echo
17 EOF
```


Cancel Create configuration

CloudShell Feedback

5. After the creation, navigate to Notebook instances, select the target instance, and click **Update settings** under Actions dropdown.




6. Select the created **Lifecycle configuration** and click **Update notebook instance**.



## AWS Lambda serverless function

As mentioned earlier, the **AWS Lambda function** is responsible for spinning up the **AWS SageMaker Notebook instance**.

1. To create an **AWS Lambda function**, navigate to the respective panel, switch to the **Functions** tab, and click on **Create Function**.



2. Please file all required entries on the page and remember to switch the Runtime to **Python 3.10**.



aws Services Search [Option+S] N. Virgi AWSAdministratorAccess/kjian@

S3

Lambda > Functions > Create function

## Create function [Info](#)

AWS Serverless Application Repository applications have moved to [Create application](#).

☒ **Author from scratch**  
Start with a simple Hello World example.

☐ **Use a blueprint**  
Build a Lambda application from sample code and configuration presets for common use cases.

☐ **Container image**  
Select a container image to deploy for your function.

### Basic information

**Function name**  
Enter a name that describes the purpose of your function.

fsxn-demo-mlops

Use only letters, numbers, hyphens, or underscores with no spaces.

**Runtime** [Info](#)  
Choose the language to use to write your function. Note that the console code editor supports only Node.js, Python, and Ruby.

Python 3.10

**Architecture** [Info](#)  
Choose the instruction set architecture you want for your function code.

☒ x86\_64

☐ arm64

**Permissions** [Info](#)  
By default, Lambda will create an execution role with permissions to upload logs to Amazon CloudWatch Logs. You can customize this default role later when adding triggers.

- Please verify that the designated role has the required permission **AmazonSageMakerFullAccess** and click on the **Create function** button.

aws Services Search [Option+S] N. Virgi AWSAdministratorAccess/kjian@

S3

Use only letters, numbers, hyphens, or underscores with no spaces.

**Runtime** [Info](#)  
Choose the language to use to write your function. Note that the console code editor supports only Node.js, Python, and Ruby.

Python 3.10

**Architecture** [Info](#)  
Choose the instruction set architecture you want for your function code.

☒ x86\_64  
☐ arm64

**Permissions** [Info](#)  
By default, Lambda will create an execution role with permissions to upload logs to Amazon CloudWatch Logs. You can customize this default role later when adding triggers.

▼ **Change default execution role**

**Execution role**  
Choose a role that defines the permissions of your function. To create a custom role, go to the [IAM console](#).

☐ Create a new role with basic Lambda permissions  
☒ Use an existing role  
☐ Create a new role from AWS policy templates

**Existing role**  
Choose an existing role that you've created to be used with this Lambda function. The role must have permission to upload logs to Amazon CloudWatch Logs.

service-role/fsxn-demo-mlops-role-585jzdny

[View the fsxn-demo-mlops-role-585jzdny role](#) on the IAM console.

► **Advanced settings**

Cancel Create function

4. Select the created Lambda function. In the code tab, copy and paste the following code into the text area. This code starts the notebook instance named **fsxn-ontap**.

```
import boto3
import logging

def lambda_handler(event, context):
    client = boto3.client('sagemaker')
    logging.info('Invoking SageMaker')
    client.start_notebook_instance(NotebookInstanceName='fsxn-ontap')
    return {
        'statusCode': 200,
        'body': f'Starting notebook instance: {notebook_instance_name}'
    }
```

5. Click the **Deploy** button to apply this code change.

The screenshot shows the AWS Lambda console interface. At the top, the navigation bar includes the AWS logo, 'Services', a search bar, and the user's name 'N. Virgin'. The main content area displays the configuration for a Lambda function named 'demo-mlops'. On the left, there are buttons for '+ Add trigger' and '+ Add destination'. On the right, the 'Last modified' time is '1 minute ago', and the 'Function ARN' is 'arn:aws:lambda:us-east-1:232233133319:function:fsxn-demo-mlops'. Below this, there are tabs for 'Code', 'Test', 'Monitor', 'Configuration', 'Aliases', and 'Versions'. The 'Code source' tab is selected, showing a code editor with a Python function 'lambda\_handler'. A red arrow points to the 'Deploy' button in the top right of the code editor area. The code in the editor is as follows:

```
1 import boto3
2 import logging
3
4 def lambda_handler(event, context):
5     client = boto3.client('sagemaker')
6     logging.info('Invoking SageMaker')
7     client.start_notebook_instance(NotebookInstanceName='fsxn-ontap')
8     return {
9         'statusCode': 200,
10        'body': f'Starting notebook instance: {notebook_instance_name}'
11    }
12
```

6. To specify how to trigger this AWS Lambda function, click on the Add Trigger button.

aws Services Search [Option+S] N. Virginia AWSAdministratorAccess/kjian@netapp.


S3


Lambda > Functions > fsxn-demo-mlops

## fsxn-demo-mlops

Throttle Copy ARN Actions

▼ Function overview Info


 fsxn-demo-mlops

 Layers (0)

+ Add trigger + Add destination

Description -

Last modified 2 minutes ago

Function ARN  
 arn:aws:lambda:us-east-1:232233133319:function:fsxn-demo-mlops

Function URL [Info](#)

-

7. Select EventBridge from the dropdown menu, then click on the radio button labeled Create a new rule. In the schedule expression field, enter `rate(1 day)`, and click on the Add button to create and apply this new cron job rule to the AWS Lambda function.

aws Services Search [Option+S] N. Virginia AWSAdministratorAccess

S3

[Lambda](#) > Add trigger

## Add trigger

**Trigger configuration** [Info](#)

**EventBridge (CloudWatch Events)**  
aws asynchronous schedule management-tools

**Rule**  
Pick an existing rule, or create a new one.

☒ Create a new rule  
☐ Existing rules

**Rule name**  
Enter a name to uniquely identify your rule.

mlops-retraining-trigger

**Rule description**  
Provide an optional description for your rule.

**Rule type**  
Trigger your target based on an event pattern, or based on an automated schedule.

☐ Event pattern  
☒ Schedule expression

**Schedule expression**  
Self-trigger your target on an automated schedule using [Cron or rate expressions](#). Cron expressions are in UTC.

rate(1 day)

e.g. rate(1 day), cron(0 17 ? \* MON-FRI \*)

Lambda will add the necessary permissions for Amazon EventBridge (CloudWatch Events) to invoke your Lambda function from this trigger. [Learn more](#) about the Lambda permissions model.

Cancel Add

After completing the two-step configuration, on a daily basis, the **AWS Lambda function** will initiate the **SageMaker Notebook**, perform model retraining using the data from the **FSx ONTAP** repository, redeploy the updated model to the production environment, and automatically shut down the **SageMaker Notebook instance** to optimize cost. This ensures that the model remains up to date.

This concludes the tutorial for developing an MLOps pipeline.

## Copyright information

Copyright © 2025 NetApp, Inc. All Rights Reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means—graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system—without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

LIMITED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (b)(3) of the Rights in Technical Data -Noncommercial Items at DFARS 252.227-7013 (FEB 2014) and FAR 52.227-19 (DEC 2007).

Data contained herein pertains to a commercial product and/or commercial service (as defined in FAR 2.101) and is proprietary to NetApp, Inc. All NetApp technical data and computer software provided under this Agreement is commercial in nature and developed solely at private expense. The U.S. Government has a non-exclusive, non-transferrable, nonsublicensable, worldwide, limited irrevocable license to use the Data only in connection with and in support of the U.S. Government contract under which the Data was delivered. Except as provided herein, the Data may not be used, disclosed, reproduced, modified, performed, or displayed without the prior written approval of NetApp, Inc. United States Government license rights for the Department of Defense are limited to those rights identified in DFARS clause 252.227-7015(b) (FEB 2014).

## Trademark information

NETAPP, the NETAPP logo, and the marks listed at <http://www.netapp.com/TM> are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.