■ NetApp

Manage SVMs

ONTAP 9.14.1 REST API reference

NetApp June 13, 2024

This PDF was generated from https://docs.netapp.com/us-en/ontap-restapi-9141/ontap/svm_svms_endpoint_overview.html on June 13, 2024. Always check docs.netapp.com for the latest

Table of Contents

V	lanage SVMs	1
	SVM svms endpoint overview	1
	Retrieve SVMs and SVM properties	1
	Create and provision an SVM	C
	Delete an SVM	2
	Retrieve SVM properties	6
	Update SVM properties	6

Manage SVMs

SVM syms endpoint overview

Managing SVMs

Cluster administrators can manage any SVM bound to the cluster. In addition, SVMs can also be managed by their SVM administrators. The SVM administrator manages the SVM resources, such as volumes, protocols and services, depending on the capabilities assigned by the cluster administrator. SVM administrators cannot create, modify, or delete SVMs. The cluster administrator manages SVM create, modify, or delete operations.

While configuring CIFS, you must also configure IP interfaces and DNS. No other protocol configuration is allowed when configuring NVMe. NFS, FCP, CIFS and iSCSI protocols can be configured together.

SVM administrators might have all or some of the following administration capabilities:

- 1. Data access protocol configuration Configures data access protocols, such as NFS, CIFS, iSCSI, and Fibre Channel (FC) protocol (Fibre Channel over Ethernet included).
- 2. Services configuration Configures services such as LDAP, NIS, and DNS.
- 3. Monitoring SVM Monitors jobs, network connections, network interfaces, and SVM health.
- 4. Updating the TLS certificate for this SVM.

Retrieve SVMs and SVM properties

GET /svm/svms

Introduced In: 9.6

Retrieves a list of SVMs and individual SVM properties. This includes protocol configurations such as CIFS and NFS, export policies, name service configurations, and network services.

Important notes

- The SVM object includes a large set of fields and can be expensive to retrieve. Use this API to list the collection of SVMs, and to retrieve only the full details of individual SVMs as needed.
- It is not recommended to create or delete more than five SVMs in parallel.
- REST APIs only expose a data SVM as an SVM.

Expensive properties

There is an added computational cost to retrieving values for these properties. They are not included by default in GET results and must be explicitly requested using the fields query parameter. See Requesting specific fields to learn more.

• snapmirror.*

Related ONTAP commands

• vserver show

Examples

1. Retrieves a list of SVMs in the cluster sorted by name

```
GET "/api/svm/svms?order_by=name"
```

1. Retrieves a list of SVMs in the cluster that have the NFS protocol enabled

```
GET "/api/svm/svms?nfs.enabled=true"
```

1. Retrieves a list of SVMs in the cluster that have the CIFS protocol enabled

```
GET "/api/svm/svms?cifs.enabled=true"
```

1. Retrieves a list of SVMs in the cluster that have the S3 protocol enabled

```
GET "/api/svm/svms?s3.enabled=true"
```

5 Retrieves a list of SVMs in the cluster that have the FCP protocol allowed

```
GET "/api/svm/svms?fcp.allowed=true"
```

1. Retrieves a list of SVMs in the cluster that have the CIFS protocol allowed

```
GET "/api/svm/svms?cifs.allowed=true"
```

1. Retrieves a list of SVMs in the cluster where the NDMP protocol is specified as allowed

```
GET "/api/svm/svms?ndmp.allowed=true"
```

1. Retrieves a list of SVMs in the cluster that have the s3 protocol allowed

```
GET "/api/svm/svms?s3.allowed=true"
```

Learn more

DOC /svm/svms

Parameters

Name	Туре	In	Required	Description
nis.enabled	boolean	query	False	Filter by nis.enabled
nis.servers	string	query	False	Filter by nis.servers
nis.domain	string	query	False	Filter by nis.domain
nvme.allowed	boolean	query	False	Filter by nvme.allowed • Introduced in: 9.9
nvme.enabled	boolean	query	False	Filter by nvme.enabled
language	string	query	False	Filter by language
nfs.allowed	boolean	query	False	• Introduced in: 9.9
nfs.enabled	boolean	query	False	Filter by nfs.enabled
comment	string	query	False	Filter by comment
aggregates.name	string	query	False	Filter by aggregates.name
aggregates.uuid	string	query	False	Filter by aggregates.uuid
subtype	string	query	False	Filter by subtype
dns.servers	string	query	False	Filter by dns.servers
dns.domains	string	query	False	Filter by dns.domains
fcp.allowed	boolean	query	False	Filter by fcp.allowed • Introduced in: 9.9

Name	Туре	In	Required	Description
fcp.enabled	boolean	query	False	Filter by fcp.enabled
iscsi.allowed	boolean	query	False	Filter by iscsi.allowed • Introduced in: 9.9
iscsi.enabled	boolean	query	False	Filter by iscsi.enabled
name	string	query	False	Filter by name
ipspace.uuid	string	query	False	Filter by ipspace.uuid
ipspace.name	string	query	False	Filter by ipspace.name
ldap.base_dn	string	query	False	Filter by Idap.base_dn
Idap.servers	string	query	False	Filter by Idap.servers
ldap.enabled	boolean	query	False	Filter by Idap.enabled
ldap.bind_dn	string	query	False	Filter by Idap.bind_dn
ldap.ad_domain	string	query	False	Filter by Idap.ad_domain
uuid	string	query	False	Filter by uuid
cifs.name	string	query	False	Filter by cifs.name
cifs.ad_domain.fqdn	string	query	False	Filter by cifs.ad_domain.fqdn
cifs.ad_domain.orga nizational_unit	string	query	False	Filter by cifs.ad_domain.orga nizational_unit

Name	Туре	In	Required	Description
cifs.allowed	boolean	query	False	• Introduced in: 9.9
cifs.enabled	boolean	query	False	Filter by cifs.enabled
s3.name	string	query	False	• Introduced in: 9.7
s3.allowed	boolean	query	False	• Introduced in: 9.12
s3.enabled	boolean	query	False	• Introduced in: 9.7
ndmp.allowed	boolean	query	False	Filter by ndmp.allowed • Introduced in: 9.10
nsswitch.netgroup	string	query	False	Filter by nsswitch.netgroup
nsswitch.group	string	query	False	Filter by nsswitch.group
nsswitch.hosts	string	query	False	Filter by nsswitch.hosts
nsswitch.namemap	string	query	False	Filter by nsswitch.namemap
nsswitch.passwd	string	query	False	Filter by nsswitch.passwd

Name	Туре	In	Required	Description
qos_policy.name	string	query	False	Filter qos_policy.name • Introduced in: 9.9
qos_policy.uuid	string	query	False	Filter qos_policy.uuid • Introduced in: 9.9
max_volumes	string	query	False	• Introduced in: 9.9
fc_interfaces.name	string	query	False	Filter by fc_interfaces.name • Introduced in: 9.7
fc_interfaces.data_pr otocol	string	query	False	Filter by fc_interfaces.data_p rotocol • Introduced in: 9.7
snapshot_policy.uuid	string	query	False	Filter by snapshot_policy.uui d
snapshot_policy.na me	string	query	False	Filter by snapshot_policy.na me
state	string	query	False	Filter by state
certificate.uuid	string	query	False	Filter by certificate.uuid • Introduced in: 9.7

Name	Туре	In	Required	Description
anti_ransomware_de fault_volume_state	string	query	False	Filter by anti_ransomware_d efault_volume_state • Introduced in: 9.10
qos_adaptive_policy _group_template.na me	string	query	False	Filter by qos_adaptive_policy _group_template.na me • Introduced in: 9.13
qos_adaptive_policy _group_template.uui d	string	query	False	Filter by qos_adaptive_policy _group_template.uui d • Introduced in: 9.13
anti_ransomware_au to_switch_from_lear ning_to_enabled	boolean	query	False	Filter by anti_ransomware_a uto_switch_from_lea rning_to_enabled • Introduced in: 9.13
anti_ransomware_au to_switch_minimum_ incoming_data	string	query	False	Filter by anti_ransomware_a uto_switch_minimu m_incoming_data • Introduced in: 9.13
anti_ransomware_au to_switch_minimum_ incoming_data_perc ent	integer	query	False	Filter by anti_ransomware_a uto_switch_minimu m_incoming_data_p ercent • Introduced in: 9.13

Name	Туре	In	Required	Description
anti_ransomware_au to_switch_duration_ without_new_file_ext ension	integer	query	False	Filter by anti_ransomware_a uto_switch_duration _without_new_file_e xtension • Introduced in: 9.13
anti_ransomware_au to_switch_minimum_ learning_period	integer	query	False	Filter by anti_ransomware_a uto_switch_minimu m_learning_period • Introduced in: 9.13
anti_ransomware_au to_switch_minimum_ file_count	integer	query	False	Filter by anti_ransomware_a uto_switch_minimu m_file_count • Introduced in: 9.13
anti_ransomware_au to_switch_minimum_ file_extension	integer	query	False	Filter by anti_ransomware_a uto_switch_minimu m_file_extension • Introduced in: 9.13
auto_enable_analytics	boolean	query	False	Filter by auto_enable_analyti cs. • Introduced in: 9.12
auto_enable_activity _tracking	boolean	query	False	Filter by auto_enable_activity _tracking. • Introduced in: 9.12

Name	Туре	In	Required	Description
storage.allocated	integer	query	False	Filter by storage_allocated • Introduced in: 9.14
storage.available	integer	query	False	Filter by storage_available • Introduced in: 9.14
storage.used_perce ntage	integer	query	False	Filter by storage_used_perce ntage • Introduced in: 9.14
number_of_volumes _in_recovery_queue	integer	query	False	Filter by number_of_volumes _in_recovery_queue • Introduced in: 9.13
total_volume_size_in _recovery_queue	integer	query	False	Filter by total_volume_size_i n_recovery_queue • Introduced in: 9.13
storage.limit_thresho ld_exceeded	integer	query	False	Filter by storage.limit_thresh old_exceeded • Introduced in: 9.14
storage.limit	integer	query	False	Filter by storage.limit • Introduced in: 9.14

Name	Туре	In	Required	Description
storage.limit_thresho ld_alert	integer	query	False	Filter by storage.limit_thresh old_alert • Introduced in: 9.14
fields	array[string]	query	False	Specify the fields to return.
max_records	integer	query	False	Limit the number of records returned.
return_records	boolean	query	False	The default is true for GET calls. When set to false, only the number of records is returned. • Default value: 1
return_timeout	integer	query	False	The number of seconds to allow the call to execute before returning. When iterating over a collection, the default is 15 seconds. ONTAP returns earlier if either max records or the end of the collection is reached. • Default value: 1 • Max value: 120 • Min value: 0
order_by	array[string]	query	False	Order results by
		1,4,		specified fields and optional [asc

Response

Status: 200, Ok

Name	Туре	Description
_links	_links	
num_records	integer	Number of records
records	array[svm]	

```
" links": {
  "next": {
   "href": "/api/resourcelink"
  },
 "self": {
   "href": "/api/resourcelink"
 }
},
"num records": 1,
"records": [
    " links": {
      "self": {
       "href": "/api/resourcelink"
      }
    },
    "aggregates": [
        " links": {
          "self": {
            "href": "/api/resourcelink"
        },
        "available size": 10156560384,
        "name": "aggr1",
        "snaplock type": "string",
        "state": "string",
        "type": "string",
        "uuid": "1cd8a442-86d1-11e0-ae1c-123478563412"
     }
    "anti ransomware default volume state": "string",
    "anti ransomware incoming write threshold": "string",
    "anti ransomware incoming write threshold percent": "string",
    "certificate": {
      " links": {
       "self": {
         "href": "/api/resourcelink"
       }
      "name": "string",
      "uuid": "1cd8a442-86d1-11e0-ae1c-123478563412"
    },
```

```
"cifs": {
  " links": {
   "self": {
     "href": "/api/resourcelink"
   }
 },
  "ad domain": {
   "default site": "string",
   "fqdn": "example.com",
   "organizational unit": "string",
   "password": "string",
   "user": "string"
 },
  "domain workgroup": "string",
 "name": "CIFS1"
"comment": "string",
"dns": {
 " links": {
   "self": {
    "href": "/api/resourcelink"
   }
  },
  "domains": [
   "example.com",
   "example2.example3.com"
 ],
 "servers": [
   "10.224.65.20",
   "2001:db08:a0b:12f0::1"
 ]
},
"fc interfaces": [
   " links": {
     "self": {
       "href": "/api/resourcelink"
    },
    "data protocol": "string",
    "location": {
      "port": {
        " links": {
         "self": {
           "href": "/api/resourcelink"
```

```
},
        "name": "0a",
        "node": {
         "name": "node1"
        "uuid": "1cd8a442-86d1-11e0-ae1c-123478563412"
      }
    } ,
    "name": "lif1",
   "uuid": "1cd8a442-86d1-11e0-ae1c-123478563412"
 }
],
"fcp": {
 " links": {
   "self": {
     "href": "/api/resourcelink"
   }
  }
"ip interfaces": [
 {
    " links": {
      "self": {
       "href": "/api/resourcelink"
     }
    } ,
    "ip": {
     "address": "10.10.10.7",
     "netmask": "24"
    } ,
    "location": {
      "broadcast domain": {
       " links": {
          "self": {
           "href": "/api/resourcelink"
         }
        } ,
        "name": "bd1",
        "uuid": "1cd8a442-86d1-11e0-ae1c-123478563412"
      },
      "home node": {
        " links": {
         "self": {
           "href": "/api/resourcelink"
        },
```

```
"name": "node1",
        "uuid": "1cd8a442-86d1-11e0-ae1c-123478563412"
     }
    },
    "name": "lif1",
    "service policy": "string",
    "services": [
     "string"
    ],
    "subnet": {
     " links": {
       "self": {
         "href": "/api/resourcelink"
       }
     },
     "name": "subnet1",
     "uuid": "1cd8a442-86d1-11e0-ae1c-123478563412"
    },
   "uuid": "1cd8a442-86d1-11e0-ae1c-123478563412"
 }
],
"ipspace": {
 " links": {
   "self": {
    "href": "/api/resourcelink"
   }
 },
  "name": "exchange",
 "uuid": "1cd8a442-86d1-11e0-ae1c-123478563412"
} ,
"iscsi": {
 " links": {
   "self": {
    "href": "/api/resourcelink"
   }
 }
"language": "c.utf_8",
"ldap": {
 "ad domain": "string",
 "base dn": "string",
 "bind dn": "string",
 "servers": [
  "string"
 ]
},
```

```
"max volumes": "string",
"name": "svm1",
"nfs": {
 " links": {
   "self": {
    "href": "/api/resourcelink"
   }
 }
},
"nis": {
 " links": {
   "self": {
    "href": "/api/resourcelink"
  }
 },
 "domain": "string",
 "servers": [
  "string"
 ]
},
"nsswitch": {
 "group": [
  "string"
 ],
  "hosts": [
  "string"
 ],
  "namemap": [
  "string"
 ],
 "netgroup": [
 "string"
 ],
 "passwd": [
 "string"
 ]
"number of volumes in recovery queue": 0,
"nvme": {
 " links": {
   "self": {
    "href": "/api/resourcelink"
 }
"qos adaptive policy group_template": {
```

```
" links": {
    "self": {
     "href": "/api/resourcelink"
   }
  },
  "max throughput iops": 10000,
 "max throughput mbps": 500,
 "min throughput iops": 2000,
  "min throughput mbps": 500,
 "name": "performance",
 "uuid": "1cd8a442-86d1-11e0-ae1c-123478563412"
} ,
"qos policy": {
  " links": {
   "self": {
     "href": "/api/resourcelink"
  },
  "max throughput iops": 10000,
  "max throughput mbps": 500,
 "min throughput iops": 2000,
 "min throughput mbps": 500,
 "name": "performance",
 "uuid": "1cd8a442-86d1-11e0-ae1c-123478563412"
},
"routes": [
 {
   "destination": {
     "address": "10.10.10.7",
     "family": "string",
     "netmask": "24"
   },
   "gateway": "10.1.1.1"
  }
],
"s3": {
 " links": {
   "self": {
     "href": "/api/resourcelink"
   }
  "certificate": {
   " links": {
     "self": {
       "href": "/api/resourcelink"
```

```
},
        "name": "string",
        "uuid": "1cd8a442-86d1-11e0-ae1c-123478563412"
      },
      "default unix user": "string",
      "default win user": "string",
      "name": "s3-server-1"
    },
    "snapmirror": {
      "protected consistency group count": 0,
      "protected volumes count": 0
    } ,
    "snapshot policy": {
      " links": {
        "self": {
         "href": "/api/resourcelink"
      },
      "name": "default",
      "uuid": "1cd8a442-86d1-11e0-ae1c-123478563412"
    },
    "state": "running",
    "storage": {
     "allocated": 0,
     "available": 0,
     "used percentage": 0
    "subtype": "string",
    "total volume size in recovery queue": 0,
    "uuid": "02c9e252-41be-11e9-81d5-00a0986138f7"
1
```

Error

```
Status: Default, Error
```

Name	Туре	Description
error	returned_error	

Example error

Definitions

See Definitions

href

Name	Туре	Description
href	string	

_links

Name	Туре	Description
next	href	
self	href	

_links

Name	Туре	Description
self	href	

aggregates

Name	Туре	Description
_links	_links	
available_size	integer	Space available, in bytes.
name	string	
snaplock_type	string	SnapLock type.
state	string	Aggregate state.
type	string	Type of aggregate.
uuid	string	

event_log

Name	Туре	Description
is_enabled_on_new_file_extensio n_seen	boolean	Specifies whether to send an EMS when a new file extension is discovered.
is_enabled_on_snapshot_copy_c reation	boolean	Specifies whether to send an EMS when a Snapshot copy is created.

arw_vserver

Anti-ransomware related information for the SVM.

Name	Туре	Description
event_log	event_log	

certificate

Support for this field will be removed in a future release. Please use /svm/svms/{svm.uuid}/web for this field. Certificate for incoming TLS connection requests.

Name	Туре	Description
_links	_links	
name	string	Certificate name
uuid	string	Certificate UUID

ad_domain

Name	Туре	Description
default_site	string	The default site used by LIFs that do not have a site membership.
fqdn	string	The fully qualified domain name of the Windows Active Directory to which this CIFS server belongs. A CIFS server appears as a member of Windows server object in the Active Directory store.
organizational_unit	string	Specifies the organizational unit within the Active Directory domain to associate with the CIFS server.
password	string	The account password used to add this CIFS server to the Active Directory. This is not audited. Valid in POST only.
user	string	The user account used to add this CIFS server to the Active Directory. Valid in POST only.

cifs

Name	Туре	Description
_links	_links	
ad_domain	ad_domain	
allowed	boolean	If this is set to true, an SVM administrator can manage the CIFS service. If it is false, only the cluster administrator can manage the service.
domain_workgroup	string	The NetBIOS name of the domain or workgroup associated with the CIFS server.
enabled	boolean	If allowed, setting to true enables the CIFS service.
name	string	The NetBIOS name of the CIFS server.

dns

Name	Туре	Description
_links	_links	

Name	Туре	Description
domains	array[string]	A list of DNS domains. Domain names have the following requirements:
		 The name must contain only the following characters: A through Z, a through z, 0 through 9, ".", "-" or "_".
		The first character of each label, delimited by ".", must be one of the following characters: A through Z or a through z or 0 through 9.
		The last character of each label, delimited by ".", must be one of the following characters: A through Z, a through z, or 0 through 9.
		 The top level domain must contain only the following characters: A through Z, a through z.
		The system reserves the following names:"all", "local", and "localhost".
servers	array[string]	The list of IP addresses of the DNS servers. Addresses can be either IPv4 or IPv6 addresses.

node

The node on which the FC port is located.

Name	Туре	Description
name	string	The name of the node on which the FC port is located.

fc_port_reference

An FC port is the physical port of an FC adapter on a cluster node that can be connected to an FC network.

Name	Туре	Description
_links	_links	

Name	Туре	Description
name	string	The name of the FC port.
node	node	The node on which the FC port is located.
uuid	string	The unique identifier of the FC port.

location

The location of the Fibre Channel interface is defined by the location of its port.

Name	Туре	Description
port	fc_port_reference	An FC port is the physical port of an FC adapter on a cluster node that can be connected to an FC network.

fc_interface_svm

Name	Туре	Description
_links	_links	
data_protocol	string	The data protocol for which the Fibre Channel interface is configured.
location	location	The location of the Fibre Channel interface is defined by the location of its port.
name	string	The name of the Fibre Channel interface.
uuid	string	The unique identifier of the Fibre Channel interface.

fcp

Name	Туре	Description
_links	_links	

Name	Туре	Description
allowed	boolean	If this is set to true, an SVM administrator can manage the FCP service. If it is false, only the cluster administrator can manage the service.
enabled	boolean	If allowed, setting to true enables the FCP service.

iр

IP information

Name	Туре	Description
address	string	IPv4 or IPv6 address
netmask	string	Input as netmask length (16) or IPv4 mask (255.255.0.0).

broadcast_domain

Broadcast domain UUID along with a readable name.

Name	Туре	Description
_links	_links	
name	string	Name of the broadcast domain, scoped to its IPspace
uuid	string	Broadcast domain UUID

home_node

Name	Туре	Description
_links	_links	
name	string	
uuid	string	

location

Home_node is optional.

Name	Туре	Description
broadcast_domain	broadcast_domain	Broadcast domain UUID along with a readable name.
home_node	home_node	

ip_subnet_reference

A named subnet. Either UUID or name can be supplied on input.

Name	Туре	Description
_links	_links	
name	string	The name of the subnet. If only the name is provided, the IPspace scope must be provided by the object this object is embedded in.
uuid	string	The UUID that uniquely identifies the subnet.

ip_interface_svm

Interface parameters. Name and home_node are optional.

Name	Туре	Description
_links	_links	
ip	ip	IP information
location	location	Home_node is optional.
name	string	The name of the interface (optional).
service_policy	string	Built-in service policies for SVMs.
services	array[string]	The services associated with the interface.
subnet	ip_subnet_reference	A named subnet. Either UUID or name can be supplied on input.
uuid	string	The UUID that uniquely identifies the interface.

ipspace

Either the UUID or name may be supplied on input.

Name	Туре	Description
_links	_links	
name	string	IPspace name
uuid	string	IPspace UUID

iscsi

Name	Туре	Description
_links	_links	
allowed	boolean	If this is set to true, an SVM administrator can manage the iSCSI service. If it is false, only the cluster administrator can manage the service.
enabled	boolean	If allowed, setting to true enables the ISCSI service.

ldap

Name	Туре	Description
ad_domain	string	This parameter specifies the name of the Active Directory domain used to discover LDAP servers for use by this client. This is mutually exclusive with servers during POST.
base_dn	string	Specifies the default base DN for all searches.
bind_dn	string	Specifies the user that binds to the LDAP servers. SVM API supports anonymous binding. For Simple and SASL LDAP binding, use the LDAP API endpoint.
enabled	boolean	Enable LDAP? Setting to true creates a configuration if not already created.

Name	Туре	Description
restrict_discovery_to_site	boolean	Specifies whether or not LDAP server discovery is restricted to site-scope.
servers	array[string]	

ndmp

Name	Туре	Description
allowed	boolean	If this is set to true, an SVM administrator can manage the NDMP service. If it is false, only the cluster administrator can manage the service.

nfs

Name	Туре	Description
_links	_links	
allowed	boolean	If this is set to true, an SVM administrator can manage the NFS service. If it is false, only the cluster administrator can manage the service.
enabled	boolean	If allowed, setting to true enables the NFS service.

nis

Name	Туре	Description
_links	_links	
domain	string	The NIS domain to which this configuration belongs.
enabled	boolean	Enable NIS? Setting to true creates a configuration if not already created.
servers	array[string]	A list of hostnames or IP addresses of NIS servers used by the NIS domain configuration.

nsswitch

Name service switch configuration

Name	Туре	Description
group	array[string]	Group sources
hosts	array[string]	Host sources
namemap	array[string]	NameMap sources
netgroup	array[string]	NetGroup sources
passwd	array[string]	Password sources

nvme

Name	Туре	Description
_links	_links	
allowed	boolean	If this is set to true, an SVM administrator can manage the NVMe service. If it is false, only the cluster administrator can manage the service.
enabled	boolean	If allowed, setting to true enables the NVMe service.

qos_adaptive_policy_group_template

This optionally specifies which QoS adaptive policy group to apply to the SVM as a template. This policy group will then be assigned to volumes created or rehosted into this SVM. This policy group defines measurable service level objectives (SLOs) and Service Level Agreements (SLAs) that adjust based on the volume allocated space or used space.

Name	Туре	Description
_links	_links	
max_throughput_iops	integer	Specifies the maximum throughput in IOPS, 0 means none. This is mutually exclusive with name and UUID during POST and PATCH.

Name	Туре	Description
max_throughput_mbps	integer	Specifies the maximum throughput in Megabytes per sec, 0 means none. This is mutually exclusive with name and UUID during POST and PATCH.
min_throughput_iops	integer	Specifies the minimum throughput in IOPS, 0 means none. Setting "min_throughput" is supported on AFF platforms only, unless FabricPool tiering policies are set. This is mutually exclusive with name and UUID during POST and PATCH.
min_throughput_mbps	integer	Specifies the minimum throughput in Megabytes per sec, 0 means none. This is mutually exclusive with name and UUID during POST and PATCH.
name	string	The QoS policy group name. This is mutually exclusive with UUID and other QoS attributes during POST and PATCH.
uuid	string	The QoS policy group UUID. This is mutually exclusive with name and other QoS attributes during POST and PATCH.

qos_policy

This optionally specifies which QoS policy group to apply to the Vserver. This policy group defines measurable service level objectives (SLOs) that apply to the storage objects with which the policy group is associated.

Name	Туре	Description
_links	_links	
max_throughput_iops	integer	Specifies the maximum throughput in IOPS, 0 means none. This is mutually exclusive with name and UUID during POST and PATCH.

Name	Туре	Description
max_throughput_mbps	integer	Specifies the maximum throughput in Megabytes per sec, 0 means none. This is mutually exclusive with name and UUID during POST and PATCH.
min_throughput_iops	integer	Specifies the minimum throughput in IOPS, 0 means none. Setting "min_throughput" is supported on AFF platforms only, unless FabricPool tiering policies are set. This is mutually exclusive with name and UUID during POST and PATCH.
min_throughput_mbps	integer	Specifies the minimum throughput in Megabytes per sec, 0 means none. This is mutually exclusive with name and UUID during POST and PATCH.
name	string	The QoS policy group name. This is mutually exclusive with UUID and other QoS attributes during POST and PATCH.
uuid	string	The QoS policy group UUID. This is mutually exclusive with name and other QoS attributes during POST and PATCH.

ip_info

IP information

Name	Туре	Description
address	string	IPv4 or IPv6 address
family	string	IPv4 or IPv6
netmask	string	Input as netmask length (16) or IPv4 mask (255.255.0.0). For IPv6, the default value is 64 with a valid range of 1 to 127. Output is always netmask length.

network_route_for_svm

Name	Туре	Description
destination	ip_info	IP information
gateway	string	The IP address of the gateway router leading to the destination.

certificate

Specifies the certificate that will be used for creating HTTPS connections to the S3 server.

Name	Туре	Description
_links	_links	
name	string	Certificate name
uuid	string	Certificate UUID

s3

Name	Туре	Description
_links	_links	
certificate	certificate	Specifies the certificate that will be used for creating HTTPS connections to the S3 server.
default_unix_user	string	Specifies the default UNIX user for NAS Access.
default_win_user	string	Specifies the default Windows user for NAS Access.
enabled	boolean	Specifies whether or not to enable S3. Setting this value to true creates a service if one is not yet created.
is_http_enabled	boolean	Specifies whether HTTP is enabled on the S3 server. By default, HTTP is disabled on the S3 server.
is_https_enabled	boolean	Specifies whether HTTPS is enabled on the S3 server. By default, HTTPS is enabled on the S3 server.

Name	Туре	Description
name	string	Specifies the name of the S3 server. A server name length can range from 1 to 253 characters and can only contain the following combination of characters 0-9, A-Z, a-z, ".", and "-".
port	integer	Specifies the HTTP listener port for the S3 server. By default, HTTP is enabled on port 80.
secure_port	integer	Specifies the HTTPS listener port for the S3 server. By default, HTTPS is enabled on port 443.

snapmirror

Specifies attributes for SVM DR protection.

Name	Туре	Description
is_protected	boolean	Specifies whether the SVM is a SnapMirror source SVM, using SnapMirror to protect its data.
protected_consistency_group_co unt	integer	Specifies the number of SVM DR protected consistency groups in the SVM.
protected_volumes_count	integer	Specifies the number of SVM DR protected volumes in the SVM.

snapshot_policy

This is a reference to the Snapshot copy policy.

Name	Туре	Description
_links	_links	
name	string	
uuid	string	

storage

Name	Туре	Description
allocated	integer	Total size of the volumes in SVM, in bytes.
available	integer	Currently available storage capacity in SVM, in bytes.
limit	integer	Maximum storage permitted on a single SVM, in bytes.
limit_threshold_alert	integer	Indicates at what percentage of storage capacity an alert message is sent. The default value is 90.
limit_threshold_exceeded	boolean	Indicates whether the total storage capacity exceeds the alert percentage.
used_percentage	integer	The percentage of storage capacity used.

svm

Name	Туре	Description
_links	_links	
aggregates	array[aggregates]	List of allowed aggregates for SVM volumes. An administrator is allowed to create volumes on these aggregates.
aggregates_delegated	boolean	This property is true when the administrator has delegated the aggregates for the SVM volumes.
anti_ransomware	arw_vserver	Anti-ransomware related information for the SVM.

Name	Туре	Description
anti_ransomware_auto_switch_d uration_without_new_file_extensi on	integer	One of the many conditions to be satisfied to automatically switch the anti-ransomware state of the volumes in this SVM from "learning" (dry-run) to "enabled" is that no new file-extensions are observed in the volume in recent time. This parameter optionally specifies the recent time duration (in days) to be considered during which no new file-extension should be observed in a given volume to automatically switch the anti-ransomware state from "learning" to "enabled".
anti_ransomware_auto_switch_fr om_learning_to_enabled	boolean	This property specifies whether anti-ransomware state of the volumes in this SVM are automatically switched by the system from "learning" (dry-run) to "enabled" (active) state after sufficient learning.
anti_ransomware_auto_switch_mi nimum_file_count	integer	One of the many conditions to be satisfied to automatically switch the anti-ransomware state of the volumes in this SVM from "learning" (dry-run) to "enabled" is that the volume should have a minimum file count in "learning" state. This parameter optionally specifies the minimum number of newly created files in "learning" state in a given volume to automatically switch the anti-ransomware state from "learning" to "enabled".

Name	Туре	Description
anti_ransomware_auto_switch_mi nimum_file_extension	integer	One of the many conditions to be satisfied to automatically switch the anti-ransomware state of the volumes in this SVM from "learning" (dry-run) to "enabled" is that the volume should have minimum number of file extensions in "learning" state. This parameter optionally specifies the minimum number of new file extensions in "learning" state in a given volume to automatically switch the anti-ransomware state from "learning" to "enabled".
anti_ransomware_auto_switch_mi nimum_learning_period	integer	One of the many conditions to be satisfied to automatically switch the anti-ransomware state of the volumes in this SVM from "learning" (dry-run) to "enabled" is that the volume should be in "learning" state for sufficient time period. This parameter optionally specifies the minimum number of days a given volume should be in "learning" state to automatically switch the anti-ransomware state from "learning" to "enabled".
anti_ransomware_default_volume _state	string	Specifies the default Antiransomware state of the volumes in the SVM. Default "anti_ransomware_default_volum e_state" property is disabled for POST operation. If this value is "disabled", Anti-ransomware protection is disabled by default on the new volumes that are created in the SVM. If this value is "dry_run", Anti-ransomware protection is in learning mode by default on the new volumes that are created in the SVM. When the Anti-ransomware license is not present, this property is ignored and volumes will be created with the "disabled" state.

Name	Туре	Description
anti_ransomware_incoming_write _threshold	string	One of the many conditions to be satisfied to automatically switch the anti-ransomware state of the volumes in this SVM from "learning" (dry-run) to "enabled" is that the volume should have sufficient data ingested to do the learning. This parameter optionally specifies the minimum amount of data (in GB) to be written to a given volume during the learning period to automatically switch the anti-ransomware state from "learning" to "enabled". The amount of data considered as ingested also includes the data that is deleted or overwritten after ingestion.
anti_ransomware_incoming_write _threshold_percent	string	One of the many conditions to be satisfied to automatically switch the anti-ransomware state of the volumes in this SVM from "learning" (dry-run) to "enabled" is that the volume should have sufficient data ingested to do the learning. This parameter optionally specifies the minimum amount of data (in percentage) to be written to a given volume during the learning period to automatically switch the anti-ransomware state from "learning" to "enabled". The amount of data considered as ingested also includes the data that is deleted or overwritten after ingestion.
auto_enable_activity_tracking	boolean	Specifies whether volume activity tracking is automatically enabled on volumes that are created in the SVM.
auto_enable_analytics	boolean	Specifies whether file system analytics is automatically enabled on volumes that are created in the SVM.

Name	Туре	Description
certificate	certificate	Support for this field will be removed in a future release. Please use /svm/svms/{svm.uuid}/web for this field. Certificate for incoming TLS connection requests.
cifs	cifs	
comment	string	Comment
dns	dns	
fc_interfaces	array[fc_interface_svm]	FC Interface for the SVM
fcp	fcp	
ip_interfaces	array[ip_interface_svm]	IP interfaces for the SVM
ipspace	ipspace	Either the UUID or name may be supplied on input.
is_space_enforcement_logical	boolean	Indicates whether logical space enforcement for the SVM is enabled.
is_space_reporting_logical	boolean	Indicates whether logical space reporting for the SVM is enabled.
iscsi	iscsi	
language	string	Default volume language code. UTF-8 encoded languages are valid in POST or PATCH. Non UTF-8 language encodings are for backward compatibility and are not valid input for POST and PATCH requests.
ldap	Idap	
max_volumes	string	This property is used by cluster administrator to specify the limit on maximum number of volumes allowed in the SVM. The value can be either the string "unlimited" or a number.
name	string	The name of the SVM.

Name	Туре	Description
ndmp	ndmp	
nfs	nfs	
nis	nis	
nsswitch	nsswitch	Name service switch configuration
number_of_volumes_in_recovery _queue	integer	Number of volumes in the recovery queue.
nvme	nvme	
qos_adaptive_policy_group_temp late	qos_adaptive_policy_group_temp late	This optionally specifies which QoS adaptive policy group to apply to the SVM as a template. This policy group will then be assigned to volumes created or rehosted into this SVM. This policy group defines measurable service level objectives (SLOs) and Service Level Agreements (SLAs) that adjust based on the volume allocated space or used space.
qos_policy	qos_policy	This optionally specifies which QoS policy group to apply to the Vserver. This policy group defines measurable service level objectives (SLOs) that apply to the storage objects with which the policy group is associated.
routes	array[network_route_for_svm]	Optional array of routes for the SVM
s3	s3	
snapmirror	snapmirror	Specifies attributes for SVM DR protection.
snapshot_policy	snapshot_policy	This is a reference to the Snapshot copy policy.
state	string	SVM State
storage	storage	

Name	Туре	Description
subtype	string	SVM subtype. The SVM subtype sync_destination is created automatically when an SVM of subtype sync_source is created on the source MetroCluster cluster. A POST request with sync_destination as SVM subtype is invalid.
total_volume_size_in_recovery_q ueue	integer	Sum of the sizes of the volumes in the recovery queue.
uuid	string	The unique identifier of the SVM.

error_arguments

Name	Туре	Description
code	string	Argument code
message	string	Message argument

returned_error

Name	Туре	Description
arguments	array[error_arguments]	Message arguments
code	string	Error code
message	string	Error message
target	string	The target parameter that caused the error.

Create and provision an SVM

POST /svm/svms

Introduced In: 9.6

Creates and provisions an SVM. If no IPspace is provided, then the SVM is created on the Default IPspace.

- The number of parallel SVMs that can be created must not be greater than five.
- If a sixth SVM POST request is issued, the following error message is generated: "Maximum allowed SVM

jobs exceeded. Wait for the existing SVM jobs to complete and try again."

Required properties

• name - Name of the SVM to be created.

Recommended optional properties

- ipspace.name or ipspace.uuid IPspace of the SVM
- is space reporting logical Logical Space Reporting parameter of the SVM
- is space enforcement logical Logical Space Enforcement parameter of the SVM
- ip interfaces If provided, the following fields are required:
- ip interfaces.name Name of the interface
- ip interfaces.ip.address IP address
- ip interfaces.ip.netmask Netmask length or IP address
- ip_interfaces.location.broadcast_domain.uuid or ip_interfaces.location.broadcast_domain.name Broadcast domain name or UUID belonging to the same IPspace of the SVM.
- subnet.uuid or subnet.name Either name or UUID of the subnet to create.
- routes If provided, the following field is required:
 - routes.gateway Gateway IP address
- cifs If provided, interfaces, routes and DNS must be provided. The following fields are also required:
 - ° cifs.name Name of the CIFS server to be created for the SVM.
 - ° cifs.ad domain.fqdn Fully qualified domain name
 - ° cifs.ad domain.user Administrator username
 - ° cifs.ad domain.password User password
- ldap If provided, the following fields are required:
 - ° ldap.servers or ldap.ad domain LDAP server list or Active Directory domain
 - ° ldap.bind dn Bind DN
 - ° ldap.base dn Base DN
- nis If provided, the following fields are required:
 - ° nis.servers NIS servers
 - ° nis.domain NIS domain
- dns If provided, the following fields are required:
 - ° dns.servers Name servers
 - ° dns.domains Domains
- fc interfaces If provided, the following fields are required:

- ° fc interfaces.name Fibre Channel interface name
- ° fc interfaces.data protocol Fibre Channel interface data protocol
- of fc_interfaces.location.port.uuid or fc_interfaces.location.port.name and fc_interfaces.location.port.node.name Either port UUID or port name and node name together must be provided.
- s3 If provided, the following field should also be specified:
 - <code>s3.name</code> Name of the S3 server. If <code>s3.name' is not specified while </code>s3.enabled` is set to 'true', the S3 server will be created with the default name '<svm.name>_S3Server'.</svm.name>
- auto enable analytics Auto-enable file system analytics on new volumes created in the SVM.
- auto_enable_activity_tracking Auto-enable volume activity-tracking on new volumes created in the SVM.
- storage.limit Maximum storage permitted on a single SVM.
- storage.limit_threshold_alert At what percentage of storage capacity, alert message needs to be sent.

Default property values

If not specified in POST, the following default property values are assigned:

- language C.UTF-8
- ipspace.name Default
- snapshot policy.name Default
- subtype Default (sync-source if MetroCluster configuration)
- anti ransomware default volume state disabled

Related ONTAP commands

- vserver create
- vserver add-aggregates
- network interface create
- network route create
- vserver services name-service dns create
- vserver nfs create
- vserver services name-service ldap client create
- vserver cifs create
- vserver services name-service nis-domain create
- vserver iscsi create
- vserver nvme create

```
• vserver fcp create
```

- vserver services name-service ns-switch create
- vserver object-store-server create
- vserver add-protocols
- vserver remove-protocols

Examples

1. Creates an SVM with default "snapshot policy"

```
POST "/api/svm/svms" '{"name":"testVs",
"snapshot_policy":{"name":"default"}}'
```

1. Creates an SVM and configures NFS, ISCSI and FCP

```
POST "/api/svm/svms" '{"name":"testVs", "nfs":{"enabled":"true"},
"fcp":{"enabled":"true"}, "iscsi":{"enabled":"true"}}'
```

1. Creates an SVM and configures NVMe

```
POST "/api/svm/svms" '{"name":"testVs", "nvme":{"enabled":"true"}}'
```

1. Creates an SVM and configures LDAP

```
POST "/api/svm/svms" '{"name":"testVs",

"snapshot_policy":{"name":"default"},

"ldap":{"servers":["10.140.101.1","10.140.101.2"], "ad_domain":"abc.com",

"base_dn":"dc=netapp,dc=com", "bind_dn":"dc=netapp,dc=com"}}'
```

1. Creates an SVM and configures NIS

```
POST "/api/svm/svms" '{"name":"testVs",
"snapshot_policy":{"name":"default"}, "nis":{"enabled":"true",
"domain":"def.com","servers":["10.224.223.130", "10.224.223.131"]}}'
```

1. Creates an SVM and configures DNS

```
POST "/api/svm/svms" '{"name":"testVs",

"snapshot_policy":{"name":"default"},

"dns":{"domains":["abc.com","def.com"], "servers":["10.224.223.130",

"10.224.223.131"]}}'
```

1. Creates an SVM and configures a LIF

```
POST "/api/svm/svms" '{"name":"testVs", "ip_interfaces":
[{"name":"lif1", "ip":{"address":"10.10.10.7", "netmask":
"255.255.255.0"}, "location":{"broadcast_domain":{"name":"bd1"},
"home_node":{"name":"node1"}}, "service_policy": "default-management"}]}'
```

1. Creates an SVM and configures a LIF with IPV6 address

```
POST "/api/svm/svms" '{"name":"testVs", "ip_interfaces":
[{"name":"lif2", "ip":{"address":"fd22:8b1e:b255:202:2a0:98ff:fe01:7d5b",
"netmask":"24"}, "location":{"broadcast_domain":{"name":"bd1"},
"home_node":{"name":"node1"}}, "service_policy": "default-management"}]}'
```

1. Creates an SVM and configures CIFS

```
POST "/api/svm/svms" '{"name":"testVs", "cifs":{"name":"CIFDOC",

"ad_domain":{"fqdn":"abc.def.com", "organizational_unit":"CN=Computers",

"user":"cif_admin", "password":"abc123"}},

"ip_interfaces":[{"name":"lif1", "ip":{"address":"10.10.10.7", "netmask":

"255.255.255.0"}, "location":{"broadcast_domain":{"name":"bd1"},

"home_node":{"name":"node1"}}, "service_policy": "default-

management"}], "routes": [{"destination": {"address": "0.0.0.0", "netmask":

"0"}, "gateway": "10.10.10.7"}], "dns":{"domains":["abc.def.com",

"def.com"], "servers":["10.224.223.130", "10.224.223.131"]}}'
```

1. Creates an SVM and configures an S3 server

```
POST "/api/svm/svms" '{"name":"svm5", "s3":{"name":"s3-server-1",
"enabled":true}}'
```

1. Creates an SVM and disallows NVMe service for the SVM

```
POST "/api/svm/svms" '{"name":"testVs", "nvme":{"allowed":"false"}}'
```

1. Creates an SVM, allows and configures the NFS service for the SVM

```
POST "/api/svm/svms" '{"name":"testVs", "nfs":{"allowed":"true",
"enabled":true}}'
```

1. Create an SVM and set the max volume limit for the SVM

```
POST "/api/svm/svms/" '{"name":"testVs", "max_volumes":"200"}'
```

1. Creates an SVM and disallows the NDMP service for the SVM.

```
POST "/api/svm/svms" '{"name":"testVs", "ndmp":{"allowed":"false"}}'
```

 Creates an SVM and specifies whether file system analytics is enabled on all newly created volumes in the SVM.

```
POST "/api/svm/svms" '{"name":"testVs", "auto_enable_analytics":true}}'
```

 Creates an SVM and specifies whether volume_activity_tracking is enabled on all newly created volumes in the SVM.

```
POST "/api/svm/svms" '{"name":"testVs",
"auto_enable_activity_tracking":true}}'
```

1. Creates an SVM and specifies whether file system analytics is enabled on all newly created volumes in the SVM.

```
POST "/api/svm/svms" '{"name":"testVs", "auto_enable_analytics":true}}'
```

1. Creates an SVM and specifies the maximum storage limit for a single SVM.

```
POST "/api/svm/svms" '{"name":"testVs", "storage": {"limit":"4GB"}}'
```

1. Creates an SVM and specifies at what percentage of storage capacity an alert message is sent. Default value is 90.

```
POST "/api/svm/svms" '{"name":"testVs", "storage": {"limit":"20GB",
"limit_threshold_alert":"95"}}'
```

Learn more

• DOC /svm/svms

Parameters

Name	Туре	In	Required	Description
return_records	boolean	query	False	The default is false. If set to true, the records are returned. • Default value:
return_timeout	integer	query	False	The number of seconds to allow the call to execute before returning. When doing a POST, PATCH, or DELETE operation on a single record, the default is 0 seconds. This means that if an asynchronous operation is started, the server immediately returns HTTP code 202 (Accepted) along with a link to the job. If a non-zero value is specified for POST, PATCH, or DELETE operations, ONTAP waits that length of time to see if the job completes so it can return something other than 202. • Default value: 1 • Max value: 120 • Min value: 0

Request Body

Name	Туре	Description
_links	_links	
aggregates	array[aggregates]	List of allowed aggregates for SVM volumes. An administrator is allowed to create volumes on these aggregates.
aggregates_delegated	boolean	This property is true when the administrator has delegated the aggregates for the SVM volumes.
anti_ransomware	arw_vserver	Anti-ransomware related information for the SVM.
anti_ransomware_auto_switch_dur ation_without_new_file_extension	integer	One of the many conditions to be satisfied to automatically switch the anti-ransomware state of the volumes in this SVM from "learning" (dry-run) to "enabled" is that no new file-extensions are observed in the volume in recent time. This parameter optionally specifies the recent time duration (in days) to be considered during which no new file-extension should be observed in a given volume to automatically switch the anti-ransomware state from 'learning'" to "enabled".
anti_ransomware_auto_switch_fro m_learning_to_enabled	boolean	This property specifies whether anti-ransomware state of the volumes in this SVM are automatically switched by the system from "learning" (dry-run) to "enabled" (active) state after sufficient learning.

Name	Туре	Description
anti_ransomware_auto_switch_min imum_file_count	integer	One of the many conditions to be satisfied to automatically switch the anti-ransomware state of the volumes in this SVM from "learning" (dry-run) to "enabled" is that the volume should have a minimum file count in "learning" state. This parameter optionally specifies the minimum number of newly created files in "learning" state in a given volume to automatically switch the anti-ransomware state from "learning" to "enabled".
anti_ransomware_auto_switch_min imum_file_extension	integer	One of the many conditions to be satisfied to automatically switch the anti-ransomware state of the volumes in this SVM from "learning" (dry-run) to "enabled" is that the volume should have minimum number of file extensions in "learning" state. This parameter optionally specifies the minimum number of new file extensions in "learning" state in a given volume to automatically switch the anti-ransomware state from "learning" to "enabled".
anti_ransomware_auto_switch_min imum_learning_period	integer	One of the many conditions to be satisfied to automatically switch the anti-ransomware state of the volumes in this SVM from "learning" (dry-run) to "enabled" is that the volume should be in "learning" state for sufficient time period. This parameter optionally specifies the minimum number of days a given volume should be in "learning" state to automatically switch the anti-ransomware state from "learning" to "enabled".

Name	Туре	Description
anti_ransomware_default_volume_ state	string	Specifies the default Antiransomware state of the volumes in the SVM. Default "anti_ransomware_default_volume _state" property is disabled for POST operation. If this value is "disabled", Anti-ransomware protection is disabled by default on the new volumes that are created in the SVM. If this value is "dry_run", Anti-ransomware protection is in learning mode by default on the new volumes that are created in the SVM. When the Anti-ransomware license is not present, this property is ignored and volumes will be created with the "disabled" state.
anti_ransomware_incoming_write_t hreshold	string	One of the many conditions to be satisfied to automatically switch the anti-ransomware state of the volumes in this SVM from "learning" (dry-run) to "enabled" is that the volume should have sufficient data ingested to do the learning. This parameter optionally specifies the minimum amount of data (in GB) to be written to a given volume during the learning period to automatically switch the anti-ransomware state from "learning" to "enabled". The amount of data considered as ingested also includes the data that is deleted or overwritten after ingestion.

Name	Туре	Description
anti_ransomware_incoming_write_t hreshold_percent	string	One of the many conditions to be satisfied to automatically switch the anti-ransomware state of the volumes in this SVM from "learning" (dry-run) to "enabled" is that the volume should have sufficient data ingested to do the learning. This parameter optionally specifies the minimum amount of data (in percentage) to be written to a given volume during the learning period to automatically switch the anti-ransomware state from "learning" to "enabled". The amount of data considered as ingested also includes the data that is deleted or overwritten after ingestion.
auto_enable_activity_tracking	boolean	Specifies whether volume activity tracking is automatically enabled on volumes that are created in the SVM.
auto_enable_analytics	boolean	Specifies whether file system analytics is automatically enabled on volumes that are created in the SVM.
certificate	certificate	Support for this field will be removed in a future release. Please use /svm/svms/{svm.uuid}/web for this field. Certificate for incoming TLS connection requests.
cifs	cifs	
comment	string	Comment
dns	dns	
fc_interfaces	array[fc_interface_svm]	FC Interface for the SVM
fcp	fcp	
ip_interfaces	array[ip_interface_svm]	IP interfaces for the SVM
ipspace	ipspace	Either the UUID or name may be supplied on input.

Name	Туре	Description
is_space_enforcement_logical	boolean	Indicates whether logical space enforcement for the SVM is enabled.
is_space_reporting_logical	boolean	Indicates whether logical space reporting for the SVM is enabled.
iscsi	iscsi	
language	string	Default volume language code. UTF-8 encoded languages are valid in POST or PATCH. Non UTF- 8 language encodings are for backward compatibility and are not valid input for POST and PATCH requests.
Idap	ldap	
max_volumes	string	This property is used by cluster administrator to specify the limit on maximum number of volumes allowed in the SVM. The value can be either the string "unlimited" or a number.
name	string	The name of the SVM.
ndmp	ndmp	
nfs	nfs	
nis	nis	
nsswitch	nsswitch	Name service switch configuration
number_of_volumes_in_recovery_ queue	integer	Number of volumes in the recovery queue.
nvme	nvme	

Name	Туре	Description
qos_adaptive_policy_group_templa te	qos_adaptive_policy_group_templa te	This optionally specifies which QoS adaptive policy group to apply to the SVM as a template. This policy group will then be assigned to volumes created or rehosted into this SVM. This policy group defines measurable service level objectives (SLOs) and Service Level Agreements (SLAs) that adjust based on the volume allocated space or used space.
qos_policy	qos_policy	This optionally specifies which QoS policy group to apply to the Vserver. This policy group defines measurable service level objectives (SLOs) that apply to the storage objects with which the policy group is associated.
routes	array[network_route_for_svm]	Optional array of routes for the SVM
s3	s3	
snapmirror	snapmirror	Specifies attributes for SVM DR protection.
snapshot_policy	snapshot_policy	This is a reference to the Snapshot copy policy.
state	string	SVM State
storage	storage	
subtype	string	SVM subtype. The SVM subtype sync_destination is created automatically when an SVM of subtype sync_source is created on the source MetroCluster cluster. A POST request with sync_destination as SVM subtype is invalid.
total_volume_size_in_recovery_qu eue	integer	Sum of the sizes of the volumes in the recovery queue.
uuid	string	The unique identifier of the SVM.

```
" links": {
 "self": {
   "href": "/api/resourcelink"
 }
},
"aggregates": [
    " links": {
     "self": {
        "href": "/api/resourcelink"
     }
    },
    "available size": 10156560384,
    "name": "aggr1",
    "snaplock type": "string",
    "state": "string",
    "type": "string",
    "uuid": "1cd8a442-86d1-11e0-ae1c-123478563412"
 }
1,
"anti ransomware default volume state": "string",
"anti ransomware incoming write threshold": "string",
"anti ransomware incoming write threshold percent": "string",
"certificate": {
  " links": {
   "self": {
     "href": "/api/resourcelink"
   }
  },
  "name": "string",
  "uuid": "1cd8a442-86d1-11e0-ae1c-123478563412"
},
"cifs": {
  " links": {
   "self": {
     "href": "/api/resourcelink"
   }
  },
  "ad domain": {
   "default site": "string",
    "fqdn": "example.com",
    "organizational unit": "string",
    "password": "string",
```

```
"user": "string"
  "domain workgroup": "string",
 "name": "CIFS1"
"comment": "string",
"dns": {
 " links": {
   "self": {
    "href": "/api/resourcelink"
   }
  },
  "domains": [
   "example.com",
   "example2.example3.com"
 ],
 "servers": [
  "10.224.65.20",
  "2001:db08:a0b:12f0::1"
 ]
} ,
"fc interfaces": [
    " links": {
     "self": {
       "href": "/api/resourcelink"
     }
    },
    "data protocol": "string",
    "location": {
      "port": {
        " links": {
         "self": {
           "href": "/api/resourcelink"
        },
        "name": "0a",
       "node": {
        "name": "node1"
       },
       "uuid": "1cd8a442-86d1-11e0-ae1c-123478563412"
   "name": "lif1",
    "uuid": "1cd8a442-86d1-11e0-ae1c-123478563412"
```

```
],
"fcp": {
 " links": {
   "self": {
     "href": "/api/resourcelink"
 }
} ,
"ip interfaces": [
   " links": {
     "self": {
       "href": "/api/resourcelink"
     }
    },
    "ip": {
     "address": "10.10.10.7",
     "netmask": "24"
   },
    "location": {
      "broadcast domain": {
       " links": {
          "self": {
           "href": "/api/resourcelink"
         }
        } ,
        "name": "bd1",
       "uuid": "1cd8a442-86d1-11e0-ae1c-123478563412"
      },
      "home node": {
        " links": {
          "self": {
           "href": "/api/resourcelink"
        },
        "name": "node1",
       "uuid": "1cd8a442-86d1-11e0-ae1c-123478563412"
     }
    },
    "name": "lif1",
    "service policy": "string",
    "services": [
    "string"
    ],
    "subnet": {
     " links": {
```

```
"self": {
         "href": "/api/resourcelink"
       }
      },
      "name": "subnet1",
     "uuid": "1cd8a442-86d1-11e0-ae1c-123478563412"
    },
    "uuid": "1cd8a442-86d1-11e0-ae1c-123478563412"
  }
],
"ipspace": {
 " links": {
   "self": {
     "href": "/api/resourcelink"
   }
  },
  "name": "exchange",
 "uuid": "1cd8a442-86d1-11e0-ae1c-123478563412"
},
"iscsi": {
 " links": {
   "self": {
     "href": "/api/resourcelink"
   }
  }
"language": "c.utf_8",
"ldap": {
 "ad domain": "string",
 "base dn": "string",
 "bind dn": "string",
 "servers": [
   "string"
 ]
},
"max volumes": "string",
"name": "svm1",
"nfs": {
 " links": {
   "self": {
     "href": "/api/resourcelink"
  }
},
"nis": {
 " links": {
```

```
"self": {
     "href": "/api/resourcelink"
   }
  },
  "domain": "string",
 "servers": [
  "string"
 ]
},
"nsswitch": {
  "group": [
  "string"
 ],
  "hosts": [
  "string"
 ],
  "namemap": [
  "string"
  "netgroup": [
  "string"
 ],
 "passwd": [
  "string"
 1
"number of volumes in recovery queue": 0,
"nvme": {
 " links": {
   "self": {
    "href": "/api/resourcelink"
   }
 }
"qos adaptive policy group template": {
 " links": {
   "self": {
    "href": "/api/resourcelink"
   }
  },
  "max throughput iops": 10000,
  "max throughput mbps": 500,
  "min throughput iops": 2000,
  "min throughput mbps": 500,
  "name": "performance",
  "uuid": "1cd8a442-86d1-11e0-ae1c-123478563412"
```

```
},
"qos policy": {
  " links": {
    "self": {
     "href": "/api/resourcelink"
  },
  "max throughput iops": 10000,
  "max throughput mbps": 500,
  "min throughput iops": 2000,
  "min throughput mbps": 500,
  "name": "performance",
 "uuid": "1cd8a442-86d1-11e0-ae1c-123478563412"
},
"routes": [
    "destination": {
     "address": "10.10.10.7",
     "family": "string",
     "netmask": "24"
   },
   "gateway": "10.1.1.1"
 }
],
"s3": {
 " links": {
   "self": {
     "href": "/api/resourcelink"
   }
  } ,
  "certificate": {
   " links": {
     "self": {
        "href": "/api/resourcelink"
     }
    },
   "name": "string",
   "uuid": "1cd8a442-86d1-11e0-ae1c-123478563412"
  "default unix user": "string",
  "default win user": "string",
 "name": "s3-server-1"
},
"snapmirror": {
  "protected consistency group count": 0,
  "protected volumes count": 0
```

```
"snapshot policy": {
    " links": {
     "self": {
       "href": "/api/resourcelink"
    },
    "name": "default",
    "uuid": "1cd8a442-86d1-11e0-ae1c-123478563412"
 },
 "state": "running",
 "storage": {
   "allocated": 0,
   "available": 0,
   "used percentage": 0
 },
 "subtype": "string",
 "total volume size in recovery queue": 0,
 "uuid": "02c9e252-41be-11e9-81d5-00a0986138f7"
}
```

Response

```
Status: 202, Accepted
```

Name	Туре	Description
job	job_link	

Example response

Headers

Name	Description	Туре
Location	Useful for tracking the resource location	string

Response

Status: 201, Created

Error

Status: Default

ONTAP Error Response Codes

Error codes	Description
2621580	Cannot specify options other than SVM name, comment and ipspace for a Vserver that is being configured as the destination for SVM DR.
2621634	"sync-source" SVM can only be created in a MetroCluster configuration.
2621657	"sync-destination" SVM can only be created by the system.
13434884	Cannot create an SVM because of incorrect fields.
13434885	Non-UTF8 language(s) not supported.
13434888	IPspace UUID and IPspace name mismatch.
13434889	Internal Error. Wait and retry.
13434894	Maximum allowed SVM jobs exceeded. Wait for the existing SVM jobs to complete and try again.
13434908	Invalid SVM name. The name is already in use by another SVM, IPSpace or cluster.
13434909	Internal Error. Failed to identify the aggregate to host SVM root volume.
13434910	Internal Error. Failed to allocate new SVM ID.
13434911	Invalid SVM name. Maximum supported length is 41 if SVM is of type \"sync-source\", otherwise 47.
13434912	Failed to find IPspace.
13434913	Internal error: Failed to check if an SVM create operation is in progress. Contact technical support for assistance.

Error codes	Description
13434914	Request to create the root volume of the SVM failed because there is not enough space in specified aggregate.
13434915	Failed to unlock the SVM because SVM create or delete job is in progress. Wait a few minutes, and then try the command again.
13434916	SVM is in the process of being created. Wait a few minutes, and then try the command again.
13434917	SVM creation successful.
13434918	IPspace name not provided for creating an SVM.
458753	Destination and gateway must belong to the same address family.

Name	Туре	Description
error	returned_error	

Example error

Definitions

See Definitions

href

Name	Туре	Description
href	string	

_links

Name	Туре	Description
self	href	

aggregates

Name	Туре	Description
_links	_links	
available_size	integer	Space available, in bytes.
name	string	
snaplock_type	string	SnapLock type.
state	string	Aggregate state.
type	string	Type of aggregate.
uuid	string	

event_log

Name	Туре	Description
is_enabled_on_new_file_extension_seen	boolean	Specifies whether to send an EMS when a new file extension is discovered.
is_enabled_on_snapshot_copy_c reation	boolean	Specifies whether to send an EMS when a Snapshot copy is created.

arw_vserver

Anti-ransomware related information for the SVM.

Name	Туре	Description
event_log	event_log	

certificate

Support for this field will be removed in a future release. Please use /svm/svms/{svm.uuid}/web for this field. Certificate for incoming TLS connection requests.

Name	Туре	Description
_links	_links	
name	string	Certificate name
uuid	string	Certificate UUID

ad_domain

Name	Туре	Description
default_site	string	The default site used by LIFs that do not have a site membership.
fqdn	string	The fully qualified domain name of the Windows Active Directory to which this CIFS server belongs. A CIFS server appears as a member of Windows server object in the Active Directory store.
organizational_unit	string	Specifies the organizational unit within the Active Directory domain to associate with the CIFS server.
password	string	The account password used to add this CIFS server to the Active Directory. This is not audited. Valid in POST only.
user	string	The user account used to add this CIFS server to the Active Directory. Valid in POST only.

cifs

Name	Туре	Description
_links	_links	
ad_domain	ad_domain	

Name	Туре	Description
allowed	boolean	If this is set to true, an SVM administrator can manage the CIFS service. If it is false, only the cluster administrator can manage the service.
domain_workgroup	string	The NetBIOS name of the domain or workgroup associated with the CIFS server.
enabled	boolean	If allowed, setting to true enables the CIFS service.
name	string	The NetBIOS name of the CIFS server.

dns

Name	Туре	Description
_links	_links	
domains	array[string]	A list of DNS domains. Domain names have the following requirements: • The name must contain only the following characters: A through Z, a through z, 0 through 9, ".", "-" or "_".
		 The first character of each label, delimited by ".", must be one of the following characters: A through Z or a through z or 0 through 9.
		 The last character of each label, delimited by ".", must be one of the following characters: A through Z, a through z, or 0 through 9.
		 The top level domain must contain only the following characters: A through Z, a through z.
		 The system reserves the following names:"all", "local", and "localhost".

Name	Туре	Description
servers	array[string]	The list of IP addresses of the DNS servers. Addresses can be either IPv4 or IPv6 addresses.

node

The node on which the FC port is located.

Name	Туре	Description
name	string	The name of the node on which the FC port is located.

fc_port_reference

An FC port is the physical port of an FC adapter on a cluster node that can be connected to an FC network.

Name	Туре	Description
_links	_links	
name	string	The name of the FC port.
node	node	The node on which the FC port is located.
uuid	string	The unique identifier of the FC port.

location

The location of the Fibre Channel interface is defined by the location of its port.

Name	Туре	Description
port	fc_port_reference	An FC port is the physical port of an FC adapter on a cluster node that can be connected to an FC network.

fc_interface_svm

Name	Туре	Description
_links	_links	

Name	Туре	Description
data_protocol	string	The data protocol for which the Fibre Channel interface is configured.
location	location	The location of the Fibre Channel interface is defined by the location of its port.
name	string	The name of the Fibre Channel interface.
uuid	string	The unique identifier of the Fibre Channel interface.

fcp

Name	Туре	Description
_links	_links	
allowed	boolean	If this is set to true, an SVM administrator can manage the FCP service. If it is false, only the cluster administrator can manage the service.
enabled	boolean	If allowed, setting to true enables the FCP service.

iр

IP information

Name	Туре	Description
address	string	IPv4 or IPv6 address
netmask	string	Input as netmask length (16) or IPv4 mask (255.255.0.0).

broadcast_domain

Broadcast domain UUID along with a readable name.

Name	Туре	Description
_links	_links	

Name	Туре	Description
name	string	Name of the broadcast domain, scoped to its IPspace
uuid	string	Broadcast domain UUID

home_node

Name	Туре	Description
_links	_links	
name	string	
uuid	string	

location

Home_node is optional.

Name	Туре	Description
broadcast_domain	broadcast_domain	Broadcast domain UUID along with a readable name.
home_node	home_node	

ip_subnet_reference

A named subnet. Either UUID or name can be supplied on input.

Name	Туре	Description
_links	_links	
name	string	The name of the subnet. If only the name is provided, the IPspace scope must be provided by the object this object is embedded in.
uuid	string	The UUID that uniquely identifies the subnet.

ip_interface_svm

Interface parameters. Name and home_node are optional.

Name	Туре	Description
_links	_links	

Name	Туре	Description
ip	ip	IP information
location	location	Home_node is optional.
name	string	The name of the interface (optional).
service_policy	string	Built-in service policies for SVMs.
services	array[string]	The services associated with the interface.
subnet	ip_subnet_reference	A named subnet. Either UUID or name can be supplied on input.
uuid	string	The UUID that uniquely identifies the interface.

ipspace

Either the UUID or name may be supplied on input.

Name	Туре	Description
_links	_links	
name	string	IPspace name
uuid	string	IPspace UUID

iscsi

Name	Туре	Description
_links	_links	
allowed	boolean	If this is set to true, an SVM administrator can manage the iSCSI service. If it is false, only the cluster administrator can manage the service.
enabled	boolean	If allowed, setting to true enables the ISCSI service.

ldap

Name	Туре	Description
ad_domain	string	This parameter specifies the name of the Active Directory domain used to discover LDAP servers for use by this client. This is mutually exclusive with servers during POST.
base_dn	string	Specifies the default base DN for all searches.
bind_dn	string	Specifies the user that binds to the LDAP servers. SVM API supports anonymous binding. For Simple and SASL LDAP binding, use the LDAP API endpoint.
enabled	boolean	Enable LDAP? Setting to true creates a configuration if not already created.
restrict_discovery_to_site	boolean	Specifies whether or not LDAP server discovery is restricted to site-scope.
servers	array[string]	

ndmp

Name	Туре	Description
allowed	boolean	If this is set to true, an SVM administrator can manage the NDMP service. If it is false, only the cluster administrator can manage the service.

nfs

Name	Туре	Description
_links	_links	
allowed	boolean	If this is set to true, an SVM administrator can manage the NFS service. If it is false, only the cluster administrator can manage the service.

Name	Туре	Description
enabled		If allowed, setting to true enables the NFS service.

nis

Name	Туре	Description
_links	_links	
domain	string	The NIS domain to which this configuration belongs.
enabled	boolean	Enable NIS? Setting to true creates a configuration if not already created.
servers	array[string]	A list of hostnames or IP addresses of NIS servers used by the NIS domain configuration.

nsswitch

Name service switch configuration

Name	Туре	Description
group	array[string]	Group sources
hosts	array[string]	Host sources
namemap	array[string]	NameMap sources
netgroup	array[string]	NetGroup sources
passwd	array[string]	Password sources

nvme

Name	Туре	Description
_links	_links	
allowed	boolean	If this is set to true, an SVM administrator can manage the NVMe service. If it is false, only the cluster administrator can manage the service.

Name	Туре	Description
enabled	boolean	If allowed, setting to true enables the NVMe service.

qos_adaptive_policy_group_template

This optionally specifies which QoS adaptive policy group to apply to the SVM as a template. This policy group will then be assigned to volumes created or rehosted into this SVM. This policy group defines measurable service level objectives (SLOs) and Service Level Agreements (SLAs) that adjust based on the volume allocated space or used space.

Name	Туре	Description
_links	_links	
max_throughput_iops	integer	Specifies the maximum throughput in IOPS, 0 means none. This is mutually exclusive with name and UUID during POST and PATCH.
max_throughput_mbps	integer	Specifies the maximum throughput in Megabytes per sec, 0 means none. This is mutually exclusive with name and UUID during POST and PATCH.
min_throughput_iops	integer	Specifies the minimum throughput in IOPS, 0 means none. Setting "min_throughput" is supported on AFF platforms only, unless FabricPool tiering policies are set. This is mutually exclusive with name and UUID during POST and PATCH.
min_throughput_mbps	integer	Specifies the minimum throughput in Megabytes per sec, 0 means none. This is mutually exclusive with name and UUID during POST and PATCH.
name	string	The QoS policy group name. This is mutually exclusive with UUID and other QoS attributes during POST and PATCH.

Name	Туре	Description
uuid		The QoS policy group UUID. This is mutually exclusive with name and other QoS attributes during POST and PATCH.

qos_policy

This optionally specifies which QoS policy group to apply to the Vserver. This policy group defines measurable service level objectives (SLOs) that apply to the storage objects with which the policy group is associated.

Name	Туре	Description
_links	_links	
max_throughput_iops	integer	Specifies the maximum throughput in IOPS, 0 means none. This is mutually exclusive with name and UUID during POST and PATCH.
max_throughput_mbps	integer	Specifies the maximum throughput in Megabytes per sec, 0 means none. This is mutually exclusive with name and UUID during POST and PATCH.
min_throughput_iops	integer	Specifies the minimum throughput in IOPS, 0 means none. Setting "min_throughput" is supported on AFF platforms only, unless FabricPool tiering policies are set. This is mutually exclusive with name and UUID during POST and PATCH.
min_throughput_mbps	integer	Specifies the minimum throughput in Megabytes per sec, 0 means none. This is mutually exclusive with name and UUID during POST and PATCH.
name	string	The QoS policy group name. This is mutually exclusive with UUID and other QoS attributes during POST and PATCH.

Name	Туре	Description
uuid		The QoS policy group UUID. This is mutually exclusive with name and other QoS attributes during POST and PATCH.

ip_info

IP information

Name	Туре	Description
address	string	IPv4 or IPv6 address
family	string	IPv4 or IPv6
netmask	string	Input as netmask length (16) or IPv4 mask (255.255.0.0). For IPv6, the default value is 64 with a valid range of 1 to 127. Output is always netmask length.

network_route_for_svm

Name	Туре	Description
destination	ip_info	IP information
gateway	string	The IP address of the gateway router leading to the destination.

certificate

Specifies the certificate that will be used for creating HTTPS connections to the S3 server.

Name	Туре	Description
_links	_links	
name	string	Certificate name
uuid	string	Certificate UUID

s3

Name	Туре	Description
_links	_links	

Name	Туре	Description
certificate	certificate	Specifies the certificate that will be used for creating HTTPS connections to the S3 server.
default_unix_user	string	Specifies the default UNIX user for NAS Access.
default_win_user	string	Specifies the default Windows user for NAS Access.
enabled	boolean	Specifies whether or not to enable S3. Setting this value to true creates a service if one is not yet created.
is_http_enabled	boolean	Specifies whether HTTP is enabled on the S3 server. By default, HTTP is disabled on the S3 server.
is_https_enabled	boolean	Specifies whether HTTPS is enabled on the S3 server. By default, HTTPS is enabled on the S3 server.
name	string	Specifies the name of the S3 server. A server name length can range from 1 to 253 characters and can only contain the following combination of characters 0-9, A-Z, a-z, ".", and "-".
port	integer	Specifies the HTTP listener port for the S3 server. By default, HTTP is enabled on port 80.
secure_port	integer	Specifies the HTTPS listener port for the S3 server. By default, HTTPS is enabled on port 443.

snapmirror

Specifies attributes for SVM DR protection.

Name	Туре	Description
is_protected	boolean	Specifies whether the SVM is a SnapMirror source SVM, using SnapMirror to protect its data.
protected_consistency_group_co unt	integer	Specifies the number of SVM DR protected consistency groups in the SVM.
protected_volumes_count	integer	Specifies the number of SVM DR protected volumes in the SVM.

snapshot_policy

This is a reference to the Snapshot copy policy.

Name	Туре	Description
_links	_links	
name	string	
uuid	string	

storage

Name	Туре	Description
allocated	integer	Total size of the volumes in SVM, in bytes.
available	integer	Currently available storage capacity in SVM, in bytes.
limit	integer	Maximum storage permitted on a single SVM, in bytes.
limit_threshold_alert	integer	Indicates at what percentage of storage capacity an alert message is sent. The default value is 90.
limit_threshold_exceeded	boolean	Indicates whether the total storage capacity exceeds the alert percentage.
used_percentage	integer	The percentage of storage capacity used.

svm

Name	Туре	Description
_links	_links	
aggregates	array[aggregates]	List of allowed aggregates for SVM volumes. An administrator is allowed to create volumes on these aggregates.
aggregates_delegated	boolean	This property is true when the administrator has delegated the aggregates for the SVM volumes.
anti_ransomware	arw_vserver	Anti-ransomware related information for the SVM.
anti_ransomware_auto_switch_d uration_without_new_file_extensi on	integer	One of the many conditions to be satisfied to automatically switch the anti-ransomware state of the volumes in this SVM from "learning" (dry-run) to "enabled" is that no new file-extensions are observed in the volume in recent time. This parameter optionally specifies the recent time duration (in days) to be considered during which no new file-extension should be observed in a given volume to automatically switch the anti-ransomware state from 'learning'" to "enabled".
anti_ransomware_auto_switch_fr om_learning_to_enabled	boolean	This property specifies whether anti-ransomware state of the volumes in this SVM are automatically switched by the system from "learning" (dry-run) to "enabled" (active) state after sufficient learning.

Name	Туре	Description
anti_ransomware_auto_switch_mi nimum_file_count	integer	One of the many conditions to be satisfied to automatically switch the anti-ransomware state of the volumes in this SVM from "learning" (dry-run) to "enabled" is that the volume should have a minimum file count in "learning" state. This parameter optionally specifies the minimum number of newly created files in "learning" state in a given volume to automatically switch the anti-ransomware state from "learning" to "enabled".
anti_ransomware_auto_switch_mi nimum_file_extension	integer	One of the many conditions to be satisfied to automatically switch the anti-ransomware state of the volumes in this SVM from "learning" (dry-run) to "enabled" is that the volume should have minimum number of file extensions in "learning" state. This parameter optionally specifies the minimum number of new file extensions in "learning" state in a given volume to automatically switch the anti-ransomware state from "learning" to "enabled".
anti_ransomware_auto_switch_mi nimum_learning_period	integer	One of the many conditions to be satisfied to automatically switch the anti-ransomware state of the volumes in this SVM from "learning" (dry-run) to "enabled" is that the volume should be in "learning" state for sufficient time period. This parameter optionally specifies the minimum number of days a given volume should be in "learning" state to automatically switch the anti-ransomware state from "learning" to "enabled".

Name	Туре	Description
anti_ransomware_default_volume _state	string	Specifies the default Anti- ransomware state of the volumes in the SVM. Default "anti_ransomware_default_volum e_state" property is disabled for POST operation. If this value is "disabled", Anti-ransomware protection is disabled by default on the new volumes that are created in the SVM. If this value is "dry_run", Anti-ransomware protection is in learning mode by default on the new volumes that are created in the SVM. When the Anti-ransomware license is not present, this property is ignored and volumes will be created with the "disabled" state.
anti_ransomware_incoming_write _threshold	string	One of the many conditions to be satisfied to automatically switch the anti-ransomware state of the volumes in this SVM from "learning" (dry-run) to "enabled" is that the volume should have sufficient data ingested to do the learning. This parameter optionally specifies the minimum amount of data (in GB) to be written to a given volume during the learning period to automatically switch the anti-ransomware state from "learning" to "enabled". The amount of data considered as ingested also includes the data that is deleted or overwritten after ingestion.

Name	Туре	Description
anti_ransomware_incoming_write _threshold_percent	string	One of the many conditions to be satisfied to automatically switch the anti-ransomware state of the volumes in this SVM from "learning" (dry-run) to "enabled" is that the volume should have sufficient data ingested to do the learning. This parameter optionally specifies the minimum amount of data (in percentage) to be written to a given volume during the learning period to automatically switch the anti-ransomware state from "learning" to "enabled". The amount of data considered as ingested also includes the data that is deleted or overwritten after ingestion.
auto_enable_activity_tracking	boolean	Specifies whether volume activity tracking is automatically enabled on volumes that are created in the SVM.
auto_enable_analytics	boolean	Specifies whether file system analytics is automatically enabled on volumes that are created in the SVM.
certificate	certificate	Support for this field will be removed in a future release. Please use /svm/svms/{svm.uuid}/web for this field. Certificate for incoming TLS connection requests.
cifs	cifs	
comment	string	Comment
dns	dns	
fc_interfaces	array[fc_interface_svm]	FC Interface for the SVM
fcp	fcp	
ip_interfaces	array[ip_interface_svm]	IP interfaces for the SVM
ipspace	ipspace	Either the UUID or name may be supplied on input.

Name	Туре	Description
is_space_enforcement_logical	boolean	Indicates whether logical space enforcement for the SVM is enabled.
is_space_reporting_logical	boolean	Indicates whether logical space reporting for the SVM is enabled.
iscsi	iscsi	
language	string	Default volume language code. UTF-8 encoded languages are valid in POST or PATCH. Non UTF-8 language encodings are for backward compatibility and are not valid input for POST and PATCH requests.
Idap	ldap	
max_volumes	string	This property is used by cluster administrator to specify the limit on maximum number of volumes allowed in the SVM. The value can be either the string "unlimited" or a number.
name	string	The name of the SVM.
ndmp	ndmp	
nfs	nfs	
nis	nis	
nsswitch	nsswitch	Name service switch configuration
number_of_volumes_in_recovery _queue	integer	Number of volumes in the recovery queue.
nvme	nvme	

Name	Туре	Description
qos_adaptive_policy_group_temp late	qos_adaptive_policy_group_temp late	This optionally specifies which QoS adaptive policy group to apply to the SVM as a template. This policy group will then be assigned to volumes created or rehosted into this SVM. This policy group defines measurable service level objectives (SLOs) and Service Level Agreements (SLAs) that adjust based on the volume allocated space or used space.
qos_policy	qos_policy	This optionally specifies which QoS policy group to apply to the Vserver. This policy group defines measurable service level objectives (SLOs) that apply to the storage objects with which the policy group is associated.
routes	array[network_route_for_svm]	Optional array of routes for the SVM
s3	s3	
snapmirror	snapmirror	Specifies attributes for SVM DR protection.
snapshot_policy	snapshot_policy	This is a reference to the Snapshot copy policy.
state	string	SVM State
storage	storage	
subtype	string	SVM subtype. The SVM subtype sync_destination is created automatically when an SVM of subtype sync_source is created on the source MetroCluster cluster. A POST request with sync_destination as SVM subtype is invalid.
total_volume_size_in_recovery_q ueue	integer	Sum of the sizes of the volumes in the recovery queue.
uuid	string	The unique identifier of the SVM.

job_link

Name	Туре	Description
_links	_links	
uuid	string	The UUID of the asynchronous job that is triggered by a POST, PATCH, or DELETE operation.

error_arguments

Name	Туре	Description
code	string	Argument code
message	string	Message argument

returned_error

Name	Туре	Description
arguments	array[error_arguments]	Message arguments
code	string	Error code
message	string	Error message
target	string	The target parameter that caused the error.

Delete an SVM

DELETE /svm/svms/{uuid}

Introduced In: 9.6

Deletes an SVM. As a prerequisite, SVM objects must be deleted first. SnapMirror relationships must be deleted and data volumes must be offline and deleted.

- The number of parallel SVMs that can be created must not be greater than five.
- If a sixth SVM POST request is issued, the following error message is generated: "Maximum allowed SVM jobs exceeded. Wait for the existing SVM jobs to complete and try again."

Related ONTAP commands

• vserver delete

Example

Deleting an individual SVM in the cluster.

DELETE "/api/svm/svms/f16f0935-5281-11e8-b94d-005056b46485"

Learn more

• DOC /svm/svms

Parameters

Name	Туре	In	Required	Description
uuid	string	path	True	Filter by UUID
return_timeout	integer	query	False	The number of seconds to allow the call to execute before returning. When doing a POST, PATCH, or DELETE operation on a single record, the default is 0 seconds. This means that if an asynchronous operation is started, the server immediately returns HTTP code 202 (Accepted) along with a link to the job. If a non-zero value is specified for POST, PATCH, or DELETE operations, ONTAP waits that length of time to see if the job completes so it can return something other than 202. • Default value: 1 • Max value: 120 • Min value: 0

Response

```
Status: 200, Ok
```

Name	Туре	Description
job	job_link	

Example response

Response

```
Status: 202, Accepted
```

Error

```
Status: Default
```

ONTAP Error Response Codes

Error codes	Description
13434894	Maximum allowed SVM jobs exceeded. Wait and retry.
2621525	SVM cannot be deleted as it is associated with an Active Directory configured CIFS server. Delete the CIFS server using "cifs delete" and retry the operation.

Name	Туре	Description
error	returned_error	

Example error

Definitions

See Definitions

Name	Туре	Description
href	string	

_links

Name	Туре	Description
self	href	

job_link

Name	Туре	Description
_links	_links	
uuid	string	The UUID of the asynchronous job that is triggered by a POST, PATCH, or DELETE operation.

error_arguments

Name	Туре	Description
code	string	Argument code
message	string	Message argument

returned_error

Name	Туре	Description
arguments	array[error_arguments]	Message arguments
code	string	Error code
message	string	Error message
target	string	The target parameter that caused the error.

Retrieve SVM properties

GET /svm/svms/{uuid}

Introduced In: 9.6

Retrieves the properties for an individual SVM. This includes protocol configurations such as CIFS and NFS, export policies, name service configurations, and network services.

Important notes

- The SVM object includes a large set of fields and can be expensive to retrieve.
- REST APIs only expose a data SVM as an SVM.

Expensive properties

There is an added computational cost to retrieving values for these properties. They are not included by default in GET results and must be explicitly requested using the fields query parameter. See Requesting specific fields to learn more.

• snapmirror.*

Example

Retrieving an individual SVM in the cluster

GET "/api/svm/svms/f16f0935-5281-11e8-b94d-005056b46485"

Parameters

Name	Туре	In	Required	Description
uuid	string	path	True	Filter by UUID
fields	array[string]	query	False	Specify the fields to return.

Response

Status: 200, Ok

Name	Туре	Description
_links	_links	
aggregates	array[aggregates]	List of allowed aggregates for SVM volumes. An administrator is allowed to create volumes on these aggregates.

Name	Туре	Description
aggregates_delegated	boolean	This property is true when the administrator has delegated the aggregates for the SVM volumes.
anti_ransomware	arw_vserver	Anti-ransomware related information for the SVM.
anti_ransomware_auto_switch_dur ation_without_new_file_extension	integer	One of the many conditions to be satisfied to automatically switch the anti-ransomware state of the volumes in this SVM from "learning" (dry-run) to "enabled" is that no new file-extensions are observed in the volume in recent time. This parameter optionally specifies the recent time duration (in days) to be considered during which no new file-extension should be observed in a given volume to automatically switch the anti-ransomware state from 'learning'" to "enabled".
anti_ransomware_auto_switch_fro m_learning_to_enabled	boolean	This property specifies whether anti-ransomware state of the volumes in this SVM are automatically switched by the system from "learning" (dry-run) to "enabled" (active) state after sufficient learning.
anti_ransomware_auto_switch_min imum_file_count	integer	One of the many conditions to be satisfied to automatically switch the anti-ransomware state of the volumes in this SVM from "learning" (dry-run) to "enabled" is that the volume should have a minimum file count in "learning" state. This parameter optionally specifies the minimum number of newly created files in "learning" state in a given volume to automatically switch the anti-ransomware state from "learning" to "enabled".

Name	Туре	Description
anti_ransomware_auto_switch_min imum_file_extension	integer	One of the many conditions to be satisfied to automatically switch the anti-ransomware state of the volumes in this SVM from "learning" (dry-run) to "enabled" is that the volume should have minimum number of file extensions in "learning" state. This parameter optionally specifies the minimum number of new file extensions in "learning" state in a given volume to automatically switch the anti-ransomware state from "learning" to "enabled".
anti_ransomware_auto_switch_min imum_learning_period	integer	One of the many conditions to be satisfied to automatically switch the anti-ransomware state of the volumes in this SVM from "learning" (dry-run) to "enabled" is that the volume should be in "learning" state for sufficient time period. This parameter optionally specifies the minimum number of days a given volume should be in "learning" state to automatically switch the anti-ransomware state from "learning" to "enabled".
anti_ransomware_default_volume_ state	string	Specifies the default Antiransomware state of the volumes in the SVM. Default "anti_ransomware_default_volume _state" property is disabled for POST operation. If this value is "disabled", Anti-ransomware protection is disabled by default on the new volumes that are created in the SVM. If this value is "dry_run", Anti-ransomware protection is in learning mode by default on the new volumes that are created in the SVM. When the Anti-ransomware license is not present, this property is ignored and volumes will be created with the "disabled" state.

Name	Туре	Description
anti_ransomware_incoming_write_t hreshold	string	One of the many conditions to be satisfied to automatically switch the anti-ransomware state of the volumes in this SVM from "learning" (dry-run) to "enabled" is that the volume should have sufficient data ingested to do the learning. This parameter optionally specifies the minimum amount of data (in GB) to be written to a given volume during the learning period to automatically switch the anti-ransomware state from "learning" to "enabled". The amount of data considered as ingested also includes the data that is deleted or overwritten after ingestion.
anti_ransomware_incoming_write_t hreshold_percent	string	One of the many conditions to be satisfied to automatically switch the anti-ransomware state of the volumes in this SVM from "learning" (dry-run) to "enabled" is that the volume should have sufficient data ingested to do the learning. This parameter optionally specifies the minimum amount of data (in percentage) to be written to a given volume during the learning period to automatically switch the anti-ransomware state from "learning" to "enabled". The amount of data considered as ingested also includes the data that is deleted or overwritten after ingestion.
auto_enable_activity_tracking	boolean	Specifies whether volume activity tracking is automatically enabled on volumes that are created in the SVM.
auto_enable_analytics	boolean	Specifies whether file system analytics is automatically enabled on volumes that are created in the SVM.

Name	Туре	Description
certificate	certificate	Support for this field will be removed in a future release. Please use /svm/svms/{svm.uuid}/web for this field. Certificate for incoming TLS connection requests.
cifs	cifs	
comment	string	Comment
dns	dns	
fc_interfaces	array[fc_interface_svm]	FC Interface for the SVM
fcp	fcp	
ip_interfaces	array[ip_interface_svm]	IP interfaces for the SVM
ipspace	ipspace	Either the UUID or name may be supplied on input.
is_space_enforcement_logical	boolean	Indicates whether logical space enforcement for the SVM is enabled.
is_space_reporting_logical	boolean	Indicates whether logical space reporting for the SVM is enabled.
iscsi	iscsi	
language	string	Default volume language code. UTF-8 encoded languages are valid in POST or PATCH. Non UTF- 8 language encodings are for backward compatibility and are not valid input for POST and PATCH requests.
ldap	Idap	
max_volumes	string	This property is used by cluster administrator to specify the limit on maximum number of volumes allowed in the SVM. The value can be either the string "unlimited" or a number.
name	string	The name of the SVM.
ndmp	ndmp	

Name	Туре	Description
nfs	nfs	
nis	nis	
nsswitch	nsswitch	Name service switch configuration
number_of_volumes_in_recovery_ queue	integer	Number of volumes in the recovery queue.
nvme	nvme	
qos_adaptive_policy_group_templa te	qos_adaptive_policy_group_templa te	This optionally specifies which QoS adaptive policy group to apply to the SVM as a template. This policy group will then be assigned to volumes created or rehosted into this SVM. This policy group defines measurable service level objectives (SLOs) and Service Level Agreements (SLAs) that adjust based on the volume allocated space or used space.
qos_policy	qos_policy	This optionally specifies which QoS policy group to apply to the Vserver. This policy group defines measurable service level objectives (SLOs) that apply to the storage objects with which the policy group is associated.
routes	array[network_route_for_svm]	Optional array of routes for the SVM
s3	s3	
snapmirror	snapmirror	Specifies attributes for SVM DR protection.
snapshot_policy	snapshot_policy	This is a reference to the Snapshot copy policy.
state	string	SVM State
storage	storage	

Name	Туре	Description
subtype	string	SVM subtype. The SVM subtype sync_destination is created automatically when an SVM of subtype sync_source is created on the source MetroCluster cluster. A POST request with sync_destination as SVM subtype is invalid.
total_volume_size_in_recovery_qu eue	integer	Sum of the sizes of the volumes in the recovery queue.
uuid	string	The unique identifier of the SVM.

```
" links": {
 "self": {
   "href": "/api/resourcelink"
 }
},
"aggregates": [
    " links": {
     "self": {
        "href": "/api/resourcelink"
     }
    },
    "available size": 10156560384,
    "name": "aggr1",
    "snaplock type": "string",
    "state": "string",
    "type": "string",
    "uuid": "1cd8a442-86d1-11e0-ae1c-123478563412"
 }
1,
"anti ransomware default volume state": "string",
"anti ransomware incoming write threshold": "string",
"anti ransomware incoming write threshold percent": "string",
"certificate": {
  " links": {
   "self": {
     "href": "/api/resourcelink"
   }
  },
  "name": "string",
  "uuid": "1cd8a442-86d1-11e0-ae1c-123478563412"
},
"cifs": {
  " links": {
   "self": {
     "href": "/api/resourcelink"
   }
  },
  "ad domain": {
   "default site": "string",
    "fqdn": "example.com",
    "organizational unit": "string",
    "password": "string",
```

```
"user": "string"
  "domain workgroup": "string",
 "name": "CIFS1"
"comment": "string",
"dns": {
 " links": {
   "self": {
    "href": "/api/resourcelink"
   }
  },
  "domains": [
   "example.com",
   "example2.example3.com"
 ],
 "servers": [
  "10.224.65.20",
  "2001:db08:a0b:12f0::1"
 ]
} ,
"fc interfaces": [
    " links": {
     "self": {
       "href": "/api/resourcelink"
     }
    },
    "data protocol": "string",
    "location": {
      "port": {
        " links": {
         "self": {
           "href": "/api/resourcelink"
        },
        "name": "0a",
       "node": {
        "name": "node1"
       },
       "uuid": "1cd8a442-86d1-11e0-ae1c-123478563412"
   "name": "lif1",
    "uuid": "1cd8a442-86d1-11e0-ae1c-123478563412"
```

```
],
"fcp": {
 " links": {
   "self": {
     "href": "/api/resourcelink"
 }
} ,
"ip interfaces": [
   " links": {
     "self": {
       "href": "/api/resourcelink"
     }
    },
    "ip": {
     "address": "10.10.10.7",
     "netmask": "24"
   },
    "location": {
      "broadcast domain": {
       " links": {
          "self": {
           "href": "/api/resourcelink"
         }
        },
        "name": "bd1",
       "uuid": "1cd8a442-86d1-11e0-ae1c-123478563412"
      },
      "home node": {
        " links": {
          "self": {
           "href": "/api/resourcelink"
        },
        "name": "node1",
       "uuid": "1cd8a442-86d1-11e0-ae1c-123478563412"
     }
    },
    "name": "lif1",
    "service policy": "string",
    "services": [
    "string"
    ],
    "subnet": {
     " links": {
```

```
"self": {
         "href": "/api/resourcelink"
       }
      } ,
      "name": "subnet1",
     "uuid": "1cd8a442-86d1-11e0-ae1c-123478563412"
    },
    "uuid": "1cd8a442-86d1-11e0-ae1c-123478563412"
  }
],
"ipspace": {
 " links": {
   "self": {
     "href": "/api/resourcelink"
   }
  },
  "name": "exchange",
 "uuid": "1cd8a442-86d1-11e0-ae1c-123478563412"
},
"iscsi": {
 " links": {
   "self": {
     "href": "/api/resourcelink"
   }
  }
"language": "c.utf_8",
"ldap": {
 "ad domain": "string",
 "base dn": "string",
 "bind dn": "string",
 "servers": [
   "string"
 ]
},
"max volumes": "string",
"name": "svm1",
"nfs": {
 " links": {
   "self": {
     "href": "/api/resourcelink"
  }
},
"nis": {
 " links": {
```

```
"self": {
     "href": "/api/resourcelink"
   }
  },
  "domain": "string",
 "servers": [
  "string"
 ]
},
"nsswitch": {
  "group": [
  "string"
 ],
  "hosts": [
  "string"
 ],
  "namemap": [
  "string"
  "netgroup": [
  "string"
 ],
 "passwd": [
  "string"
 1
"number of volumes in recovery queue": 0,
"nvme": {
 " links": {
   "self": {
    "href": "/api/resourcelink"
   }
 }
"qos adaptive policy group template": {
 " links": {
   "self": {
    "href": "/api/resourcelink"
   }
  },
  "max throughput iops": 10000,
  "max throughput mbps": 500,
  "min throughput iops": 2000,
  "min throughput mbps": 500,
  "name": "performance",
  "uuid": "1cd8a442-86d1-11e0-ae1c-123478563412"
```

```
},
"qos policy": {
  " links": {
    "self": {
     "href": "/api/resourcelink"
  },
  "max throughput iops": 10000,
  "max throughput mbps": 500,
  "min throughput iops": 2000,
  "min throughput mbps": 500,
  "name": "performance",
 "uuid": "1cd8a442-86d1-11e0-ae1c-123478563412"
},
"routes": [
    "destination": {
     "address": "10.10.10.7",
     "family": "string",
     "netmask": "24"
   },
   "gateway": "10.1.1.1"
 }
],
"s3": {
 " links": {
   "self": {
     "href": "/api/resourcelink"
   }
  },
  "certificate": {
   " links": {
     "self": {
        "href": "/api/resourcelink"
     }
    },
   "name": "string",
   "uuid": "1cd8a442-86d1-11e0-ae1c-123478563412"
  "default unix user": "string",
  "default win user": "string",
 "name": "s3-server-1"
},
"snapmirror": {
  "protected consistency group count": 0,
  "protected volumes count": 0
```

```
} ,
  "snapshot policy": {
    " links": {
     "self": {
       "href": "/api/resourcelink"
    },
    "name": "default",
    "uuid": "1cd8a442-86d1-11e0-ae1c-123478563412"
 } ,
 "state": "running",
 "storage": {
   "allocated": 0,
   "available": 0,
   "used percentage": 0
 "subtype": "string",
 "total volume size in recovery queue": 0,
 "uuid": "02c9e252-41be-11e9-81d5-00a0986138f7"
}
```

Error

```
Status: Default
```

ONTAP Error Response Codes

Error codes	Description
262188	Field "top_metric" was specified twice (to "iops.read" and "throughput.read").

Name	Туре	Description
error	returned_error	

Example error

Definitions

See Definitions

href

Name	Туре	Description
href	string	

_links

Name	Туре	Description
self	href	

aggregates

Name	Туре	Description
_links	_links	
available_size	integer	Space available, in bytes.
name	string	
snaplock_type	string	SnapLock type.
state	string	Aggregate state.
type	string	Type of aggregate.
uuid	string	

event_log

Name	Туре	Description
is_enabled_on_new_file_extension_seen	boolean	Specifies whether to send an EMS when a new file extension is discovered.
is_enabled_on_snapshot_copy_c reation	boolean	Specifies whether to send an EMS when a Snapshot copy is created.

arw_vserver

Anti-ransomware related information for the SVM.

Name	Туре	Description
event_log	event_log	

certificate

Support for this field will be removed in a future release. Please use /svm/svms/{svm.uuid}/web for this field. Certificate for incoming TLS connection requests.

Name	Туре	Description
_links	_links	
name	string	Certificate name
uuid	string	Certificate UUID

ad_domain

Name	Туре	Description
default_site	string	The default site used by LIFs that do not have a site membership.
fqdn	string	The fully qualified domain name of the Windows Active Directory to which this CIFS server belongs. A CIFS server appears as a member of Windows server object in the Active Directory store.
organizational_unit	string	Specifies the organizational unit within the Active Directory domain to associate with the CIFS server.
password	string	The account password used to add this CIFS server to the Active Directory. This is not audited. Valid in POST only.
user	string	The user account used to add this CIFS server to the Active Directory. Valid in POST only.

cifs

Name	Туре	Description
_links	_links	
ad_domain	ad_domain	

Name	Туре	Description
allowed	boolean	If this is set to true, an SVM administrator can manage the CIFS service. If it is false, only the cluster administrator can manage the service.
domain_workgroup	string	The NetBIOS name of the domain or workgroup associated with the CIFS server.
enabled	boolean	If allowed, setting to true enables the CIFS service.
name	string	The NetBIOS name of the CIFS server.

dns

Name	Туре	Description
_links	_links	
domains	array[string]	A list of DNS domains. Domain names have the following requirements: • The name must contain only the following characters: A through Z, a through z, 0 through 9, ".", "-" or "_".
		 The first character of each label, delimited by ".", must be one of the following characters: A through Z or a through z or 0 through 9.
		 The last character of each label, delimited by ".", must be one of the following characters: A through Z, a through z, or 0 through 9.
		 The top level domain must contain only the following characters: A through Z, a through z.
		 The system reserves the following names:"all", "local", and "localhost".

Name	Туре	Description
servers	array[string]	The list of IP addresses of the DNS servers. Addresses can be either IPv4 or IPv6 addresses.

node

The node on which the FC port is located.

Name	Туре	Description
name	string	The name of the node on which the FC port is located.

fc_port_reference

An FC port is the physical port of an FC adapter on a cluster node that can be connected to an FC network.

Name	Туре	Description
_links	_links	
name	string	The name of the FC port.
node	node	The node on which the FC port is located.
uuid	string	The unique identifier of the FC port.

location

The location of the Fibre Channel interface is defined by the location of its port.

Name	Туре	Description
port	fc_port_reference	An FC port is the physical port of an FC adapter on a cluster node that can be connected to an FC network.

fc_interface_svm

Name	Туре	Description
_links	_links	

Name	Туре	Description
data_protocol	string	The data protocol for which the Fibre Channel interface is configured.
location	location	The location of the Fibre Channel interface is defined by the location of its port.
name	string	The name of the Fibre Channel interface.
uuid	string	The unique identifier of the Fibre Channel interface.

fcp

Name	Туре	Description
_links	_links	
allowed	boolean	If this is set to true, an SVM administrator can manage the FCP service. If it is false, only the cluster administrator can manage the service.
enabled	boolean	If allowed, setting to true enables the FCP service.

ip

IP information

Name	Туре	Description
address	string	IPv4 or IPv6 address
netmask	string	Input as netmask length (16) or IPv4 mask (255.255.0.0).

broadcast_domain

Broadcast domain UUID along with a readable name.

Name	Туре	Description
_links	_links	

Name	Туре	Description
name	string	Name of the broadcast domain, scoped to its IPspace
uuid	string	Broadcast domain UUID

home_node

Name	Туре	Description
_links	_links	
name	string	
uuid	string	

location

Home_node is optional.

Name	Туре	Description
broadcast_domain	broadcast_domain	Broadcast domain UUID along with a readable name.
home_node	home_node	

ip_subnet_reference

A named subnet. Either UUID or name can be supplied on input.

Name	Туре	Description
_links	_links	
name	string	The name of the subnet. If only the name is provided, the IPspace scope must be provided by the object this object is embedded in.
uuid	string	The UUID that uniquely identifies the subnet.

ip_interface_svm

Interface parameters. Name and home_node are optional.

Name	Туре	Description
_links	_links	

Name	Туре	Description
ip	ip	IP information
location	location	Home_node is optional.
name	string	The name of the interface (optional).
service_policy	string	Built-in service policies for SVMs.
services	array[string]	The services associated with the interface.
subnet	ip_subnet_reference	A named subnet. Either UUID or name can be supplied on input.
uuid	string	The UUID that uniquely identifies the interface.

ipspace

Either the UUID or name may be supplied on input.

Name	Туре	Description
_links	_links	
name	string	IPspace name
uuid	string	IPspace UUID

iscsi

Name	Туре	Description
_links	_links	
allowed	boolean	If this is set to true, an SVM administrator can manage the iSCSI service. If it is false, only the cluster administrator can manage the service.
enabled	boolean	If allowed, setting to true enables the ISCSI service.

ldap

Name	Туре	Description
ad_domain	string	This parameter specifies the name of the Active Directory domain used to discover LDAP servers for use by this client. This is mutually exclusive with servers during POST.
base_dn	string	Specifies the default base DN for all searches.
bind_dn	string	Specifies the user that binds to the LDAP servers. SVM API supports anonymous binding. For Simple and SASL LDAP binding, use the LDAP API endpoint.
enabled	boolean	Enable LDAP? Setting to true creates a configuration if not already created.
restrict_discovery_to_site	boolean	Specifies whether or not LDAP server discovery is restricted to site-scope.
servers	array[string]	

ndmp

Name	Туре	Description
allowed	boolean	If this is set to true, an SVM administrator can manage the NDMP service. If it is false, only the cluster administrator can manage the service.

nfs

Name	Туре	Description
_links	_links	
allowed	boolean	If this is set to true, an SVM administrator can manage the NFS service. If it is false, only the cluster administrator can manage the service.

Name	Туре	Description
enabled		If allowed, setting to true enables the NFS service.

nis

Name	Туре	Description
_links	_links	
domain	string	The NIS domain to which this configuration belongs.
enabled	boolean	Enable NIS? Setting to true creates a configuration if not already created.
servers	array[string]	A list of hostnames or IP addresses of NIS servers used by the NIS domain configuration.

nsswitch

Name service switch configuration

Name	Туре	Description
group	array[string]	Group sources
hosts	array[string]	Host sources
namemap	array[string]	NameMap sources
netgroup	array[string]	NetGroup sources
passwd	array[string]	Password sources

nvme

Name	Туре	Description
_links	_links	
allowed	boolean	If this is set to true, an SVM administrator can manage the NVMe service. If it is false, only the cluster administrator can manage the service.

Name	Туре	Description
enabled		If allowed, setting to true enables the NVMe service.

qos_adaptive_policy_group_template

This optionally specifies which QoS adaptive policy group to apply to the SVM as a template. This policy group will then be assigned to volumes created or rehosted into this SVM. This policy group defines measurable service level objectives (SLOs) and Service Level Agreements (SLAs) that adjust based on the volume allocated space or used space.

Name	Туре	Description
_links	_links	
max_throughput_iops	integer	Specifies the maximum throughput in IOPS, 0 means none. This is mutually exclusive with name and UUID during POST and PATCH.
max_throughput_mbps	integer	Specifies the maximum throughput in Megabytes per sec, 0 means none. This is mutually exclusive with name and UUID during POST and PATCH.
min_throughput_iops	integer	Specifies the minimum throughput in IOPS, 0 means none. Setting "min_throughput" is supported on AFF platforms only, unless FabricPool tiering policies are set. This is mutually exclusive with name and UUID during POST and PATCH.
min_throughput_mbps	integer	Specifies the minimum throughput in Megabytes per sec, 0 means none. This is mutually exclusive with name and UUID during POST and PATCH.
name	string	The QoS policy group name. This is mutually exclusive with UUID and other QoS attributes during POST and PATCH.

Name	Туре	Description
uuid		The QoS policy group UUID. This is mutually exclusive with name and other QoS attributes during POST and PATCH.

qos_policy

This optionally specifies which QoS policy group to apply to the Vserver. This policy group defines measurable service level objectives (SLOs) that apply to the storage objects with which the policy group is associated.

Name	Туре	Description
_links	_links	
max_throughput_iops	integer	Specifies the maximum throughput in IOPS, 0 means none. This is mutually exclusive with name and UUID during POST and PATCH.
max_throughput_mbps	integer	Specifies the maximum throughput in Megabytes per sec, 0 means none. This is mutually exclusive with name and UUID during POST and PATCH.
min_throughput_iops	integer	Specifies the minimum throughput in IOPS, 0 means none. Setting "min_throughput" is supported on AFF platforms only, unless FabricPool tiering policies are set. This is mutually exclusive with name and UUID during POST and PATCH.
min_throughput_mbps	integer	Specifies the minimum throughput in Megabytes per sec, 0 means none. This is mutually exclusive with name and UUID during POST and PATCH.
name	string	The QoS policy group name. This is mutually exclusive with UUID and other QoS attributes during POST and PATCH.

Name	Туре	Description
uuid		The QoS policy group UUID. This is mutually exclusive with name and other QoS attributes during POST and PATCH.

ip_info

IP information

Name	Туре	Description
address	string	IPv4 or IPv6 address
family	string	IPv4 or IPv6
netmask	string	Input as netmask length (16) or IPv4 mask (255.255.0.0). For IPv6, the default value is 64 with a valid range of 1 to 127. Output is always netmask length.

network_route_for_svm

Name	Туре	Description
destination	ip_info	IP information
gateway	string	The IP address of the gateway router leading to the destination.

certificate

Specifies the certificate that will be used for creating HTTPS connections to the S3 server.

Name	Туре	Description
_links	_links	
name	string	Certificate name
uuid	string	Certificate UUID

s3

Name	Туре	Description
_links	_links	

Name	Туре	Description
certificate	certificate	Specifies the certificate that will be used for creating HTTPS connections to the S3 server.
default_unix_user	string	Specifies the default UNIX user for NAS Access.
default_win_user	string	Specifies the default Windows user for NAS Access.
enabled	boolean	Specifies whether or not to enable S3. Setting this value to true creates a service if one is not yet created.
is_http_enabled	boolean	Specifies whether HTTP is enabled on the S3 server. By default, HTTP is disabled on the S3 server.
is_https_enabled	boolean	Specifies whether HTTPS is enabled on the S3 server. By default, HTTPS is enabled on the S3 server.
name	string	Specifies the name of the S3 server. A server name length can range from 1 to 253 characters and can only contain the following combination of characters 0-9, A-Z, a-z, ".", and "-".
port	integer	Specifies the HTTP listener port for the S3 server. By default, HTTP is enabled on port 80.
secure_port	integer	Specifies the HTTPS listener port for the S3 server. By default, HTTPS is enabled on port 443.

snapmirror

Specifies attributes for SVM DR protection.

Name	Туре	Description
is_protected	boolean	Specifies whether the SVM is a SnapMirror source SVM, using SnapMirror to protect its data.
protected_consistency_group_co unt	integer	Specifies the number of SVM DR protected consistency groups in the SVM.
protected_volumes_count	integer	Specifies the number of SVM DR protected volumes in the SVM.

snapshot_policy

This is a reference to the Snapshot copy policy.

Name	Туре	Description
_links	_links	
name	string	
uuid	string	

storage

Name	Туре	Description
allocated	integer	Total size of the volumes in SVM, in bytes.
available	integer	Currently available storage capacity in SVM, in bytes.
limit	integer	Maximum storage permitted on a single SVM, in bytes.
limit_threshold_alert	integer	Indicates at what percentage of storage capacity an alert message is sent. The default value is 90.
limit_threshold_exceeded	boolean	Indicates whether the total storage capacity exceeds the alert percentage.
used_percentage	integer	The percentage of storage capacity used.

error_arguments

Name	Туре	Description
code	string	Argument code
message	string	Message argument

returned_error

Name	Туре	Description
arguments	array[error_arguments]	Message arguments
code	string	Error code
message	string	Error message
target	string	The target parameter that caused the error.

Update SVM properties

PATCH /svm/svms/{uuid}

Introduced In: 9.6

Updates one or more of the following properties of an individual SVM: SVM name, SVM default volume language code, SVM comment, and SVM state.

Related ONTAP commands

- vserver modify
- vserver rename
- vserver start
- vserver stop
- security ssl modify
- vserver add-protocols
- vserver remove-protocols

Examples

1. Stops an SVM and updates the "comment" field for an individual SVM

```
PATCH "/api/svm/svms/f16f0935-5281-11e8-b94d-005056b46485"
'{"state":"stopped", "comment":"This SVM is stopped."}'
```

1. Starts an SVM and updates the "comment" field for an individual SVM

```
PATCH "/api/svm/svms/f16f0935-5281-11e8-b94d-005056b46485"
'{"state":"running", "comment":"This SVM is running."}'
```

1. Updates the "language" field for an individual SVM

```
PATCH "/api/svm/svms/f16f0935-5281-11e8-b94d-005056b46485"
'{"language":"en.UTF-8"}'
```

1. Updates the "name" field for an SVM or renames the SVM

```
PATCH "/api/svm/svms/f16f0935-5281-11e8-b94d-005056b46485"
'{"name":"svm_new"}'
```

1. Updates the aggregates for an individual SVM

```
PATCH "/api/svm/svms/f16f0935-5281-11e8-b94d-005056b46485"
'{"aggregates":{"name":["aggr1","aggr2","aggr3"]}}'
```

1. Updates the Snapshot copy policy for an individual SVM

```
PATCH "/api/svm/svms/f16f0935-5281-11e8-b94d-005056b46485"
'{"snapshot_policy":{"name":"custom1"}}'
```

1. Updates the TLS certificate for an individual SVM

```
PATCH "/api/svm/svms/f16f0935-5281-11e8-b94d-005056b46485"

'{"certificate":{"uuid":"1cd8a442-86d1-11e0-ae1c-123478563412"}}'
```

1. Updates the QoS policy for the SVM

```
PATCH "/api/svm/svms/f16f0935-5281-11e8-b94d-005056b46485"
'{"qos_policy_group":{"name":"qpolicy1"}}'
```

1. Allows NFS protocol which was previously disallowed for the SVM

```
PATCH "/api/svm/svms/f16f0935-5281-11e8-b94d-005056b46485"
'{"nfs":{"allowed":"true"}}'
```

1. Updates the max volume limit for the SVM

```
PATCH "/api/svm/svms/f16f0935-5281-11e8-b94d-005056b46485"
'{"max_volumes":"200"}'
```

1. Updates whether file system analytics is enabled on all newly created volumes in the SVM.

```
PATCH "/api/svm/svms/f16f0935-5281-11e8-b94d-005056b46485"
'{"auto_enable_analytics":"true"}'
```

1. Updates whether volume activity tracking is enabled on all newly created volumes in the SVM.

```
PATCH "/api/svm/svms/f16f0935-5281-11e8-b94d-005056b46485"
'{"auto_enable_activity_tracking":"true"}'
```

1. Updates the QoS adaptive policy group template for the SVM.

```
PATCH "/api/svm/svms/f16f0935-5281-11e8-b94d-005056b46485"
'{"qos_adaptive_policy_group_template":{"name":"aqpolicy1"}}'
```

1. Updates the maximum storage permitted on a single SVM.

```
PATCH "/api/svm/svms/f16f0935-5281-11e8-b94d-005056b46485"

'{"storage":{"limit":"40GB"}}'
```

1. Updates the percentage of storage capacity at which an alert message is sent.

```
PATCH "/api/svm/svms/f16f0935-5281-11e8-b94d-005056b46485"
'{"storage":{"limit":"400MB", "limit_threshold_alert":"98"}}'
```

Learn more

DOC /svm/svms

Parameters

Name	Туре	In	Required	Description
uuid	string	path	True	Filter by UUID
return_timeout	integer	query	False	The number of seconds to allow the call to execute before returning. When doing a POST, PATCH, or DELETE operation on a single record, the default is 0 seconds. This means that if an asynchronous operation is started, the server immediately returns HTTP code 202 (Accepted) along with a link to the job. If a non-zero value is specified for POST, PATCH, or DELETE operations, ONTAP waits that length of time to see if the job completes so it can return something other than 202. • Default value: 1 • Max value: 120 • Min value: 0

Request Body

Name	Туре	Description
_links	_links	
aggregates	array[aggregates]	List of allowed aggregates for SVM volumes. An administrator is allowed to create volumes on these aggregates.
aggregates_delegated	boolean	This property is true when the administrator has delegated the aggregates for the SVM volumes.

Name	Туре	Description
anti_ransomware	arw_vserver	Anti-ransomware related information for the SVM.
anti_ransomware_auto_switch_dur ation_without_new_file_extension	integer	One of the many conditions to be satisfied to automatically switch the anti-ransomware state of the volumes in this SVM from "learning" (dry-run) to "enabled" is that no new file-extensions are observed in the volume in recent time. This parameter optionally specifies the recent time duration (in days) to be considered during which no new file-extension should be observed in a given volume to automatically switch the anti-ransomware state from '`learning`" to "enabled".
anti_ransomware_auto_switch_fro m_learning_to_enabled	boolean	This property specifies whether anti-ransomware state of the volumes in this SVM are automatically switched by the system from "learning" (dry-run) to "enabled" (active) state after sufficient learning.
anti_ransomware_auto_switch_min imum_file_count	integer	One of the many conditions to be satisfied to automatically switch the anti-ransomware state of the volumes in this SVM from "learning" (dry-run) to "enabled" is that the volume should have a minimum file count in "learning" state. This parameter optionally specifies the minimum number of newly created files in "learning" state in a given volume to automatically switch the anti-ransomware state from "learning" to "enabled".

Name	Туре	Description
anti_ransomware_auto_switch_min imum_file_extension	integer	One of the many conditions to be satisfied to automatically switch the anti-ransomware state of the volumes in this SVM from "learning" (dry-run) to "enabled" is that the volume should have minimum number of file extensions in "learning" state. This parameter optionally specifies the minimum number of new file extensions in "learning" state in a given volume to automatically switch the anti-ransomware state from "learning" to "enabled".
anti_ransomware_auto_switch_min imum_learning_period	integer	One of the many conditions to be satisfied to automatically switch the anti-ransomware state of the volumes in this SVM from "learning" (dry-run) to "enabled" is that the volume should be in "learning" state for sufficient time period. This parameter optionally specifies the minimum number of days a given volume should be in "learning" state to automatically switch the anti-ransomware state from "learning" to "enabled".
anti_ransomware_default_volume_ state	string	Specifies the default Antiransomware state of the volumes in the SVM. Default "anti_ransomware_default_volume _state" property is disabled for POST operation. If this value is "disabled", Anti-ransomware protection is disabled by default on the new volumes that are created in the SVM. If this value is "dry_run", Anti-ransomware protection is in learning mode by default on the new volumes that are created in the SVM. When the Anti-ransomware license is not present, this property is ignored and volumes will be created with the "disabled" state.

Name	Туре	Description
anti_ransomware_incoming_write_t hreshold	string	One of the many conditions to be satisfied to automatically switch the anti-ransomware state of the volumes in this SVM from "learning" (dry-run) to "enabled" is that the volume should have sufficient data ingested to do the learning. This parameter optionally specifies the minimum amount of data (in GB) to be written to a given volume during the learning period to automatically switch the anti-ransomware state from "learning" to "enabled". The amount of data considered as ingested also includes the data that is deleted or overwritten after ingestion.
anti_ransomware_incoming_write_t hreshold_percent	string	One of the many conditions to be satisfied to automatically switch the anti-ransomware state of the volumes in this SVM from "learning" (dry-run) to "enabled" is that the volume should have sufficient data ingested to do the learning. This parameter optionally specifies the minimum amount of data (in percentage) to be written to a given volume during the learning period to automatically switch the anti-ransomware state from "learning" to "enabled". The amount of data considered as ingested also includes the data that is deleted or overwritten after ingestion.
auto_enable_activity_tracking	boolean	Specifies whether volume activity tracking is automatically enabled on volumes that are created in the SVM.
auto_enable_analytics	boolean	Specifies whether file system analytics is automatically enabled on volumes that are created in the SVM.

Name	Туре	Description
certificate	certificate	Support for this field will be removed in a future release. Please use /svm/svms/{svm.uuid}/web for this field. Certificate for incoming TLS connection requests.
cifs	cifs	
comment	string	Comment
dns	dns	
fc_interfaces	array[fc_interface_svm]	FC Interface for the SVM
fcp	fcp	
ip_interfaces	array[ip_interface_svm]	IP interfaces for the SVM
ipspace	ipspace	Either the UUID or name may be supplied on input.
is_space_enforcement_logical	boolean	Indicates whether logical space enforcement for the SVM is enabled.
is_space_reporting_logical	boolean	Indicates whether logical space reporting for the SVM is enabled.
iscsi	iscsi	
language	string	Default volume language code. UTF-8 encoded languages are valid in POST or PATCH. Non UTF- 8 language encodings are for backward compatibility and are not valid input for POST and PATCH requests.
ldap	Idap	
max_volumes	string	This property is used by cluster administrator to specify the limit on maximum number of volumes allowed in the SVM. The value can be either the string "unlimited" or a number.
name	string	The name of the SVM.
ndmp	ndmp	

Name	Туре	Description
nfs	nfs	
nis	nis	
nsswitch	nsswitch	Name service switch configuration
number_of_volumes_in_recovery_ queue	integer	Number of volumes in the recovery queue.
nvme	nvme	
qos_adaptive_policy_group_templa te	qos_adaptive_policy_group_templa te	This optionally specifies which QoS adaptive policy group to apply to the SVM as a template. This policy group will then be assigned to volumes created or rehosted into this SVM. This policy group defines measurable service level objectives (SLOs) and Service Level Agreements (SLAs) that adjust based on the volume allocated space or used space.
qos_policy	qos_policy	This optionally specifies which QoS policy group to apply to the Vserver. This policy group defines measurable service level objectives (SLOs) that apply to the storage objects with which the policy group is associated.
routes	array[network_route_for_svm]	Optional array of routes for the SVM
s3	s3	
snapmirror	snapmirror	Specifies attributes for SVM DR protection.
snapshot_policy	snapshot_policy	This is a reference to the Snapshot copy policy.
state	string	SVM State
storage	storage	

Name	Туре	Description
subtype	string	SVM subtype. The SVM subtype sync_destination is created automatically when an SVM of subtype sync_source is created on the source MetroCluster cluster. A POST request with sync_destination as SVM subtype is invalid.
total_volume_size_in_recovery_qu eue	integer	Sum of the sizes of the volumes in the recovery queue.
uuid	string	The unique identifier of the SVM.

```
" links": {
 "self": {
   "href": "/api/resourcelink"
 }
},
"aggregates": [
    " links": {
     "self": {
        "href": "/api/resourcelink"
     }
    },
    "available size": 10156560384,
    "name": "aggr1",
    "snaplock type": "string",
    "state": "string",
    "type": "string",
    "uuid": "1cd8a442-86d1-11e0-ae1c-123478563412"
 }
1,
"anti ransomware default volume state": "string",
"anti ransomware incoming write threshold": "string",
"anti ransomware incoming write threshold percent": "string",
"certificate": {
  " links": {
   "self": {
     "href": "/api/resourcelink"
   }
  },
  "name": "string",
  "uuid": "1cd8a442-86d1-11e0-ae1c-123478563412"
},
"cifs": {
  " links": {
   "self": {
     "href": "/api/resourcelink"
   }
  },
  "ad domain": {
   "default site": "string",
    "fqdn": "example.com",
    "organizational unit": "string",
    "password": "string",
```

```
"user": "string"
  "domain workgroup": "string",
 "name": "CIFS1"
"comment": "string",
"dns": {
 " links": {
   "self": {
    "href": "/api/resourcelink"
   }
  },
  "domains": [
   "example.com",
   "example2.example3.com"
 ],
 "servers": [
  "10.224.65.20",
  "2001:db08:a0b:12f0::1"
 ]
} ,
"fc interfaces": [
    " links": {
     "self": {
       "href": "/api/resourcelink"
     }
    },
    "data protocol": "string",
    "location": {
      "port": {
        " links": {
         "self": {
           "href": "/api/resourcelink"
        },
        "name": "0a",
       "node": {
        "name": "node1"
       },
       "uuid": "1cd8a442-86d1-11e0-ae1c-123478563412"
   "name": "lif1",
    "uuid": "1cd8a442-86d1-11e0-ae1c-123478563412"
```

```
],
"fcp": {
 " links": {
   "self": {
     "href": "/api/resourcelink"
 }
} ,
"ip interfaces": [
   " links": {
     "self": {
       "href": "/api/resourcelink"
     }
    },
    "ip": {
     "address": "10.10.10.7",
     "netmask": "24"
    },
    "location": {
      "broadcast domain": {
       " links": {
          "self": {
           "href": "/api/resourcelink"
         }
        },
        "name": "bd1",
       "uuid": "1cd8a442-86d1-11e0-ae1c-123478563412"
      },
      "home node": {
        " links": {
          "self": {
           "href": "/api/resourcelink"
        },
        "name": "node1",
       "uuid": "1cd8a442-86d1-11e0-ae1c-123478563412"
     }
    },
    "name": "lif1",
    "service policy": "string",
    "services": [
    "string"
    ],
    "subnet": {
     " links": {
```

```
"self": {
         "href": "/api/resourcelink"
       }
      } ,
      "name": "subnet1",
     "uuid": "1cd8a442-86d1-11e0-ae1c-123478563412"
    },
    "uuid": "1cd8a442-86d1-11e0-ae1c-123478563412"
  }
],
"ipspace": {
 " links": {
   "self": {
     "href": "/api/resourcelink"
   }
  },
  "name": "exchange",
 "uuid": "1cd8a442-86d1-11e0-ae1c-123478563412"
},
"iscsi": {
 " links": {
   "self": {
     "href": "/api/resourcelink"
   }
  }
"language": "c.utf_8",
"ldap": {
 "ad domain": "string",
 "base dn": "string",
 "bind dn": "string",
 "servers": [
   "string"
 ]
},
"max volumes": "string",
"name": "svm1",
"nfs": {
 " links": {
   "self": {
     "href": "/api/resourcelink"
  }
},
"nis": {
 " links": {
```

```
"self": {
     "href": "/api/resourcelink"
   }
  },
  "domain": "string",
 "servers": [
  "string"
 ]
},
"nsswitch": {
  "group": [
  "string"
 ],
  "hosts": [
  "string"
 ],
  "namemap": [
  "string"
  "netgroup": [
  "string"
 ],
 "passwd": [
  "string"
 1
"number of volumes in recovery queue": 0,
"nvme": {
 " links": {
   "self": {
    "href": "/api/resourcelink"
   }
 }
"qos adaptive policy group template": {
 " links": {
   "self": {
    "href": "/api/resourcelink"
   }
  },
  "max throughput iops": 10000,
  "max throughput mbps": 500,
  "min throughput iops": 2000,
  "min throughput mbps": 500,
  "name": "performance",
  "uuid": "1cd8a442-86d1-11e0-ae1c-123478563412"
```

```
"qos policy": {
  " links": {
    "self": {
     "href": "/api/resourcelink"
  },
  "max throughput iops": 10000,
  "max throughput mbps": 500,
  "min throughput iops": 2000,
  "min throughput mbps": 500,
  "name": "performance",
 "uuid": "1cd8a442-86d1-11e0-ae1c-123478563412"
},
"routes": [
    "destination": {
     "address": "10.10.10.7",
     "family": "string",
     "netmask": "24"
   },
   "gateway": "10.1.1.1"
 }
],
"s3": {
 " links": {
   "self": {
     "href": "/api/resourcelink"
   }
  } ,
  "certificate": {
   " links": {
     "self": {
        "href": "/api/resourcelink"
     }
    },
   "name": "string",
   "uuid": "1cd8a442-86d1-11e0-ae1c-123478563412"
  "default unix user": "string",
  "default win user": "string",
 "name": "s3-server-1"
},
"snapmirror": {
  "protected consistency group count": 0,
  "protected volumes count": 0
```

```
"snapshot policy": {
    " links": {
     "self": {
       "href": "/api/resourcelink"
    },
    "name": "default",
    "uuid": "1cd8a442-86d1-11e0-ae1c-123478563412"
 },
 "state": "running",
 "storage": {
   "allocated": 0,
   "available": 0,
   "used percentage": 0
 },
 "subtype": "string",
 "total volume size in recovery queue": 0,
 "uuid": "02c9e252-41be-11e9-81d5-00a0986138f7"
}
```

Response

```
Status: 200, Ok
```

Name	Туре	Description
job	job_link	

Example response

Response

Status: 202, Accepted

Error

Status: Default

ONTAP Error Response Codes

Error codes	Description
13434880	Failed to modify SVM parameters.
13434881	Failed to rename SVM.
13434883	SVM parameters except name modified successfully.
13434885	Non-UTF8 language(s) not supported.
13434886	Invalid Snapshot copy policy.
13434902	Modification of NSSwitch parameters failed for the SVM.
13434906	Operation not supported for an SVM of type syncdestination.
12451843	Certificate does not exist.
13434908	Invalid SVM name. The name is already in use by another SVM, IPSpace or cluster.
13434916	SVM is in the process of being created. Wait a few minutes, and then try the command again.
13434915	Failed to unlock the SVM because SVM create or delete job is in progress. Wait a few minutes, and then try the command again.
13434911	Invalid SVM name. Maximum supported length is 41 if SVM is of type \"sync-source\", otherwise 47.
262179	Unexpected argument "storage_limit".

Name	Туре	Description
error	returned_error	

Example error

Definitions

See Definitions

href

Name	Туре	Description
href	string	

_links

Name	Туре	Description
self	href	

aggregates

Name	Туре	Description
_links	_links	
available_size	integer	Space available, in bytes.
name	string	
snaplock_type	string	SnapLock type.
state	string	Aggregate state.
type	string	Type of aggregate.
uuid	string	

event_log

Name	Туре	Description
is_enabled_on_new_file_extensio n_seen	boolean	Specifies whether to send an EMS when a new file extension is discovered.
is_enabled_on_snapshot_copy_c reation	boolean	Specifies whether to send an EMS when a Snapshot copy is created.

arw_vserver

Anti-ransomware related information for the SVM.

Name	Туре	Description
event_log	event_log	

certificate

Support for this field will be removed in a future release. Please use /svm/svms/{svm.uuid}/web for this field. Certificate for incoming TLS connection requests.

Name	Туре	Description
_links	_links	
name	string	Certificate name
uuid	string	Certificate UUID

ad_domain

Name	Туре	Description
default_site	string	The default site used by LIFs that do not have a site membership.
fqdn	string	The fully qualified domain name of the Windows Active Directory to which this CIFS server belongs. A CIFS server appears as a member of Windows server object in the Active Directory store.
organizational_unit	string	Specifies the organizational unit within the Active Directory domain to associate with the CIFS server.
password	string	The account password used to add this CIFS server to the Active Directory. This is not audited. Valid in POST only.
user	string	The user account used to add this CIFS server to the Active Directory. Valid in POST only.

cifs

Name	Туре	Description
_links	_links	
ad_domain	ad_domain	

Name	Туре	Description
allowed	boolean	If this is set to true, an SVM administrator can manage the CIFS service. If it is false, only the cluster administrator can manage the service.
domain_workgroup	string	The NetBIOS name of the domain or workgroup associated with the CIFS server.
enabled	boolean	If allowed, setting to true enables the CIFS service.
name	string	The NetBIOS name of the CIFS server.

dns

Name	Туре	Description
_links	_links	
domains	array[string]	A list of DNS domains. Domain names have the following requirements: • The name must contain only the following characters: A through Z, a through z, 0 through 9, ".", "-" or "_".
		 The first character of each label, delimited by ".", must be one of the following characters: A through Z or a through z or 0 through 9.
		 The last character of each label, delimited by ".", must be one of the following characters: A through Z, a through z, or 0 through 9.
		 The top level domain must contain only the following characters: A through Z, a through z.
		 The system reserves the following names:"all", "local", and "localhost".

Name	Туре	Description
servers	array[string]	The list of IP addresses of the DNS servers. Addresses can be either IPv4 or IPv6 addresses.

node

The node on which the FC port is located.

Name	Туре	Description
name	string	The name of the node on which the FC port is located.

fc_port_reference

An FC port is the physical port of an FC adapter on a cluster node that can be connected to an FC network.

Name	Туре	Description
_links	_links	
name	string	The name of the FC port.
node	node	The node on which the FC port is located.
uuid	string	The unique identifier of the FC port.

location

The location of the Fibre Channel interface is defined by the location of its port.

Name	Туре	Description
port	fc_port_reference	An FC port is the physical port of an FC adapter on a cluster node that can be connected to an FC network.

fc_interface_svm

Name	Туре	Description
_links	_links	

Name	Туре	Description
data_protocol	string	The data protocol for which the Fibre Channel interface is configured.
location	location	The location of the Fibre Channel interface is defined by the location of its port.
name	string	The name of the Fibre Channel interface.
uuid	string	The unique identifier of the Fibre Channel interface.

fcp

Name	Туре	Description
_links	_links	
allowed	boolean	If this is set to true, an SVM administrator can manage the FCP service. If it is false, only the cluster administrator can manage the service.
enabled	boolean	If allowed, setting to true enables the FCP service.

iр

IP information

Name	Туре	Description
address	string	IPv4 or IPv6 address
netmask	string	Input as netmask length (16) or IPv4 mask (255.255.0.0).

broadcast_domain

Broadcast domain UUID along with a readable name.

Name	Туре	Description
_links	_links	

Name	Туре	Description
name	string	Name of the broadcast domain, scoped to its IPspace
uuid	string	Broadcast domain UUID

home_node

Name	Туре	Description
_links	_links	
name	string	
uuid	string	

location

Home_node is optional.

Name	Туре	Description
broadcast_domain	broadcast_domain	Broadcast domain UUID along with a readable name.
home_node	home_node	

ip_subnet_reference

A named subnet. Either UUID or name can be supplied on input.

Name	Туре	Description
_links	_links	
name	string	The name of the subnet. If only the name is provided, the IPspace scope must be provided by the object this object is embedded in.
uuid	string	The UUID that uniquely identifies the subnet.

ip_interface_svm

Interface parameters. Name and home_node are optional.

Name	Туре	Description
_links	_links	

Name	Туре	Description
ip	ip	IP information
location	location	Home_node is optional.
name	string	The name of the interface (optional).
service_policy	string	Built-in service policies for SVMs.
services	array[string]	The services associated with the interface.
subnet	ip_subnet_reference	A named subnet. Either UUID or name can be supplied on input.
uuid	string	The UUID that uniquely identifies the interface.

ipspace

Either the UUID or name may be supplied on input.

Name	Туре	Description
_links	_links	
name	string	IPspace name
uuid	string	IPspace UUID

iscsi

Name	Туре	Description
_links	_links	
allowed	boolean	If this is set to true, an SVM administrator can manage the iSCSI service. If it is false, only the cluster administrator can manage the service.
enabled	boolean	If allowed, setting to true enables the ISCSI service.

ldap

Name	Туре	Description
ad_domain	string	This parameter specifies the name of the Active Directory domain used to discover LDAP servers for use by this client. This is mutually exclusive with servers during POST.
base_dn	string	Specifies the default base DN for all searches.
bind_dn	string	Specifies the user that binds to the LDAP servers. SVM API supports anonymous binding. For Simple and SASL LDAP binding, use the LDAP API endpoint.
enabled	boolean	Enable LDAP? Setting to true creates a configuration if not already created.
restrict_discovery_to_site	boolean	Specifies whether or not LDAP server discovery is restricted to site-scope.
servers	array[string]	

ndmp

Name	Туре	Description
allowed	boolean	If this is set to true, an SVM administrator can manage the NDMP service. If it is false, only the cluster administrator can manage the service.

nfs

Name	Туре	Description
_links	_links	
allowed	boolean	If this is set to true, an SVM administrator can manage the NFS service. If it is false, only the cluster administrator can manage the service.

Name	Туре	Description
enabled		If allowed, setting to true enables the NFS service.

nis

Name	Туре	Description
_links	_links	
domain	string	The NIS domain to which this configuration belongs.
enabled	boolean	Enable NIS? Setting to true creates a configuration if not already created.
servers	array[string]	A list of hostnames or IP addresses of NIS servers used by the NIS domain configuration.

nsswitch

Name service switch configuration

Name	Туре	Description
group	array[string]	Group sources
hosts	array[string]	Host sources
namemap	array[string]	NameMap sources
netgroup	array[string]	NetGroup sources
passwd	array[string]	Password sources

nvme

Name	Туре	Description
_links	_links	
allowed	boolean	If this is set to true, an SVM administrator can manage the NVMe service. If it is false, only the cluster administrator can manage the service.

Name	Туре	Description
enabled		If allowed, setting to true enables the NVMe service.

qos_adaptive_policy_group_template

This optionally specifies which QoS adaptive policy group to apply to the SVM as a template. This policy group will then be assigned to volumes created or rehosted into this SVM. This policy group defines measurable service level objectives (SLOs) and Service Level Agreements (SLAs) that adjust based on the volume allocated space or used space.

Name	Туре	Description
_links	_links	
max_throughput_iops	integer	Specifies the maximum throughput in IOPS, 0 means none. This is mutually exclusive with name and UUID during POST and PATCH.
max_throughput_mbps	integer	Specifies the maximum throughput in Megabytes per sec, 0 means none. This is mutually exclusive with name and UUID during POST and PATCH.
min_throughput_iops	integer	Specifies the minimum throughput in IOPS, 0 means none. Setting "min_throughput" is supported on AFF platforms only, unless FabricPool tiering policies are set. This is mutually exclusive with name and UUID during POST and PATCH.
min_throughput_mbps	integer	Specifies the minimum throughput in Megabytes per sec, 0 means none. This is mutually exclusive with name and UUID during POST and PATCH.
name	string	The QoS policy group name. This is mutually exclusive with UUID and other QoS attributes during POST and PATCH.

Name	Туре	Description
uuid		The QoS policy group UUID. This is mutually exclusive with name and other QoS attributes during POST and PATCH.

qos_policy

This optionally specifies which QoS policy group to apply to the Vserver. This policy group defines measurable service level objectives (SLOs) that apply to the storage objects with which the policy group is associated.

Name	Туре	Description
_links	_links	
max_throughput_iops	integer	Specifies the maximum throughput in IOPS, 0 means none. This is mutually exclusive with name and UUID during POST and PATCH.
max_throughput_mbps	integer	Specifies the maximum throughput in Megabytes per sec, 0 means none. This is mutually exclusive with name and UUID during POST and PATCH.
min_throughput_iops	integer	Specifies the minimum throughput in IOPS, 0 means none. Setting "min_throughput" is supported on AFF platforms only, unless FabricPool tiering policies are set. This is mutually exclusive with name and UUID during POST and PATCH.
min_throughput_mbps	integer	Specifies the minimum throughput in Megabytes per sec, 0 means none. This is mutually exclusive with name and UUID during POST and PATCH.
name	string	The QoS policy group name. This is mutually exclusive with UUID and other QoS attributes during POST and PATCH.

Name	Туре	Description
uuid	string	The QoS policy group UUID. This is mutually exclusive with name and other QoS attributes during POST and PATCH.

ip_info

IP information

Name	Туре	Description
address	string	IPv4 or IPv6 address
family	string	IPv4 or IPv6
netmask	string	Input as netmask length (16) or IPv4 mask (255.255.0.0). For IPv6, the default value is 64 with a valid range of 1 to 127. Output is always netmask length.

network_route_for_svm

Name	Туре	Description
destination	ip_info	IP information
gateway	string	The IP address of the gateway router leading to the destination.

certificate

Specifies the certificate that will be used for creating HTTPS connections to the S3 server.

Name	Туре	Description
_links	_links	
name	string	Certificate name
uuid	string	Certificate UUID

s3

Name	Туре	Description
_links	_links	

Name	Туре	Description
certificate	certificate	Specifies the certificate that will be used for creating HTTPS connections to the S3 server.
default_unix_user	string	Specifies the default UNIX user for NAS Access.
default_win_user	string	Specifies the default Windows user for NAS Access.
enabled	boolean	Specifies whether or not to enable S3. Setting this value to true creates a service if one is not yet created.
is_http_enabled	boolean	Specifies whether HTTP is enabled on the S3 server. By default, HTTP is disabled on the S3 server.
is_https_enabled	boolean	Specifies whether HTTPS is enabled on the S3 server. By default, HTTPS is enabled on the S3 server.
name	string	Specifies the name of the S3 server. A server name length can range from 1 to 253 characters and can only contain the following combination of characters 0-9, A-Z, a-z, ".", and "-".
port	integer	Specifies the HTTP listener port for the S3 server. By default, HTTP is enabled on port 80.
secure_port	integer	Specifies the HTTPS listener port for the S3 server. By default, HTTPS is enabled on port 443.

snapmirror

Specifies attributes for SVM DR protection.

Name	Туре	Description
is_protected	boolean	Specifies whether the SVM is a SnapMirror source SVM, using SnapMirror to protect its data.
protected_consistency_group_co unt	integer	Specifies the number of SVM DR protected consistency groups in the SVM.
protected_volumes_count	integer	Specifies the number of SVM DR protected volumes in the SVM.

snapshot_policy

This is a reference to the Snapshot copy policy.

Name	Туре	Description
_links	_links	
name	string	
uuid	string	

storage

Name	Туре	Description
allocated	integer	Total size of the volumes in SVM, in bytes.
available	integer	Currently available storage capacity in SVM, in bytes.
limit	integer	Maximum storage permitted on a single SVM, in bytes.
limit_threshold_alert	integer	Indicates at what percentage of storage capacity an alert message is sent. The default value is 90.
limit_threshold_exceeded	boolean	Indicates whether the total storage capacity exceeds the alert percentage.
used_percentage	integer	The percentage of storage capacity used.

svm

Name	Туре	Description
_links	_links	
aggregates	array[aggregates]	List of allowed aggregates for SVM volumes. An administrator is allowed to create volumes on these aggregates.
aggregates_delegated	boolean	This property is true when the administrator has delegated the aggregates for the SVM volumes.
anti_ransomware	arw_vserver	Anti-ransomware related information for the SVM.
anti_ransomware_auto_switch_d uration_without_new_file_extensi on	integer	One of the many conditions to be satisfied to automatically switch the anti-ransomware state of the volumes in this SVM from "learning" (dry-run) to "enabled" is that no new file-extensions are observed in the volume in recent time. This parameter optionally specifies the recent time duration (in days) to be considered during which no new file-extension should be observed in a given volume to automatically switch the anti-ransomware state from 'learning' to "enabled".
anti_ransomware_auto_switch_fr om_learning_to_enabled	boolean	This property specifies whether anti-ransomware state of the volumes in this SVM are automatically switched by the system from "learning" (dry-run) to "enabled" (active) state after sufficient learning.

Name	Туре	Description
anti_ransomware_auto_switch_mi nimum_file_count	integer	One of the many conditions to be satisfied to automatically switch the anti-ransomware state of the volumes in this SVM from "learning" (dry-run) to "enabled" is that the volume should have a minimum file count in "learning" state. This parameter optionally specifies the minimum number of newly created files in "learning" state in a given volume to automatically switch the anti-ransomware state from "learning" to "enabled".
anti_ransomware_auto_switch_mi nimum_file_extension	integer	One of the many conditions to be satisfied to automatically switch the anti-ransomware state of the volumes in this SVM from "learning" (dry-run) to "enabled" is that the volume should have minimum number of file extensions in "learning" state. This parameter optionally specifies the minimum number of new file extensions in "learning" state in a given volume to automatically switch the anti-ransomware state from "learning" to "enabled".
anti_ransomware_auto_switch_mi nimum_learning_period	integer	One of the many conditions to be satisfied to automatically switch the anti-ransomware state of the volumes in this SVM from "learning" (dry-run) to "enabled" is that the volume should be in "learning" state for sufficient time period. This parameter optionally specifies the minimum number of days a given volume should be in "learning" state to automatically switch the anti-ransomware state from "learning" to "enabled".

Name	Туре	Description
anti_ransomware_default_volume _state	string	Specifies the default Anti- ransomware state of the volumes in the SVM. Default "anti_ransomware_default_volum e_state" property is disabled for POST operation. If this value is "disabled", Anti-ransomware protection is disabled by default on the new volumes that are created in the SVM. If this value is "dry_run", Anti-ransomware protection is in learning mode by default on the new volumes that are created in the SVM. When the Anti-ransomware license is not present, this property is ignored and volumes will be created with the "disabled" state.
anti_ransomware_incoming_write _threshold	string	One of the many conditions to be satisfied to automatically switch the anti-ransomware state of the volumes in this SVM from "learning" (dry-run) to "enabled" is that the volume should have sufficient data ingested to do the learning. This parameter optionally specifies the minimum amount of data (in GB) to be written to a given volume during the learning period to automatically switch the anti-ransomware state from "learning" to "enabled". The amount of data considered as ingested also includes the data that is deleted or overwritten after ingestion.

Name	Туре	Description
anti_ransomware_incoming_write _threshold_percent	string	One of the many conditions to be satisfied to automatically switch the anti-ransomware state of the volumes in this SVM from "learning" (dry-run) to "enabled" is that the volume should have sufficient data ingested to do the learning. This parameter optionally specifies the minimum amount of data (in percentage) to be written to a given volume during the learning period to automatically switch the anti-ransomware state from "learning" to "enabled". The amount of data considered as ingested also includes the data that is deleted or overwritten after ingestion.
auto_enable_activity_tracking	boolean	Specifies whether volume activity tracking is automatically enabled on volumes that are created in the SVM.
auto_enable_analytics	boolean	Specifies whether file system analytics is automatically enabled on volumes that are created in the SVM.
certificate	certificate	Support for this field will be removed in a future release. Please use /svm/svms/{svm.uuid}/web for this field. Certificate for incoming TLS connection requests.
cifs	cifs	
comment	string	Comment
dns	dns	
fc_interfaces	array[fc_interface_svm]	FC Interface for the SVM
fcp	fcp	
ip_interfaces	array[ip_interface_svm]	IP interfaces for the SVM
ipspace	ipspace	Either the UUID or name may be supplied on input.

Name	Туре	Description
is_space_enforcement_logical	boolean	Indicates whether logical space enforcement for the SVM is enabled.
is_space_reporting_logical	boolean	Indicates whether logical space reporting for the SVM is enabled.
iscsi	iscsi	
language	string	Default volume language code. UTF-8 encoded languages are valid in POST or PATCH. Non UTF-8 language encodings are for backward compatibility and are not valid input for POST and PATCH requests.
Idap	Idap	
max_volumes	string	This property is used by cluster administrator to specify the limit on maximum number of volumes allowed in the SVM. The value can be either the string "unlimited" or a number.
name	string	The name of the SVM.
ndmp	ndmp	
nfs	nfs	
nis	nis	
nsswitch	nsswitch	Name service switch configuration
number_of_volumes_in_recovery _queue	integer	Number of volumes in the recovery queue.
nvme	nvme	

Name	Туре	Description
qos_adaptive_policy_group_temp late	qos_adaptive_policy_group_temp late	This optionally specifies which QoS adaptive policy group to apply to the SVM as a template. This policy group will then be assigned to volumes created or rehosted into this SVM. This policy group defines measurable service level objectives (SLOs) and Service Level Agreements (SLAs) that adjust based on the volume allocated space or used space.
qos_policy	qos_policy	This optionally specifies which QoS policy group to apply to the Vserver. This policy group defines measurable service level objectives (SLOs) that apply to the storage objects with which the policy group is associated.
routes	array[network_route_for_svm]	Optional array of routes for the SVM
s3	s3	
snapmirror	snapmirror	Specifies attributes for SVM DR protection.
snapshot_policy	snapshot_policy	This is a reference to the Snapshot copy policy.
state	string	SVM State
storage	storage	
subtype	string	SVM subtype. The SVM subtype sync_destination is created automatically when an SVM of subtype sync_source is created on the source MetroCluster cluster. A POST request with sync_destination as SVM subtype is invalid.
total_volume_size_in_recovery_q ueue	integer	Sum of the sizes of the volumes in the recovery queue.
uuid	string	The unique identifier of the SVM.

job_link

Name	Туре	Description
_links	_links	
uuid	string	The UUID of the asynchronous job that is triggered by a POST, PATCH, or DELETE operation.

error_arguments

Name	Туре	Description
code	string	Argument code
message	string	Message argument

returned_error

Name	Туре	Description
arguments	array[error_arguments]	Message arguments
code	string	Error code
message	string	Error message
target	string	The target parameter that caused the error.

Copyright information

Copyright © 2024 NetApp, Inc. All Rights Reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means—graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system—without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP "AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

LIMITED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (b)(3) of the Rights in Technical Data -Noncommercial Items at DFARS 252.227-7013 (FEB 2014) and FAR 52.227-19 (DEC 2007).

Data contained herein pertains to a commercial product and/or commercial service (as defined in FAR 2.101) and is proprietary to NetApp, Inc. All NetApp technical data and computer software provided under this Agreement is commercial in nature and developed solely at private expense. The U.S. Government has a non-exclusive, non-transferrable, nonsublicensable, worldwide, limited irrevocable license to use the Data only in connection with and in support of the U.S. Government contract under which the Data was delivered. Except as provided herein, the Data may not be used, disclosed, reproduced, modified, performed, or displayed without the prior written approval of NetApp, Inc. United States Government license rights for the Department of Defense are limited to those rights identified in DFARS clause 252.227-7015(b) (FEB 2014).

Trademark information

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.