



# **Manage group membership cache settings**

## **REST API reference**

NetApp  
September 09, 2025

This PDF was generated from [https://docs.netapp.com/us-en/ontap-restapi-9161/name-services\\_cache\\_group-membership\\_settings\\_endpoint\\_overview.html](https://docs.netapp.com/us-en/ontap-restapi-9161/name-services_cache_group-membership_settings_endpoint_overview.html) on September 09, 2025. Always check docs.netapp.com for the latest.

# Table of Contents

- Manage group membership cache settings . . . . . 1
  - Name-services cache group-membership settings endpoint overview . . . . . 1
    - Overview . . . . . 1
    - Examples . . . . . 1
  - Retrieve group membership cache settings . . . . . 3
    - Related ONTAP commands . . . . . 4
    - Learn more . . . . . 4
    - Parameters . . . . . 4
    - Response . . . . . 5
    - Error . . . . . 6
    - Definitions . . . . . 7
  - Retrieve a group membership cache setting for an SVM . . . . . 9
    - Related ONTAP commands . . . . . 9
    - Learn more . . . . . 9
    - Parameters . . . . . 9
    - Response . . . . . 10
    - Error . . . . . 11
    - Definitions . . . . . 12
  - Update a group membership cache setting . . . . . 14
    - Important notes . . . . . 14
    - Related ONTAP commands . . . . . 14
    - Learn more . . . . . 14
    - Parameters . . . . . 14
    - Request Body . . . . . 14
    - Response . . . . . 15
    - Error . . . . . 15
    - Definitions . . . . . 15

# Manage group membership cache settings

## Name-services cache group-membership settings endpoint overview

### Overview

This API is used to retrieve and manage group-membership cache settings.

### Examples

#### Retrieving group-membership cache settings

---

The following example shows how to use the cache group-membership settings GET endpoint to retrieve group-membership cache settings.

```
# The API:
GET /api/name-services/cache/group-membership/settings

# The call:
curl -X GET "https://<mgmt-ip>/api/name-services/cache/group-membership/settings?fields=*" -H "accept: application/hal+json"

# The response:
{
  "records": [
    {
      "svm": {
        "uuid": "8a1a8730-2036-11ec-8457-005056bbcfdb",
        "name": "vs43"
      },
      "enabled": true,
      "ttl": "PT1H"
    },
    {
      "svm": {
        "uuid": "dc458b2f-2035-11ec-bfe2-005056bb6bef",
        "name": "vs34"
      },
      "enabled": true,
      "ttl": "PT5M"
    }
  ],
  "num_records": 2
}
```

---

## Retrieving group-membership cache settings for a given SVM

---

The following example shows how to use the cache group-membership settings GET endpoint to retrieve group-membership cache settings for a given SVM.

```
# The API:
GET /api/name-services/cache/group-membership/settings/{svm.uuid}

# The call:
curl -X GET "https://<mgmt-ip>/api/name-services/cache/group-
membership/settings/dc458b2f-2035-11ec-bfe2-005056bb6bef" -H "accept:
application/hal+json"

# The response:
{
  "svm": {
    "uuid": "dc458b2f-2035-11ec-bfe2-005056bb6bef",
    "name": "vs34"
  },
  "enabled": true,
  "ttl": "PT1H"
}
```

---

## Updating a group-membership cache setting

---

The following example shows how to use the cache group-membership settings PATCH endpoint to update a group-membership setting.

```
# The API:
PATCH /api/name-services/cache/group-membership/settings/{svm.uuid}

# The call:
curl -X PATCH "https://<mgmt-ip>/api/name-services/cache/unix-
user/settings/02c9e252-41be-11e9-81d5-00a0986138f9" -H "accept:
application/json" -H "Content-Type: application/json" -d "{ \"enabled\":
\"false\" }"
```

---

## Retrieve group membership cache settings

GET /name-services/cache/group-membership/settings

**Introduced In:** 9.11

Retrieves group-membership cache settings.

## Related ONTAP commands

- `vserver services name-service cache group-membership settings show`

## Learn more

- [DOC /name-services/cache/group-membership/settings](#)

## Parameters

| Name           | Type          | In    | Required | Description                                                                                                             |
|----------------|---------------|-------|----------|-------------------------------------------------------------------------------------------------------------------------|
| svm.name       | string        | query | False    | Filter by svm.name                                                                                                      |
| svm.uuid       | string        | query | False    | Filter by svm.uuid                                                                                                      |
| ttl            | string        | query | False    | Filter by ttl                                                                                                           |
| enabled        | boolean       | query | False    | Filter by enabled                                                                                                       |
| fields         | array[string] | query | False    | Specify the fields to return.                                                                                           |
| max_records    | integer       | query | False    | Limit the number of records returned.                                                                                   |
| return_records | boolean       | query | False    | The default is true for GET calls. When set to false, only the number of records is returned.<br><br>• Default value: 1 |

| Name           | Type          | In    | Required | Description                                                                                                                                                                                                                                                                                                                                          |
|----------------|---------------|-------|----------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| return_timeout | integer       | query | False    | <p>The number of seconds to allow the call to execute before returning. When iterating over a collection, the default is 15 seconds. ONTAP returns earlier if either max records or the end of the collection is reached.</p> <ul style="list-style-type: none"> <li>• Default value: 1</li> <li>• Max value: 120</li> <li>• Min value: 0</li> </ul> |
| order_by       | array[string] | query | False    | Order results by specified fields and optional [asc                                                                                                                                                                                                                                                                                                  |

## Response

Status: 200, Ok

| Name        | Type                                               | Description        |
|-------------|----------------------------------------------------|--------------------|
| _links      | <a href="#">_links</a>                             |                    |
| num_records | integer                                            | Number of records. |
| records     | array[ <a href="#">group_membership_settings</a> ] |                    |

## Example response

```
{
  "_links": {
    "next": {
      "href": "/api/resourcelink"
    },
    "self": {
      "href": "/api/resourcelink"
    }
  },
  "num_records": 1,
  "records": [
    {
      "_links": {
        "self": {
          "href": "/api/resourcelink"
        }
      },
      "svm": {
        "_links": {
          "self": {
            "href": "/api/resourcelink"
          }
        },
        "name": "svm1",
        "uuid": "02c9e252-41be-11e9-81d5-00a0986138f7"
      },
      "ttl": "PT2H30M"
    }
  ]
}
```

## Error

Status: Default, Error

| Name  | Type                           | Description |
|-------|--------------------------------|-------------|
| error | <a href="#">returned_error</a> |             |



### Example error

```
{
  "error": {
    "arguments": [
      {
        "code": "string",
        "message": "string"
      }
    ],
    "code": "4",
    "message": "entry doesn't exist",
    "target": "uuid"
  }
}
```

### Definitions

## See Definitions

href

| Name | Type   | Description |
|------|--------|-------------|
| href | string |             |

\_links

| Name | Type                 | Description |
|------|----------------------|-------------|
| next | <a href="#">href</a> |             |
| self | <a href="#">href</a> |             |

\_links

| Name | Type                 | Description |
|------|----------------------|-------------|
| self | <a href="#">href</a> |             |

svm

SVM, applies only to SVM-scoped objects.

| Name   | Type                   | Description                                                                         |
|--------|------------------------|-------------------------------------------------------------------------------------|
| _links | <a href="#">_links</a> |                                                                                     |
| name   | string                 | The name of the SVM. This field cannot be specified in a PATCH method.              |
| uuid   | string                 | The unique identifier of the SVM. This field cannot be specified in a PATCH method. |

group\_membership\_settings

Group membership cache setting.

| Name    | Type                   | Description                                    |
|---------|------------------------|------------------------------------------------|
| _links  | <a href="#">_links</a> |                                                |
| enabled | boolean                | Specifies whether or not the cache is enabled. |
| svm     | <a href="#">svm</a>    | SVM, applies only to SVM-scoped objects.       |

| Name | Type   | Description                                                           |
|------|--------|-----------------------------------------------------------------------|
| ttl  | string | Specifies Time to Live for list of group members, in ISO 8601 format. |

error\_arguments

| Name    | Type   | Description      |
|---------|--------|------------------|
| code    | string | Argument code    |
| message | string | Message argument |

returned\_error

| Name      | Type                                     | Description                                 |
|-----------|------------------------------------------|---------------------------------------------|
| arguments | array[ <a href="#">error_arguments</a> ] | Message arguments                           |
| code      | string                                   | Error code                                  |
| message   | string                                   | Error message                               |
| target    | string                                   | The target parameter that caused the error. |

## Retrieve a group membership cache setting for an SVM

GET /name-services/cache/group-membership/settings/{svm.uuid}

**Introduced In:** 9.11

Retrieves a group-membership cache setting for a given SVM.

### Related ONTAP commands

- `vserver services name-service cache group-membership settings show`

### Learn more

- [DOC /name-services/cache/group-membership/settings](#)

### Parameters

| Name           | Type          | In    | Required | Description                                                                                                                                                                                                                                                                                                                                          |
|----------------|---------------|-------|----------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| svm.uuid       | string        | path  | True     | SVM UUID.                                                                                                                                                                                                                                                                                                                                            |
| svm.name       | string        | query | False    | Filter by svm.name                                                                                                                                                                                                                                                                                                                                   |
| ttl            | string        | query | False    | Filter by ttl                                                                                                                                                                                                                                                                                                                                        |
| enabled        | boolean       | query | False    | Filter by enabled                                                                                                                                                                                                                                                                                                                                    |
| fields         | array[string] | query | False    | Specify the fields to return.                                                                                                                                                                                                                                                                                                                        |
| max_records    | integer       | query | False    | Limit the number of records returned.                                                                                                                                                                                                                                                                                                                |
| return_records | boolean       | query | False    | <p>The default is true for GET calls. When set to false, only the number of records is returned.</p> <ul style="list-style-type: none"> <li>• Default value: 1</li> </ul>                                                                                                                                                                            |
| return_timeout | integer       | query | False    | <p>The number of seconds to allow the call to execute before returning. When iterating over a collection, the default is 15 seconds. ONTAP returns earlier if either max records or the end of the collection is reached.</p> <ul style="list-style-type: none"> <li>• Default value: 1</li> <li>• Max value: 120</li> <li>• Min value: 0</li> </ul> |
| order_by       | array[string] | query | False    | Order results by specified fields and optional [asc                                                                                                                                                                                                                                                                                                  |

## Response

Status: 200, Ok

| Name    | Type                   | Description                                                           |
|---------|------------------------|-----------------------------------------------------------------------|
| _links  | <a href="#">_links</a> |                                                                       |
| enabled | boolean                | Specifies whether or not the cache is enabled.                        |
| svm     | <a href="#">svm</a>    | SVM, applies only to SVM-scoped objects.                              |
| ttl     | string                 | Specifies Time to Live for list of group members, in ISO 8601 format. |

### Example response

```
{
  "_links": {
    "self": {
      "href": "/api/resourcelink"
    }
  },
  "svm": {
    "_links": {
      "self": {
        "href": "/api/resourcelink"
      }
    },
    "name": "svm1",
    "uuid": "02c9e252-41be-11e9-81d5-00a0986138f7"
  },
  "ttl": "PT2H30M"
}
```

### Error

Status: Default, Error

| Name  | Type                           | Description |
|-------|--------------------------------|-------------|
| error | <a href="#">returned_error</a> |             |

### Example error

```
{
  "error": {
    "arguments": [
      {
        "code": "string",
        "message": "string"
      }
    ],
    "code": "4",
    "message": "entry doesn't exist",
    "target": "uuid"
  }
}
```

### Definitions

## See Definitions

href

| Name | Type   | Description |
|------|--------|-------------|
| href | string |             |

\_links

| Name | Type                 | Description |
|------|----------------------|-------------|
| self | <a href="#">href</a> |             |

svm

SVM, applies only to SVM-scoped objects.

| Name   | Type                   | Description                                                                         |
|--------|------------------------|-------------------------------------------------------------------------------------|
| _links | <a href="#">_links</a> |                                                                                     |
| name   | string                 | The name of the SVM. This field cannot be specified in a PATCH method.              |
| uuid   | string                 | The unique identifier of the SVM. This field cannot be specified in a PATCH method. |

error\_arguments

| Name    | Type   | Description      |
|---------|--------|------------------|
| code    | string | Argument code    |
| message | string | Message argument |

returned\_error

| Name      | Type                                     | Description                                 |
|-----------|------------------------------------------|---------------------------------------------|
| arguments | array[ <a href="#">error_arguments</a> ] | Message arguments                           |
| code      | string                                   | Error code                                  |
| message   | string                                   | Error message                               |
| target    | string                                   | The target parameter that caused the error. |

# Update a group membership cache setting

PATCH /name-services/cache/group-membership/settings/{svm.uuid}

Introduced In: 9.11

Updates a group-membership cache setting.

## Important notes

- svm.uuid field cannot be empty.
- Returns success in case no values are provided for update.

## Related ONTAP commands

- `vserver services name-service cache group-membership settings modify`

## Learn more

- [DOC /name-services/cache/group-membership/settings](#)

## Parameters

| Name     | Type   | In   | Required | Description |
|----------|--------|------|----------|-------------|
| svm.uuid | string | path | True     | SVM UUID.   |

## Request Body

| Name    | Type                | Description                                                           |
|---------|---------------------|-----------------------------------------------------------------------|
| enabled | boolean             | Specifies whether or not the cache is enabled.                        |
| svm     | <a href="#">svm</a> | SVM, applies only to SVM-scoped objects.                              |
| ttl     | string              | Specifies Time to Live for list of group members, in ISO 8601 format. |



## Example request

```
{
  "svm": {
    "name": "svm1",
    "uuid": "02c9e252-41be-11e9-81d5-00a0986138f7"
  },
  "ttl": "PT2H30M"
}
```

## Response

Status: 200, Ok

## Error

Status: Default

## ONTAP Error Response Codes

| Error Code | Description                                                                                                                                                          |
|------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| 23724055   | Internal error. Configuration for Vserver failed. Verify that the cluster is healthy, then try the command again. For further assistance, contact technical support. |

Also see the table of common errors in the [Response body](#) overview section of this documentation.

## Definitions

## See Definitions

href

| Name | Type   | Description |
|------|--------|-------------|
| href | string |             |

\_links

svm

SVM, applies only to SVM-scoped objects.

| Name | Type   | Description                                                                         |
|------|--------|-------------------------------------------------------------------------------------|
| name | string | The name of the SVM. This field cannot be specified in a PATCH method.              |
| uuid | string | The unique identifier of the SVM. This field cannot be specified in a PATCH method. |

group\_membership\_settings

Group membership cache setting.

| Name    | Type                | Description                                                           |
|---------|---------------------|-----------------------------------------------------------------------|
| enabled | boolean             | Specifies whether or not the cache is enabled.                        |
| svm     | <a href="#">svm</a> | SVM, applies only to SVM-scoped objects.                              |
| ttl     | string              | Specifies Time to Live for list of group members, in ISO 8601 format. |

error\_arguments

| Name    | Type   | Description      |
|---------|--------|------------------|
| code    | string | Argument code    |
| message | string | Message argument |

returned\_error

| Name      | Type                                     | Description                                 |
|-----------|------------------------------------------|---------------------------------------------|
| arguments | array[ <a href="#">error_arguments</a> ] | Message arguments                           |
| code      | string                                   | Error code                                  |
| message   | string                                   | Error message                               |
| target    | string                                   | The target parameter that caused the error. |

## Copyright information

Copyright © 2025 NetApp, Inc. All Rights Reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means—graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system—without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

LIMITED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (b)(3) of the Rights in Technical Data -Noncommercial Items at DFARS 252.227-7013 (FEB 2014) and FAR 52.227-19 (DEC 2007).

Data contained herein pertains to a commercial product and/or commercial service (as defined in FAR 2.101) and is proprietary to NetApp, Inc. All NetApp technical data and computer software provided under this Agreement is commercial in nature and developed solely at private expense. The U.S. Government has a non-exclusive, non-transferrable, nonsublicensable, worldwide, limited irrevocable license to use the Data only in connection with and in support of the U.S. Government contract under which the Data was delivered. Except as provided herein, the Data may not be used, disclosed, reproduced, modified, performed, or displayed without the prior written approval of NetApp, Inc. United States Government license rights for the Department of Defense are limited to those rights identified in DFARS clause 252.227-7015(b) (FEB 2014).

## Trademark information

NETAPP, the NETAPP logo, and the marks listed at <http://www.netapp.com/TM> are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.