



# **Manage security login messages**

## REST API reference

NetApp

February 13, 2026

This PDF was generated from [https://docs.netapp.com/us-en/ontap-restapi-9171/manage\\_security\\_login\\_messages.html](https://docs.netapp.com/us-en/ontap-restapi-9171/manage_security_login_messages.html) on February 13, 2026. Always check docs.netapp.com for the latest.

# Table of Contents

- Manage security login messages . . . . . 1
  - Manage security login messages . . . . . 1
    - Overview . . . . . 1
    - Examples . . . . . 1
  - Retrieve the login banner and messages of the day . . . . . 10
    - Parameters . . . . . 10
    - Response . . . . . 11
    - Error . . . . . 12
    - Definitions . . . . . 13
  - Retrieve a login message configuration by UUID . . . . . 16
    - Parameters . . . . . 16
    - Response . . . . . 17
    - Error . . . . . 18
    - Definitions . . . . . 19
  - Update a login message configuration . . . . . 21
    - Parameters . . . . . 21
    - Request Body . . . . . 21
    - Response . . . . . 22
    - Error . . . . . 22
    - Definitions . . . . . 22

# Manage security login messages

## Manage security login messages

### Overview

You can use this API to display and manage the login messages configuration. The GET request retrieves all of the login messages in the cluster. GET operations on `/security/login/messages/{uuid}` retrieve the login messages configuration by UUID. PATCH operations on `/security/login/messages/{uuid}` update the login messages configuration by UUID.

### Examples

#### Retrieving all of the login messages in the cluster

```
# The API:
/api/security/login/messages

# The call:
curl -X GET "https://<mgmt-ip>/api/security/login/messages?fields=*" -H
"accept: application/hal+json"

# The response:
{
  "records": [
    {
      "uuid": "2581e5aa-9fe3-11e8-b309-005056bbef18",
      "scope": "cluster",
      "banner": "*** WARNING: DO NOT PROCEED IF YOU ARE NOT AUTHORIZED!
      ****\n",
      "message": "#### Welcome to Cluster X ####\n",
      "show_cluster_message": true,
      "_links": {
        "self": {
          "href": "/api/security/login/messages/2581e5aa-9fe3-11e8-b309-
005056bbef18"
        }
      }
    },
    {
      "uuid": "7b1b3715-9ffa-11e8-a5dd-005056bbef18",
      "scope": "svm",
      "svm": {
```

```

    "uuid": "7b1b3715-9ffa-11e8-a5dd-005056bbef18",
    "name": "svm1"
  },
  "message": "#### Welcome to SVM1 ####\n",
  "show_cluster_message": true,
  "_links": {
    "self": {
      "href": "/api/security/login/messages/7b1b3715-9ffa-11e8-a5dd-005056bbef18"
    }
  }
},
{
  "uuid": "8ddee11e-a58c-11e8-85e0-005056bbef18",
  "scope": "svm",
  "svm": {
    "uuid": "8ddee11e-a58c-11e8-85e0-005056bbef18",
    "name": "svm3"
  },
  "banner": "*** WARNING: This system is for the use of authorized users only. ****\n",
  "_links": {
    "self": {
      "href": "/api/security/login/messages/8ddee11e-a58c-11e8-85e0-005056bbef18"
    }
  }
},
{
  "uuid": "f7e41c99-9ffa-11e8-a5dd-005056bbef18",
  "scope": "svm",
  "svm": {
    "uuid": "f7e41c99-9ffa-11e8-a5dd-005056bbef18",
    "name": "svm2"
  },
  "_links": {
    "self": {
      "href": "/api/security/login/messages/f7e41c99-9ffa-11e8-a5dd-005056bbef18"
    }
  }
}
],
"num_records": 4,
"_links": {
  "self": {

```

```
    "href": "/api/security/login/messages?fields=*"
  }
}
}
```

---

## Retrieving the login messages configuration at the cluster scope

---

```
# The API:
/api/security/login/messages

# The call:
curl -X GET "https://<mgmt-
ip>/api/security/login/messages?scope=cluster&fields=*" -H "accept:
application/hal+json"

# The response:
{
  "records": [
    {
      "uuid": "2581e5aa-9fe3-11e8-b309-005056bbef18",
      "scope": "cluster",
      "banner": "*** WARNING: DO NOT PROCEED IF YOU ARE NOT AUTHORIZED!
****\n",
      "message": "#### Welcome to Cluster X ####\n",
      "show_cluster_message": true,
      "_links": {
        "self": {
          "href": "/api/security/login/messages/2581e5aa-9fe3-11e8-b309-
005056bbef18"
        }
      }
    }
  ],
  "num_records": 1,
  "_links": {
    "self": {
      "href": "/api/security/login/messages?scope=cluster&fields=*"
    }
  }
}
```

## Retrieving the login banner configured at the cluster scope

---

```
# The API:
/api/security/login/messages

# The call:
curl -X GET "https://<mgmt-
ip>/api/security/login/messages?scope=cluster&fields=banner" -H "accept:
application/hal+json"

# The response:
{
  "records": [
    {
      "uuid": "2581e5aa-9fe3-11e8-b309-005056bbef18",
      "scope": "cluster",
      "banner": "*** WARNING: DO NOT PROCEED IF YOU ARE NOT AUTHORIZED!
      ****\n",
      "_links": {
        "self": {
          "href": "/api/security/login/messages/2581e5aa-9fe3-11e8-b309-
005056bbef18"
        }
      }
    }
  ],
  "num_records": 1,
  "_links": {
    "self": {
      "href": "/api/security/login/messages?scope=cluster&fields=banner"
    }
  }
}
```

## Retrieving the login messages configuration of a specific SVM

---

```
# The API:
/api/security/login/messages

# The call:
curl -X GET "https://<mgmt-
ip>/api/security/login/messages?svm.name=svm1&fields=*" -H "accept:
application/hal+json"

# The response:
{
  "records": [
    {
      "uuid": "7b1b3715-9ffa-11e8-a5dd-005056bbef18",
      "scope": "svm",
      "svm": {
        "uuid": "7b1b3715-9ffa-11e8-a5dd-005056bbef18",
        "name": "svm1"
      },
      "message": "#### Welcome to SVM1 ####\n",
      "show_cluster_message": true,
      "_links": {
        "self": {
          "href": "/api/security/login/messages/7b1b3715-9ffa-11e8-a5dd-
005056bbef18"
        }
      }
    },
    ],
  "num_records": 1,
  "_links": {
    "self": {
      "href": "/api/security/login/messages?svm.name=svm1&fields=*"
    }
  }
}
```

---

### Retrieving the login messages configuration by UUID, including all fields

---

```
# The API:
/api/security/login/messages/{uuid}

# The call:
curl -X GET "https://<mgmt-ip>/api/security/login/messages/7b1b3715-9ffa-11e8-a5dd-005056bbef18?fields=*" -H "accept: application/hal+json"

# The response:
{
  "uuid": "7b1b3715-9ffa-11e8-a5dd-005056bbef18",
  "scope": "svm",
  "svm": {
    "uuid": "7b1b3715-9ffa-11e8-a5dd-005056bbef18",
    "name": "svm1"
  },
  "message": "#### Welcome to SVM1 ####\n",
  "show_cluster_message": true,
  "_links": {
    "self": {
      "href": "/api/security/login/messages/7b1b3715-9ffa-11e8-a5dd-005056bbef18"
    }
  }
}
```

---

## Configuring the login banner in a cluster

---

```
# The API:
/api/security/login/messages

# The call:
curl -X PATCH "https://<mgmt-
ip>/api/security/login/messages?scope=cluster" -H "accept:
application/hal+json" -H "Content-Type: application/json" -d "{
  \"banner\": \"You are entering secure area.\" }"

# The response:
{
  "num_records": 1,
  "_links": {
    "self": {
      "href": "/api/security/login/messages?scope=cluster"
    }
  }
}
```

---

## Configuring the message of the day (MOTD) in a cluster

---

```
# The API:
/api/security/login/messages

# The call:
curl -X PATCH "https://<mgmt-
ip>/api/security/login/messages?scope=cluster" -H "accept:
application/hal+json" -H "Content-Type: application/json" -d "{
  \"message\": \"Welcome to Cluster X\", \"show_cluster_message\": true }"

# The response:
{
  "num_records": 1,
  "_links": {
    "self": {
      "href": "/api/security/login/messages?scope=cluster"
    }
  }
}
```

## Clearing the login banner and message of the day (MOTD) in a cluster

---

```
# The API:
/api/security/login/messages

# The call:
curl -X PATCH "https://<mgmt-
ip>/api/security/login/messages?scope=cluster" -H "accept:
application/hal+json" -H "Content-Type: application/json" -d "{
  \"banner\": \"\", \"message\": \"\" }"

# The response:
{
  "num_records": 1,
  "_links": {
    "self": {
      "href": "/api/security/login/messages?scope=cluster"
    }
  }
}
```

## Configuring the login messages for a specific SVM

---

```
# The API:
/api/security/login/messages

# The call:
curl -X PATCH "https://<mgmt-
ip>/api/security/login/messages?svm.name=svm1" -H "accept:
application/hal+json" -H "Content-Type: application/json" -d "{
  \"banner\" : \"AUTHORIZED ACCESS ONLY\", \"message\": \"WELCOME!\" }"

# The response:
{
  "num_records": 1,
  "_links": {
    "self": {
      "href": "/api/security/login/messages?svm.name=svm1"
    }
  }
}
```

---

## Configuring the login messages by UUID

---

```
# The API:
/api/security/login/messages/{uuid}

# The call:
curl -X PATCH "https://<mgmt-ip>/api/security/login/messages/7b1b3715-
9ffa-11e8-a5dd-005056bbef18" -H "accept: application/hal+json" -H
"Content-Type: application/json" -d "{ \"banner\" : \"AUTHORIZED ACCESS
ONLY\", \"message\": \"WELCOME!\" }"
```

---

## Clearing the login messages configuration by UUID

---

```
# The API:
/api/security/login/messages/{uuid}

# The call:
curl -X PATCH "https://<mgmt-ip>/api/security/login/messages/7b1b3715-9ffa-11e8-a5dd-005056bbef18" -H "accept: application/hal+json" -H "Content-Type: application/json" -d "{ \"banner\": \"\", \"message\": \"\" }"
```

## Retrieve the login banner and messages of the day

GET /security/login/messages

Introduced In: 9.6

Retrieves the login banner and messages of the day (MOTD) configured in the cluster and in specific SVMs.

### Parameters

| Name                 | Type    | In    | Required | Description                                                                                                |
|----------------------|---------|-------|----------|------------------------------------------------------------------------------------------------------------|
| uuid                 | string  | query | False    | Filter by uuid                                                                                             |
| message              | string  | query | False    | Filter by message <ul style="list-style-type: none"><li>• maxLength: 2048</li><li>• minLength: 0</li></ul> |
| banner               | string  | query | False    | Filter by banner <ul style="list-style-type: none"><li>• maxLength: 2048</li><li>• minLength: 0</li></ul>  |
| scope                | string  | query | False    | Filter by scope                                                                                            |
| svm.name             | string  | query | False    | Filter by svm.name                                                                                         |
| svm.uuid             | string  | query | False    | Filter by svm.uuid                                                                                         |
| show_cluster_message | boolean | query | False    | Filter by show_cluster_message                                                                             |

| Name           | Type          | In    | Required | Description                                                                                                                                                                                                                                                                                                                                           |
|----------------|---------------|-------|----------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| fields         | array[string] | query | False    | Specify the fields to return.                                                                                                                                                                                                                                                                                                                         |
| max_records    | integer       | query | False    | Limit the number of records returned.                                                                                                                                                                                                                                                                                                                 |
| return_timeout | integer       | query | False    | <p>The number of seconds to allow the call to execute before returning. When iterating over a collection, the default is 15 seconds. ONTAP returns earlier if either max records or the end of the collection is reached.</p> <ul style="list-style-type: none"> <li>• Default value: 15</li> <li>• Max value: 120</li> <li>• Min value: 0</li> </ul> |
| return_records | boolean       | query | False    | <p>The default is true for GET calls. When set to false, only the number of records is returned.</p> <ul style="list-style-type: none"> <li>• Default value: 1</li> </ul>                                                                                                                                                                             |
| order_by       | array[string] | query | False    | Order results by specified fields and optional [asc                                                                                                                                                                                                                                                                                                   |

## Response

Status: 200, Ok

| Name        | Type                                    | Description       |
|-------------|-----------------------------------------|-------------------|
| _links      | <a href="#">_links</a>                  |                   |
| num_records | integer                                 | Number of records |
| records     | array[ <a href="#">login_messages</a> ] |                   |

## Example response

```
{
  "_links": {
    "next": {
      "href": "/api/resourcelink"
    },
    "self": {
      "href": "/api/resourcelink"
    }
  },
  "num_records": 1,
  "records": [
    {
      "_links": {
        "self": {
          "href": "/api/resourcelink"
        }
      },
      "banner": "string",
      "message": "string",
      "scope": "string",
      "svm": {
        "_links": {
          "self": {
            "href": "/api/resourcelink"
          }
        },
        "name": "svm1",
        "uuid": "02c9e252-41be-11e9-81d5-00a0986138f7"
      },
      "uuid": "string"
    }
  ]
}
```

## Error

Status: Default, Error

| Name  | Type                           | Description |
|-------|--------------------------------|-------------|
| error | <a href="#">returned_error</a> |             |

### Example error

```
{
  "error": {
    "arguments": [
      {
        "code": "string",
        "message": "string"
      }
    ],
    "code": "4",
    "message": "entry doesn't exist",
    "target": "uuid"
  }
}
```

### Definitions

## See Definitions

href

| Name | Type   | Description |
|------|--------|-------------|
| href | string |             |

\_links

| Name | Type                 | Description |
|------|----------------------|-------------|
| next | <a href="#">href</a> |             |
| self | <a href="#">href</a> |             |

\_links

| Name | Type                 | Description |
|------|----------------------|-------------|
| self | <a href="#">href</a> |             |

svm

SVM, applies only to SVM-scoped objects.

| Name   | Type                   | Description                                                                         |
|--------|------------------------|-------------------------------------------------------------------------------------|
| _links | <a href="#">_links</a> |                                                                                     |
| name   | string                 | The name of the SVM. This field cannot be specified in a PATCH method.              |
| uuid   | string                 | The unique identifier of the SVM. This field cannot be specified in a PATCH method. |

login\_messages

The login banner and message of the day (MOTD) configuration.

| Name   | Type                   | Description |
|--------|------------------------|-------------|
| _links | <a href="#">_links</a> |             |

| Name                 | Type    | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                    |
|----------------------|---------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| banner               | string  | The login banner text. This message is displayed during SSH and console device login just before the password prompt displays. When configured, a cluster-level login banner is used for every incoming connection. Each data SVM can override the cluster-level banner to instead display when you log into the SVM. To restore the default setting for a data SVM, set the banner to an empty string. New lines are supplied as either LF or CRLF but are always returned as LF. Optional in the PATCH body. |
| message              | string  | The message of the day (MOTD). This message appears just before the clustershell prompt after a successful login. When configured, the cluster message displays first. If you log in as a data SVM administrator, the SVM message is then printed. The cluster-level MOTD can be disabled for a given data SVM using the "show_cluster_message" property. New lines are supplied as either LF or CRLF but are always returned as LF. Optional in the PATCH body.                                               |
| scope                | string  | Set to "svm" for interfaces owned by an SVM. Otherwise, set to "cluster".                                                                                                                                                                                                                                                                                                                                                                                                                                      |
| show_cluster_message | boolean | Specifies whether to show a cluster-level message before the SVM message when logging in as an SVM administrator. This setting can only be modified by cluster administrators. Optional in the PATCH body.                                                                                                                                                                                                                                                                                                     |
| svm                  | svm     | SVM, applies only to SVM-scoped objects.                                                                                                                                                                                                                                                                                                                                                                                                                                                                       |

| Name | Type   | Description                                                     |
|------|--------|-----------------------------------------------------------------|
| uuid | string | The unique identifier (ID) of the login messages configuration. |

error\_arguments

| Name    | Type   | Description      |
|---------|--------|------------------|
| code    | string | Argument code    |
| message | string | Message argument |

returned\_error

| Name      | Type                                     | Description                                 |
|-----------|------------------------------------------|---------------------------------------------|
| arguments | array[ <a href="#">error_arguments</a> ] | Message arguments                           |
| code      | string                                   | Error code                                  |
| message   | string                                   | Error message                               |
| target    | string                                   | The target parameter that caused the error. |

## Retrieve a login message configuration by UUID

GET /security/login/messages/{uuid}

**Introduced In:** 9.6

Retrieves the login messages configuration by UUID.

### Parameters

| Name   | Type          | In    | Required | Description                       |
|--------|---------------|-------|----------|-----------------------------------|
| uuid   | string        | path  | True     | Login messages configuration UUID |
| fields | array[string] | query | False    | Specify the fields to return.     |

## Response

Status: 200, Ok

| Name                 | Type                   | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                    |
|----------------------|------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| _links               | <a href="#">_links</a> |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                |
| banner               | string                 | The login banner text. This message is displayed during SSH and console device login just before the password prompt displays. When configured, a cluster-level login banner is used for every incoming connection. Each data SVM can override the cluster-level banner to instead display when you log into the SVM. To restore the default setting for a data SVM, set the banner to an empty string. New lines are supplied as either LF or CRLF but are always returned as LF. Optional in the PATCH body. |
| message              | string                 | The message of the day (MOTD). This message appears just before the clustershell prompt after a successful login. When configured, the cluster message displays first. If you log in as a data SVM administrator, the SVM message is then printed. The cluster-level MOTD can be disabled for a given data SVM using the "show_cluster_message" property. New lines are supplied as either LF or CRLF but are always returned as LF. Optional in the PATCH body.                                               |
| scope                | string                 | Set to "svm" for interfaces owned by an SVM. Otherwise, set to "cluster".                                                                                                                                                                                                                                                                                                                                                                                                                                      |
| show_cluster_message | boolean                | Specifies whether to show a cluster-level message before the SVM message when logging in as an SVM administrator. This setting can only be modified by cluster administrators. Optional in the PATCH body.                                                                                                                                                                                                                                                                                                     |

| Name | Type   | Description                                                     |
|------|--------|-----------------------------------------------------------------|
| svm  | svm    | SVM, applies only to SVM-scoped objects.                        |
| uuid | string | The unique identifier (ID) of the login messages configuration. |

### Example response

```
{
  "_links": {
    "self": {
      "href": "/api/resourcelink"
    }
  },
  "banner": "string",
  "message": "string",
  "scope": "string",
  "svm": {
    "_links": {
      "self": {
        "href": "/api/resourcelink"
      }
    },
    "name": "svm1",
    "uuid": "02c9e252-41be-11e9-81d5-00a0986138f7"
  },
  "uuid": "string"
}
```

### Error

Status: Default, Error

| Name  | Type           | Description |
|-------|----------------|-------------|
| error | returned_error |             |

### Example error

```
{
  "error": {
    "arguments": [
      {
        "code": "string",
        "message": "string"
      }
    ],
    "code": "4",
    "message": "entry doesn't exist",
    "target": "uuid"
  }
}
```

### Definitions

## See Definitions

href

| Name | Type   | Description |
|------|--------|-------------|
| href | string |             |

\_links

| Name | Type                 | Description |
|------|----------------------|-------------|
| self | <a href="#">href</a> |             |

svm

SVM, applies only to SVM-scoped objects.

| Name   | Type                   | Description                                                                         |
|--------|------------------------|-------------------------------------------------------------------------------------|
| _links | <a href="#">_links</a> |                                                                                     |
| name   | string                 | The name of the SVM. This field cannot be specified in a PATCH method.              |
| uuid   | string                 | The unique identifier of the SVM. This field cannot be specified in a PATCH method. |

error\_arguments

| Name    | Type   | Description      |
|---------|--------|------------------|
| code    | string | Argument code    |
| message | string | Message argument |

returned\_error

| Name      | Type                                     | Description                                 |
|-----------|------------------------------------------|---------------------------------------------|
| arguments | array[ <a href="#">error_arguments</a> ] | Message arguments                           |
| code      | string                                   | Error code                                  |
| message   | string                                   | Error message                               |
| target    | string                                   | The target parameter that caused the error. |

# Update a login message configuration

PATCH /security/login/messages/{uuid}

**Introduced In:** 9.6

Updates the login messages configuration. There are no required fields. An empty body makes no modifications.

## Parameters

| Name | Type   | In   | Required | Description                       |
|------|--------|------|----------|-----------------------------------|
| uuid | string | path | True     | Login messages configuration UUID |

## Request Body

| Name    | Type   | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                    |
|---------|--------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| banner  | string | The login banner text. This message is displayed during SSH and console device login just before the password prompt displays. When configured, a cluster-level login banner is used for every incoming connection. Each data SVM can override the cluster-level banner to instead display when you log into the SVM. To restore the default setting for a data SVM, set the banner to an empty string. New lines are supplied as either LF or CRLF but are always returned as LF. Optional in the PATCH body. |
| message | string | The message of the day (MOTD). This message appears just before the clustershell prompt after a successful login. When configured, the cluster message displays first. If you log in as a data SVM administrator, the SVM message is then printed. The cluster-level MOTD can be disabled for a given data SVM using the "show_cluster_message" property. New lines are supplied as either LF or CRLF but are always returned as LF. Optional in the PATCH body.                                               |

| Name                 | Type    | Description                                                                                                                                                                                                |
|----------------------|---------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| scope                | string  | Set to "svm" for interfaces owned by an SVM. Otherwise, set to "cluster".                                                                                                                                  |
| show_cluster_message | boolean | Specifies whether to show a cluster-level message before the SVM message when logging in as an SVM administrator. This setting can only be modified by cluster administrators. Optional in the PATCH body. |
| uuid                 | string  | The unique identifier (ID) of the login messages configuration.                                                                                                                                            |

#### Example request

```
{
  "banner": "string",
  "message": "string",
  "scope": "string",
  "uuid": "string"
}
```

#### Response

Status: 200, Ok

#### Error

Status: Default

#### ONTAP Error Response codes

| Error codes | Description                                                                |
|-------------|----------------------------------------------------------------------------|
| 10225636    | Only a cluster administrator can modify the show_cluster_message property. |

#### Definitions

## See Definitions

href

| Name | Type   | Description |
|------|--------|-------------|
| href | string |             |

\_links

svm

SVM, applies only to SVM-scoped objects.

| Name | Type   | Description                                                                         |
|------|--------|-------------------------------------------------------------------------------------|
| name | string | The name of the SVM. This field cannot be specified in a PATCH method.              |
| uuid | string | The unique identifier of the SVM. This field cannot be specified in a PATCH method. |

login\_messages

The login banner and message of the day (MOTD) configuration.

| Name   | Type   | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                    |
|--------|--------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| banner | string | The login banner text. This message is displayed during SSH and console device login just before the password prompt displays. When configured, a cluster-level login banner is used for every incoming connection. Each data SVM can override the cluster-level banner to instead display when you log into the SVM. To restore the default setting for a data SVM, set the banner to an empty string. New lines are supplied as either LF or CRLF but are always returned as LF. Optional in the PATCH body. |

| Name                 | Type    | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                      |
|----------------------|---------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| message              | string  | The message of the day (MOTD). This message appears just before the clustershell prompt after a successful login. When configured, the cluster message displays first. If you log in as a data SVM administrator, the SVM message is then printed. The cluster-level MOTD can be disabled for a given data SVM using the "show_cluster_message" property. New lines are supplied as either LF or CRLF but are always returned as LF. Optional in the PATCH body. |
| scope                | string  | Set to "svm" for interfaces owned by an SVM. Otherwise, set to "cluster".                                                                                                                                                                                                                                                                                                                                                                                        |
| show_cluster_message | boolean | Specifies whether to show a cluster-level message before the SVM message when logging in as an SVM administrator. This setting can only be modified by cluster administrators. Optional in the PATCH body.                                                                                                                                                                                                                                                       |
| uuid                 | string  | The unique identifier (ID) of the login messages configuration.                                                                                                                                                                                                                                                                                                                                                                                                  |

#### error\_arguments

| Name    | Type   | Description      |
|---------|--------|------------------|
| code    | string | Argument code    |
| message | string | Message argument |

#### returned\_error

| Name      | Type                                     | Description       |
|-----------|------------------------------------------|-------------------|
| arguments | array[ <a href="#">error_arguments</a> ] | Message arguments |
| code      | string                                   | Error code        |

| Name    | Type   | Description                                 |
|---------|--------|---------------------------------------------|
| message | string | Error message                               |
| target  | string | The target parameter that caused the error. |

## Copyright information

Copyright © 2026 NetApp, Inc. All Rights Reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means—graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system—without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

LIMITED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (b)(3) of the Rights in Technical Data -Noncommercial Items at DFARS 252.227-7013 (FEB 2014) and FAR 52.227-19 (DEC 2007).

Data contained herein pertains to a commercial product and/or commercial service (as defined in FAR 2.101) and is proprietary to NetApp, Inc. All NetApp technical data and computer software provided under this Agreement is commercial in nature and developed solely at private expense. The U.S. Government has a non-exclusive, non-transferrable, nonsublicensable, worldwide, limited irrevocable license to use the Data only in connection with and in support of the U.S. Government contract under which the Data was delivered. Except as provided herein, the Data may not be used, disclosed, reproduced, modified, performed, or displayed without the prior written approval of NetApp, Inc. United States Government license rights for the Department of Defense are limited to those rights identified in DFARS clause 252.227-7015(b) (FEB 2014).

## Trademark information

NETAPP, the NETAPP logo, and the marks listed at <http://www.netapp.com/TM> are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.