



# **Manage SnapMirror relationship transfers**

## **REST API reference**

NetApp  
February 13, 2026

This PDF was generated from [https://docs.netapp.com/us-en/ontap-restapi-97/manage\\_snapmirror\\_relationship\\_transfers.html](https://docs.netapp.com/us-en/ontap-restapi-97/manage_snapmirror_relationship_transfers.html) on February 13, 2026. Always check docs.netapp.com for the latest.

# Table of Contents

Manage SnapMirror relationship tranfers . . . . .	1
Manage SnapMirror relationship tranfers . . . . .	1
Overview . . . . .	1
Retrieves the list of ongoing snapmirror transfers for the specified relationship . . . . .	1
Related ONTAP commands . . . . .	1
Example . . . . .	1
Learn more . . . . .	1
Parameters . . . . .	2
Response . . . . .	3
Error . . . . .	5
Definitions . . . . .	5
Starts a snapmirror transfer operation this api initiates a restore operation if the snapmirror relationship is of type "restore" otherwise, it initiates a snapmirror "initialize" operation or "update" operation based on the current snapmirror state . . . . .	9
Default property values . . . . .	9
Related ONTAP commands . . . . .	9
Examples . . . . .	9
Learn more . . . . .	10
Parameters . . . . .	10
Request Body . . . . .	11
Response . . . . .	13
Error . . . . .	13
Definitions . . . . .	14
Retrieves the attributes of a specific ongoing snapmirror transfer . . . . .	18
Related ONTAP commands . . . . .	18
Example . . . . .	18
Learn more . . . . .	18
Parameters . . . . .	18
Response . . . . .	19
Error . . . . .	20
Definitions . . . . .	21
Aborts an ongoing snapmirror transfer . . . . .	24
Related ONTAP commands . . . . .	24
Example . . . . .	24
Learn more . . . . .	24
Parameters . . . . .	25
Request Body . . . . .	25
Response . . . . .	26
Error . . . . .	27
Definitions . . . . .	27

# Manage SnapMirror relationship transfers

## Manage SnapMirror relationship transfers

### Overview

This API is used to manage transfers on an existing SnapMirror relationship.

You can initiate SnapMirror operations such as "initialize", "update", "restore-transfer", and "abort" using this API and it only manages the active transfers on the specified relationship. For the restore relationships, the POST on transfers API triggers "restore-transfer". Successful completion of "restore" also deletes the restore relationship. If the "restore" fails, DELETE on relationships must be called to delete the restore relationship.

## Retrieves the list of ongoing snapmirror transfers for the specified relationship

### related ontap commands

- `snapmirror show # example`

```
get "/api/snapmirror/relationships/293baa53-e63d-11e8-bff1-005056a793dd/transfers"
```

### learn more

- `[doc /snapmirror/relationships/{relationshipuuid}/transfers](#docs-snapmirror-snapmirror_relationships_{relationshipuuid}_transfers)`

GET /snapmirror/relationships/{relationship.uuid}/transfers

Retrieves the list of ongoing SnapMirror transfers for the specified relationship.

### Related ONTAP commands

- `snapmirror show`

### Example

```
GET "/api/snapmirror/relationships/293baa53-e63d-11e8-bff1-005056a793dd/transfers"
```

### Learn more

- [DOC /snapmirror/relationships/{relationship.uuid}/transfers](#)

## Parameters

Name	Type	In	Required	Description
relationship.uuid	string	path	True	Relationship UUID
bytes_transferred	integer	query	False	Filter by bytes_transferred
state	string	query	False	Filter by state
relationship.uuid	string	query	False	Filter by relationship.uuid
relationship.restore	boolean	query	False	Filter by relationship.restore
relationship.destination.svm.uuid	string	query	False	Filter by relationship.destination.svm.uuid
relationship.destination.svm.name	string	query	False	Filter by relationship.destination.svm.name
relationship.destination.path	string	query	False	Filter by relationship.destination.path
relationship.destination.cluster.uuid	string	query	False	Filter by relationship.destination.cluster.uuid
relationship.destination.cluster.name	string	query	False	Filter by relationship.destination.cluster.name
uuid	string	query	False	Filter by uuid
snapshot	string	query	False	Filter by snapshot
checkpoint_size	integer	query	False	Filter by checkpoint_size
fields	array[string]	query	False	Specify the fields to return.

Name	Type	In	Required	Description
max_records	integer	query	False	Limit the number of records returned.
return_records	boolean	query	False	The default is true for GET calls. When set to false, only the number of records is returned.
return_timeout	integer	query	False	The number of seconds to allow the call to execute before returning. When iterating over a collection, the default is 15 seconds. ONTAP returns earlier if either max records or the end of the collection is reached.
order_by	array[string]	query	False	Order results by specified fields and optional [asc

## Response

Status: 200, Ok

Name	Type	Description
_links	<a href="#">_links</a>	
num_records	integer	Number of records
records	array[ <a href="#">snapmirror_transfer</a> ]	

## Example response

```
{
  "_links": {
    "next": {
      "href": "/api/resourcelink"
    },
    "self": {
      "href": "/api/resourcelink"
    }
  },
  "records": [
    {
      "_links": {
        "self": {
          "href": "/api/resourcelink"
        }
      },
      "bytes_transferred": 0,
      "checkpoint_size": 0,
      "relationship": {
        "destination": {
          "cluster": {
            "_links": {
              "self": {
                "href": "/api/resourcelink"
              }
            },
            "name": "cluster1",
            "uuid": "1cd8a442-86d1-11e0-ae1c-123478563412"
          },
          "path": "svm1:volumel",
          "svm": {
            "_links": {
              "self": {
                "href": "/api/resourcelink"
              }
            },
            "name": "svm1",
            "uuid": "02c9e252-41be-11e9-81d5-00a0986138f7"
          }
        },
        "uuid": "d2d7ceea-ab52-11e8-855e-00505682a4c7"
      },
      "snapshot": "string",
      "state": "string",
    }
  ]
}
```

```
    "storage_efficiency_enabled": null,  
    "uuid": "4ea7a442-86d1-11e0-ae1c-123478563412"  
  }  
]  
}
```

## Error

Status: Default, Error

Name	Type	Description
error	error	

### Example error

```
{  
  "error": {  
    "arguments": [  
      {  
        "code": "string",  
        "message": "string"  
      }  
    ],  
    "code": "4",  
    "message": "entry doesn't exist",  
    "target": "uuid"  
  }  
}
```

## Definitions

## See Definitions

href

Name	Type	Description
href	string	

\_links

Name	Type	Description
next	<a href="#">href</a>	
self	<a href="#">href</a>	

\_links

Name	Type	Description
self	<a href="#">href</a>	

files

Specifies a file or LUN consisting of a source\_path and an optional destination\_path. If not specified, the destination\_path is the same as the source\_path.

Name	Type	Description
destination_path	string	
source_path	string	

cluster

Name	Type	Description
_links	<a href="#">_links</a>	
name	string	
uuid	string	

svm

Name	Type	Description
_links	<a href="#">_links</a>	
name	string	The name of the SVM.
uuid	string	The unique identifier of the SVM.

snapmirror\_endpoint



Endpoint of a SnapMirror relationship. For a GET request, the property "cluster" is populated when the endpoint is on a remote cluster. A POST request to create the destination SVM endpoint or to establish an SVM DR relationship must have the property "cluster" populated with the remote cluster details. A POST request to create the destination FlexVol volume or FlexGroup volume endpoints can optionally specify the "cluster" property. A POST request to establish a SnapMirror relationship when the source SVM and the destination SVM are not peered, must specify the "cluster" property.

Name	Type	Description
cluster	<a href="#">cluster</a>	
path	string	ONTAP FlexVol/FlexGroup - svm1:volume1 ONTAP SVM - svm1: <ul style="list-style-type: none"> <li>• example: svm1:volume1</li> <li>• readCreate: 1</li> </ul>
svm	<a href="#">svm</a>	

relationship

Name	Type	Description
destination	<a href="#">snapmirror_endpoint</a>	Endpoint of a SnapMirror relationship. For a GET request, the property "cluster" is populated when the endpoint is on a remote cluster. A POST request to create the destination SVM endpoint or to establish an SVM DR relationship must have the property "cluster" populated with the remote cluster details. A POST request to create the destination FlexVol volume or FlexGroup volume endpoints can optionally specify the "cluster" property. A POST request to establish a SnapMirror relationship when the source SVM and the destination SVM are not peered, must specify the "cluster" property.
restore	boolean	Is the relationship for restore?
uuid	string	

snapmirror\_transfer

SnapMirror transfer information

Name	Type	Description
_links	<a href="#">_links</a>	
bytes_transferred	integer	Bytes transferred
checkpoint_size	integer	Amount of data transferred in bytes as recorded in the restart checkpoint.
relationship	<a href="#">relationship</a>	
snapshot	string	Name of Snapshot copy being transferred.
state	string	Status of the transfer. Set PATCH state to "aborted" to abort the transfer. Set PATCH state to "hard_aborted" to abort the transfer and discard the restart checkpoint.
uuid	string	

#### error\_arguments

Name	Type	Description
code	string	Argument code
message	string	Message argument

#### error

Name	Type	Description
arguments	array[ <a href="#">error_arguments</a> ]	Message arguments
code	string	Error code
message	string	Error message
target	string	The target parameter that caused the error.

**Starts a snapmirror transfer operation this api initiates a restore operation if the snapmirror relationship is of type "restore" otherwise, it initiates a snapmirror "initialize" operation or "update" operation based on the current snapmirror state**

#### default property values

- `storage_efficiency_enabled - true` # related ontap commands
- `snapmirror update`
- `snapmirror initialize`
- `snapmirror restore` # examples the following examples show how to perform snapmirror "initialize", "update", and "restore" operations <br/> performing a snapmirror initialize or update <br/> ` post `"/api/snapmirror/relationships/e4e7e130-0279-11e9-b566-0050568e9909/transfers"` `{}` <br/> performing a snapmirror restore transfer <br/> ` post `"/api/snapmirror/relationships/c8c62a90-0fef-11e9-b09e-0050568e7067/transfers"` `{"source-snapshot": "src", "files": {"source_path": ["/altxt0"], "destination_path": ["/a1-renamedtxt0"]}}` <br/> # learn more
- `[doc /snapmirror/relationships/{relationshipuuid}/transfers](#docs-snapmirror-snapmirror_relationships_{relationshipuuid}_transfers)`

POST /snapmirror/relationships/{relationship.uuid}/transfers

Starts a SnapMirror transfer operation. This API initiates a restore operation if the SnapMirror relationship is of type "restore". Otherwise, it initiates a SnapMirror "initialize" operation or "update" operation based on the current SnapMirror state.

#### Default property values

- `storage_efficiency_enabled - true`

#### Related ONTAP commands

- `snapmirror update`
- `snapmirror initialize`
- `snapmirror restore`

#### Examples

The following examples show how to perform SnapMirror "initialize", "update", and "restore" operations.

Performing a SnapMirror initialize or update

```
POST "/api/snapmirror/relationships/e4e7e130-0279-11e9-b566-0050568e9909/transfers" '{}'
```

## Performing a SnapMirror restore transfer

```
POST "/api/snapmirror/relationships/c8c62a90-0fef-11e9-b09e-0050568e7067/transfers" '{"source-snapshot": "src", "files": {"source_path": ["/a1.txt.0"], "destination_path": ["/a1-renamed.txt.0"]}]}'
```

## Learn more

- [DOC /snapmirror/relationships/{relationship.uuid}/transfers](#)

## Parameters

Name	Type	In	Required	Description
return_records	boolean	query	False	The default is false. If set to true, the records are returned.
return_timeout	integer	query	False	The number of seconds to allow the call to execute before returning. When doing a POST, PATCH, or DELETE operation on a single record, the default is 0 seconds. This means that if an asynchronous operation is started, the server immediately returns HTTP code 202 (Accepted) along with a link to the job. If a non-zero value is specified for POST, PATCH, or DELETE operations, ONTAP waits that length of time to see if the job completes so it can return something other than 202.
relationship.uuid	string	path	True	Relationship UUID

## Request Body

Name	Type	Description
_links	<a href="#">_links</a>	
bytes_transferred	integer	Bytes transferred
checkpoint_size	integer	Amount of data transferred in bytes as recorded in the restart checkpoint.
files	array[ <a href="#">files</a> ]	This is supported for transfer of restore relationship only. This specifies the list of files or LUNs to be restored. Can contain up to eight files or LUNs.
relationship	<a href="#">relationship</a>	
snapshot	string	Name of Snapshot copy being transferred.
source_snapshot	string	Specifies the Snapshot copy on the source to be transferred to the destination.
storage_efficiency_enabled	boolean	This is supported for transfer of restore relationship only. Set this property to "false" to turn off storage efficiency for data transferred over the wire and written to the destination.
uuid	string	

## Example request

```
{
  "_links": {
    "self": {
      "href": "/api/resourcelink"
    }
  },
  "bytes_transferred": 0,
  "checkpoint_size": 0,
  "files": [
    {
      "destination_path": "/dirb/file2",
      "source_path": "/dira/file1"
    }
  ],
  "relationship": {
    "destination": {
      "cluster": {
        "_links": {
          "self": {
            "href": "/api/resourcelink"
          }
        }
      },
      "name": "cluster1",
      "uuid": "1cd8a442-86d1-11e0-ae1c-123478563412"
    },
    "ipspace": "Default",
    "path": "svm1:volumel",
    "svm": {
      "_links": {
        "self": {
          "href": "/api/resourcelink"
        }
      },
      "name": "svm1",
      "uuid": "02c9e252-41be-11e9-81d5-00a0986138f7"
    }
  },
  "uuid": "d2d7ceea-ab52-11e8-855e-00505682a4c7"
},
"snapshot": "string",
"source_snapshot": "string",
"uuid": "4ea7a442-86d1-11e0-ae1c-123478563412"
}
```

## Response

Status: 201, Created

## Error

Status: Default

### ONTAP Error Response codes

Error code	Description
13303845	Restore operation failed
13303812	Initialize operation failed
13303844	Update operation failed
13303846	Empty source path file list
13303847	Invalid arguments
6620237	SnapMirror relationship database write failed
6620238	SnapMirror relationship database read failed

Name	Type	Description
error	<a href="#">error</a>	

### Example error

```
{
  "error": {
    "arguments": [
      {
        "code": "string",
        "message": "string"
      }
    ],
    "code": "4",
    "message": "entry doesn't exist",
    "target": "uuid"
  }
}
```

**Definitions**



## See Definitions

href

Name	Type	Description
href	string	

\_links

Name	Type	Description
self	<a href="#">href</a>	

files

Specifies a file or LUN consisting of a source\_path and an optional destination\_path. If not specified, the destination\_path is the same as the source\_path.

Name	Type	Description
destination_path	string	
source_path	string	

cluster

Name	Type	Description
_links	<a href="#">_links</a>	
name	string	
uuid	string	

svm

Name	Type	Description
_links	<a href="#">_links</a>	
name	string	The name of the SVM.
uuid	string	The unique identifier of the SVM.

snapmirror\_endpoint

Endpoint of a SnapMirror relationship. For a GET request, the property "cluster" is populated when the endpoint is on a remote cluster. A POST request to create the destination SVM endpoint or to establish an SVM DR relationship must have the property "cluster" populated with the remote cluster details. A POST request to create the destination FlexVol volume or FlexGroup volume endpoints can optionally specify the "cluster" property. A POST request to establish a SnapMirror relationship when the source SVM and the destination SVM are not peered, must specify the "cluster" property.

Name	Type	Description
cluster	<a href="#">cluster</a>	
ipspace	string	Optional property to specify the IPspace of the SVM.
path	string	ONTAP FlexVol/FlexGroup - svm1:volume1 ONTAP SVM - svm1: <ul style="list-style-type: none"> <li>• example: svm1:volume1</li> <li>• readCreate: 1</li> </ul>
svm	<a href="#">svm</a>	

#### relationship

Name	Type	Description
destination	<a href="#">snapmirror_endpoint</a>	Endpoint of a SnapMirror relationship. For a GET request, the property "cluster" is populated when the endpoint is on a remote cluster. A POST request to create the destination SVM endpoint or to establish an SVM DR relationship must have the property "cluster" populated with the remote cluster details. A POST request to create the destination FlexVol volume or FlexGroup volume endpoints can optionally specify the "cluster" property. A POST request to establish a SnapMirror relationship when the source SVM and the destination SVM are not peered, must specify the "cluster" property.
restore	boolean	Is the relationship for restore?
uuid	string	

#### snapmirror\_transfer

##### SnapMirror transfer information

Name	Type	Description
_links	<a href="#">_links</a>	

Name	Type	Description
bytes_transferred	integer	Bytes transferred
checkpoint_size	integer	Amount of data transferred in bytes as recorded in the restart checkpoint.
files	array[files]	This is supported for transfer of restore relationship only. This specifies the list of files or LUNs to be restored. Can contain up to eight files or LUNs.
relationship	relationship	
snapshot	string	Name of Snapshot copy being transferred.
source_snapshot	string	Specifies the Snapshot copy on the source to be transferred to the destination.
storage_efficiency_enabled	boolean	This is supported for transfer of restore relationship only. Set this property to "false" to turn off storage efficiency for data transferred over the wire and written to the destination.
uuid	string	

#### error\_arguments

Name	Type	Description
code	string	Argument code
message	string	Message argument

#### error

Name	Type	Description
arguments	array[error_arguments]	Message arguments
code	string	Error code
message	string	Error message

Name	Type	Description
target	string	The target parameter that caused the error.

## Retrieves the attributes of a specific ongoing snapmirror transfer

### related ontap commands

- `snapmirror show # example` <br/>

```
get "/api/snapmirror/relationships/293baa53-e63d-11e8-bff1-005056a793dd/transfers/293baa53-e63d-11e8-bff1-005056a793dd"
```

<br/> [# learn more](#) \* [doc /snapmirror/relationships/{relationshipuuid}/transfers](#docs-snapmirror-snapmirror\_relationships\_{relationshipuuid}\_transfers)

GET /snapmirror/relationships/{relationship.uuid}/transfers/{uuid}

Retrieves the attributes of a specific ongoing SnapMirror transfer.

### Related ONTAP commands

- `snapmirror show`

### Example

```
GET "/api/snapmirror/relationships/293baa53-e63d-11e8-bff1-005056a793dd/transfers/293baa53-e63d-11e8-bff1-005056a793dd"
```

### Learn more

- [DOC /snapmirror/relationships/{relationship.uuid}/transfers](#)

### Parameters

Name	Type	In	Required	Description
relationship.uuid	string	path	True	Relationship UUID
uuid	string	path	True	Transfer UUID

Name	Type	In	Required	Description
fields	array[string]	query	False	Specify the fields to return.

## Response

Status: 200, Ok

Name	Type	Description
_links	<a href="#">_links</a>	
bytes_transferred	integer	Bytes transferred
checkpoint_size	integer	Amount of data transferred in bytes as recorded in the restart checkpoint.
relationship	<a href="#">relationship</a>	
snapshot	string	Name of Snapshot copy being transferred.
state	string	Status of the transfer. Set PATCH state to "aborted" to abort the transfer. Set PATCH state to "hard_aborted" to abort the transfer and discard the restart checkpoint.
uuid	string	

## Example response

```
{
  "_links": {
    "self": {
      "href": "/api/resourcelink"
    }
  },
  "bytes_transferred": 0,
  "checkpoint_size": 0,
  "relationship": {
    "destination": {
      "cluster": {
        "_links": {
          "self": {
            "href": "/api/resourcelink"
          }
        },
        "name": "cluster1",
        "uuid": "1cd8a442-86d1-11e0-ae1c-123478563412"
      },
      "path": "svm1:volumel",
      "svm": {
        "_links": {
          "self": {
            "href": "/api/resourcelink"
          }
        },
        "name": "svm1",
        "uuid": "02c9e252-41be-11e9-81d5-00a0986138f7"
      }
    },
    "uuid": "d2d7ceea-ab52-11e8-855e-00505682a4c7"
  },
  "snapshot": "string",
  "state": "string",
  "storage_efficiency_enabled": null,
  "uuid": "4ea7a442-86d1-11e0-ae1c-123478563412"
}
```

## Error

Status: Default, Error

Name	Type	Description
error	error	

### Example error

```
{
  "error": {
    "arguments": [
      {
        "code": "string",
        "message": "string"
      }
    ],
    "code": "4",
    "message": "entry doesn't exist",
    "target": "uuid"
  }
}
```

### Definitions

## See Definitions

href

Name	Type	Description
href	string	

\_links

Name	Type	Description
self	<a href="#">href</a>	

files

Specifies a file or LUN consisting of a source\_path and an optional destination\_path. If not specified, the destination\_path is the same as the source\_path.

Name	Type	Description
destination_path	string	
source_path	string	

cluster

Name	Type	Description
_links	<a href="#">_links</a>	
name	string	
uuid	string	

svm

Name	Type	Description
_links	<a href="#">_links</a>	
name	string	The name of the SVM.
uuid	string	The unique identifier of the SVM.

snapmirror\_endpoint

Endpoint of a SnapMirror relationship. For a GET request, the property "cluster" is populated when the endpoint is on a remote cluster. A POST request to create the destination SVM endpoint or to establish an SVM DR relationship must have the property "cluster" populated with the remote cluster details. A POST request to create the destination FlexVol volume or FlexGroup volume endpoints can optionally specify the "cluster" property. A POST request to establish a SnapMirror relationship when the source SVM and the destination SVM are not peered, must specify the "cluster" property.



Name	Type	Description
cluster	<a href="#">cluster</a>	
path	string	ONTAP FlexVol/FlexGroup - svm1:volume1 ONTAP SVM - svm1: <ul style="list-style-type: none"> <li>• example: svm1:volume1</li> <li>• readCreate: 1</li> </ul>
svm	<a href="#">svm</a>	

#### relationship

Name	Type	Description
destination	<a href="#">snapmirror_endpoint</a>	Endpoint of a SnapMirror relationship. For a GET request, the property "cluster" is populated when the endpoint is on a remote cluster. A POST request to create the destination SVM endpoint or to establish an SVM DR relationship must have the property "cluster" populated with the remote cluster details. A POST request to create the destination FlexVol volume or FlexGroup volume endpoints can optionally specify the "cluster" property. A POST request to establish a SnapMirror relationship when the source SVM and the destination SVM are not peered, must specify the "cluster" property.
restore	boolean	Is the relationship for restore?
uuid	string	

#### error\_arguments

Name	Type	Description
code	string	Argument code
message	string	Message argument

#### error

Name	Type	Description
arguments	array[ <a href="#">error_arguments</a> ]	Message arguments
code	string	Error code
message	string	Error message
target	string	The target parameter that caused the error.

## Aborts an ongoing snapmirror transfer

### related ontap commands

- `snapmirror abort` [# example](#) <br/>

```
patch "/api/snapmirror/relationships/293baa53-e63d-11e8-bff1-005056a793dd/transfers/293baa53-e63d-11e8-bff1-005056a793dd"
{"state":"aborted"}
```

<br/> [# learn more](#) \* [doc /snapmirror/relationships/{relationshipuuid}/transfers](#docs-snapmirror-snapmirror\_relationships\_{relationshipuuid}\_transfers)

PATCH /snapmirror/relationships/{relationship.uuid}/transfers/{uuid}

Aborts an ongoing SnapMirror transfer.

### Related ONTAP commands

- `snapmirror abort`

### Example

```
PATCH "/api/snapmirror/relationships/293baa53-e63d-11e8-bff1-005056a793dd/transfers/293baa53-e63d-11e8-bff1-005056a793dd"
'{"state":"aborted"}'
```

### Learn more

- [DOC /snapmirror/relationships/{relationship.uuid}/transfers](#)

## Parameters

Name	Type	In	Required	Description
relationship.uuid	string	path	True	Relationship UUID
uuid	string	path	True	Transfer UUID

## Request Body

Name	Type	Description
_links	<a href="#">_links</a>	
bytes_transferred	integer	Bytes transferred
checkpoint_size	integer	Amount of data transferred in bytes as recorded in the restart checkpoint.
relationship	<a href="#">relationship</a>	
snapshot	string	Name of Snapshot copy being transferred.
state	string	Status of the transfer. Set PATCH state to "aborted" to abort the transfer. Set PATCH state to "hard_aborted" to abort the transfer and discard the restart checkpoint.
uuid	string	

## Example request

```
{
  "_links": {
    "self": {
      "href": "/api/resourcelink"
    }
  },
  "bytes_transferred": 0,
  "checkpoint_size": 0,
  "relationship": {
    "destination": {
      "cluster": {
        "_links": {
          "self": {
            "href": "/api/resourcelink"
          }
        },
        "name": "cluster1",
        "uuid": "1cd8a442-86d1-11e0-ae1c-123478563412"
      },
      "svm": {
        "_links": {
          "self": {
            "href": "/api/resourcelink"
          }
        },
        "name": "svm1",
        "uuid": "02c9e252-41be-11e9-81d5-00a0986138f7"
      }
    },
    "uuid": "d2d7ceea-ab52-11e8-855e-00505682a4c7"
  },
  "snapshot": "string",
  "state": "string",
  "storage_efficiency_enabled": null,
  "uuid": "4ea7a442-86d1-11e0-ae1c-123478563412"
}
```

## Response

Status: 200, Ok

## Error

Status: Default

### ONTAP Error Response codes

Error code	Description
13303848	Abort of sync SnapMirror is not allowed
13303849	SnapMirror transfer state is invalid

Name	Type	Description
error	<a href="#">error</a>	

### Example error

```
{
  "error": {
    "arguments": [
      {
        "code": "string",
        "message": "string"
      }
    ],
    "code": "4",
    "message": "entry doesn't exist",
    "target": "uuid"
  }
}
```

## Definitions

## See Definitions

href

Name	Type	Description
href	string	

\_links

Name	Type	Description
self	<a href="#">href</a>	

files

Specifies a file or LUN consisting of a source\_path and an optional destination\_path. If not specified, the destination\_path is the same as the source\_path.

Name	Type	Description
destination_path	string	
source_path	string	

cluster

Name	Type	Description
_links	<a href="#">_links</a>	
name	string	
uuid	string	

svm

Name	Type	Description
_links	<a href="#">_links</a>	
name	string	The name of the SVM.
uuid	string	The unique identifier of the SVM.

snapmirror\_endpoint

Endpoint of a SnapMirror relationship. For a GET request, the property "cluster" is populated when the endpoint is on a remote cluster. A POST request to create the destination SVM endpoint or to establish an SVM DR relationship must have the property "cluster" populated with the remote cluster details. A POST request to create the destination FlexVol volume or FlexGroup volume endpoints can optionally specify the "cluster" property. A POST request to establish a SnapMirror relationship when the source SVM and the destination SVM are not peered, must specify the "cluster" property.

Name	Type	Description
cluster	<a href="#">cluster</a>	
svm	<a href="#">svm</a>	

relationship

Name	Type	Description
destination	<a href="#">snapmirror_endpoint</a>	Endpoint of a SnapMirror relationship. For a GET request, the property "cluster" is populated when the endpoint is on a remote cluster. A POST request to create the destination SVM endpoint or to establish an SVM DR relationship must have the property "cluster" populated with the remote cluster details. A POST request to create the destination FlexVol volume or FlexGroup volume endpoints can optionally specify the "cluster" property. A POST request to establish a SnapMirror relationship when the source SVM and the destination SVM are not peered, must specify the "cluster" property.
restore	boolean	Is the relationship for restore?
uuid	string	

snapmirror\_transfer

SnapMirror transfer information

Name	Type	Description
_links	<a href="#">_links</a>	
bytes_transferred	integer	Bytes transferred
checkpoint_size	integer	Amount of data transferred in bytes as recorded in the restart checkpoint.
relationship	<a href="#">relationship</a>	
snapshot	string	Name of Snapshot copy being transferred.

Name	Type	Description
state	string	Status of the transfer. Set PATCH state to "aborted" to abort the transfer. Set PATCH state to "hard_aborted" to abort the transfer and discard the restart checkpoint.
uuid	string	

#### error\_arguments

Name	Type	Description
code	string	Argument code
message	string	Message argument

#### error

Name	Type	Description
arguments	array[ <a href="#">error_arguments</a> ]	Message arguments
code	string	Error code
message	string	Error message
target	string	The target parameter that caused the error.



## Copyright information

Copyright © 2026 NetApp, Inc. All Rights Reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means—graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system—without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

LIMITED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (b)(3) of the Rights in Technical Data -Noncommercial Items at DFARS 252.227-7013 (FEB 2014) and FAR 52.227-19 (DEC 2007).

Data contained herein pertains to a commercial product and/or commercial service (as defined in FAR 2.101) and is proprietary to NetApp, Inc. All NetApp technical data and computer software provided under this Agreement is commercial in nature and developed solely at private expense. The U.S. Government has a non-exclusive, non-transferrable, nonsublicensable, worldwide, limited irrevocable license to use the Data only in connection with and in support of the U.S. Government contract under which the Data was delivered. Except as provided herein, the Data may not be used, disclosed, reproduced, modified, performed, or displayed without the prior written approval of NetApp, Inc. United States Government license rights for the Department of Defense are limited to those rights identified in DFARS clause 252.227-7015(b) (FEB 2014).

## Trademark information

NETAPP, the NETAPP logo, and the marks listed at <http://www.netapp.com/TM> are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.