



Manage Vscan configuration

REST API reference

NetApp
February 06, 2026

This PDF was generated from https://docs.netapp.com/us-en/ontap-restapi/protocols_vscan_server-status_endpoint_overview.html on February 06, 2026. Always check docs.netapp.com for the latest.

Table of Contents

Manage Vscan configuration	1
Manage Vscan configuration	1
Overview	1
Examples	1
Retrieve the Vscan server status	4
Related ONTAP commands	4
Learn more	5
Parameters	5
Response	6
Error	9
Definitions	9
Delete a Vscan configuration	14
Related ONTAP commands	14
Learn more	14
Parameters	14
Response	15
Error	15
Definitions	15
Retrieve the Vscan configuration for an SVM	16
Related ONTAP commands	16
Learn more	17
Parameters	17
Response	17
Error	20
Definitions	20
Update the Vscan configuration for an SVM	25
Related ONTAP commands	25
Learn more	26
Parameters	26
Request Body	26
Response	26
Error	26
Definitions	27
Retrieve Vscan events	32
Related ONTAP commands	32
Parameters	33
Response	34
Error	37
Definitions	37

Manage Vscan configuration

Manage Vscan configuration

Overview

This API is used to display connection status information for the external virus-scanning servers or "Vscan servers".

Examples

Retrieving all fields for the Vscan server status

```

    "ifmac=FA:16:3E:F0:70:88,
    tcpstat=retrans:7538,connfail:2137,connreset:52018,inerr:0",
    "cfg=Host Name:SCSPB2271817001",
    "OS Name:Microsoft Windows Server 2012 R2 Standard",
    "OS Version:6.3.9600 N/A Build 9600",
    "System Boot Time:5/6/2021, 9:01:42 PM",
    "System Manufacturer:RDO",
    "System Model:OpenStack Compute",
    "System Type:x64-based PC",
    "Processor(s):2 Processor(s) Installed.",
    "[01]:Intel64 Family 6 Model 94 Stepping 3 GenuineIntel ~2400 Mhz"
],
"interface": {
    "name": "vs1.data",
    "uuid": "6911e7c6-aefc-11eb-bd8c-0050568e8ed1",
    "ip": {
        "address": "10.140.69.165"
    }
}
},
{
    "svm": {
        "uuid": "a776e8f2-aef9-11eb-8530-0050568e8ed1",
        "name": "vs2"
    },
    "node": {
        "uuid": "ce2463d9-aef6-11eb-bd8c-0050568e8ed1",
        "name": "user-vsimg1"
    },
    "ip": "10.140.128.163",
    "type": "primary",
    "state": "connected",
    "update_time": "2021-05-07T21:35:43+05:30",
    "vendor": "mighty master anti-evil scanner",
    "version": "5.643",
    "extended_stats": [
        "ts=10:15:26 PM May 07,2021",
        "scans=sent:0,compok:0,comperr:0,compnotfnd:0,ms/comp:0",
        "avshim-version=1.0.5.0",
        "mempage/s=0, procs=46, threads=1947, %cpu=0.07, procqlen=0,
diskio/s=1, smbbytes/s=181, ",
        "ifmac=FA:16:3E:06:9F:D6,
tcpstat=retrans:123453,connfail:6864,connreset:13188,inerr:0",
        "cfg=Host Name:SCSPB2271815001",
        "OS Name:Microsoft Windows Server 2012 R2 Standard",
        "OS Version:6.3.9600 N/A Build 9600",

```

```

"System Boot Time:4/20/2021, 5:23:29 PM",
"System Manufacturer:RDO",
"System Model:OpenStack Compute",
"System Type:x64-based PC",
"Processor(s):2 Processor(s) Installed.",
"[01]:Intel64 Family 6 Model 94 Stepping 3 GenuineIntel ~2400 Mhz"
],
"interface": {
  "name": "vs2.data",
  "uuid": "c070b4c2-aef9-11eb-8530-0050568e8ed1",
  "ip": {
    "address": "10.140.70.154"
  }
}
},
"num_records": 2
}

```

Retrieving the server status information for the server with IP address 10.141.46.173

```

# The API:
/api/protocols/vscan/server-status

# The call:
curl -X GET "https://<mgmt-ip>/api/protocols/vscan/server-
status?ip=10.140.132.141&fields=*" -H "accept: application/json+hal"

# The response:
{
"records": [
{
  "svm": {
    "uuid": "66f8564d-aefc-11eb-bd8c-0050568e8ed1",
    "name": "vs1"
  },
  "node": {
    "uuid": "ce2463d9-aef6-11eb-bd8c-0050568e8ed1",
    "name": "user-vs1m"
  },
  "ip": "10.140.132.141",
  "type": "primary",
}

```

```

"state": "connected",
"update_time": "2021-05-07T23:08:21+05:30",
"vendor": "mighty master anti-evil scanner",
"version": "5.643",
"extended_stats": [
    "ts=12:07:30 AM May 08,2021",
    "scans=sent:0,compok:0,comperr:0,compnotfnd:0,ms/comp:0",
    "avshim-version=1.0.5.0",
    "mempage/s=0, procs=52, threads=2108, %cpu=0.07, procqlen=0,
diskio/s=0, smbbytes/s=230, ",
    "ifmac=FA:16:3E:F0:70:88,
tcpstat=retrans:8249,connfail:2174,connreset:52243,inerr:0",
    "cfg=Host Name:SCSPB2271817001",
    "OS Name:Microsoft Windows Server 2012 R2 Standard",
    "OS Version:6.3.9600 N/A Build 9600",
    "System Boot Time:5/6/2021, 9:01:42 PM",
    "System Manufacturer:RDO",
    "System Model:OpenStack Compute",
    "System Type:x64-based PC",
    "Processor(s):2 Processor(s) Installed.",
    "[01]:Intel64 Family 6 Model 94 Stepping 3 GenuineIntel ~2400 Mhz"
],
"interface": {
    "name": "vs1.data",
    "uuid": "6911e7c6-aefc-11eb-bd8c-0050568e8ed1",
    "ip": {
        "address": "10.140.69.165"
    }
}
],
"num_records": 1
}

```

Retrieve the Vscan server status

GET /protocols/vscan/server-status

Introduced In: 9.6

Retrieves a Vscan server status.

Related ONTAP commands

- vserver vscan connection-status show-all

Learn more

- [DOC /protocols/vscan/server-status](#)

Parameters

Name	Type	In	Required	Description
node.name	string	query	False	Filter by node.name
node.uuid	string	query	False	Filter by node.uuid
type	string	query	False	Filter by type
vendor	string	query	False	Filter by vendor
update_time	string	query	False	Filter by update_time
svm.name	string	query	False	Filter by svm.name
svm.uuid	string	query	False	Filter by svm.uuid
interface.ip.address	string	query	False	Filter by interface.ip.address <ul style="list-style-type: none">• Introduced in: 9.10
interface.name	string	query	False	Filter by interface.name <ul style="list-style-type: none">• Introduced in: 9.10
interface.uuid	string	query	False	Filter by interface.uuid <ul style="list-style-type: none">• Introduced in: 9.10
state	string	query	False	Filter by state
disconnected_reason	string	query	False	Filter by disconnected_reason
ip	string	query	False	Filter by ip

Name	Type	In	Required	Description
version	string	query	False	Filter by version
fields	array[string]	query	False	Specify the fields to return.
max_records	integer	query	False	Limit the number of records returned.
return_records	boolean	query	False	<p>The default is true for GET calls. When set to false, only the number of records is returned.</p> <ul style="list-style-type: none"> Default value: 1
return_timeout	integer	query	False	<p>The number of seconds to allow the call to execute before returning. When iterating over a collection, the default is 15 seconds. ONTAP returns earlier if either max records or the end of the collection is reached.</p> <ul style="list-style-type: none"> Default value: 15 Max value: 120 Min value: 0
order_by	array[string]	query	False	Order results by specified fields and optional [asc

Response

Status: 200, Ok

Name	Type	Description
_links	_links	

Name	Type	Description
num_records	integer	Number of records
records	array[vscan_server_status]	

Example response

```
{  
  "_links": {  
    "next": {  
      "href": "/api/resourcelink"  
    },  
    "self": {  
      "href": "/api/resourcelink"  
    }  
  },  
  "num_records": 1,  
  "records": [  
    {  
      "disconnected_reason": "string",  
      "interface": {  
        "_links": {  
          "self": {  
            "href": "/api/resourcelink"  
          }  
        },  
        "ip": {  
          "address": "10.10.10.7"  
        },  
        "name": "lif1",  
        "uuid": "1cd8a442-86d1-11e0-ae1c-123478563412"  
      },  
      "ip": "string",  
      "node": {  
        "_links": {  
          "self": {  
            "href": "/api/resourcelink"  
          }  
        },  
        "name": "node1",  
        "uuid": "1cd8a442-86d1-11e0-ae1c-123478563412"  
      },  
      "state": "string",  
      "svm": {  
        "_links": {  
          "self": {  
            "href": "/api/resourcelink"  
          }  
        },  
        "name": "svm1",  
        "uuid": "02c9e252-41be-11e9-81d5-00a0986138f7"  
      }  
    }  
  ]  
}
```

```

        },
        "type": "string",
        "update_time": "string",
        "vendor": "string",
        "version": "string"
    }
]
}

```

Error

Status: Default, Error

Name	Type	Description
error	returned_error	

Example error

```

{
  "error": {
    "arguments": [
      {
        "code": "string",
        "message": "string"
      }
    ],
    "code": "4",
    "message": "entry doesn't exist",
    "target": "uuid"
  }
}

```

Definitions

See Definitions

href

Name	Type	Description
href	string	

_links

Name	Type	Description
next	href	
self	href	

_links

Name	Type	Description
self	href	

ip

IP information

Name	Type	Description
address	string	IPv4 or IPv6 address

interface

Address of the interface used for the Vscan connection.

Name	Type	Description
_links	_links	
ip	ip	IP information
name	string	The name of the interface. If only the name is provided, the SVM scope must be provided by the object this object is embedded in.
uuid	string	The UUID that uniquely identifies the interface.

node

Name	Type	Description
_links	_links	
name	string	
uuid	string	

svm

SVM, applies only to SVM-scoped objects.

Name	Type	Description
_links	_links	
name	string	The name of the SVM. This field cannot be specified in a PATCH method.
uuid	string	The unique identifier of the SVM. This field cannot be specified in a PATCH method.

vscan_server_status

Displays the connection status information of the external virus-scanning servers.

Name	Type	Description
disconnected_reason	string	<p>Specifies the server disconnected reason. The following is a list of the possible reasons:</p> <ul style="list-style-type: none"> • unknown - Disconnected, unknown reason. • vscan_disabled - Disconnected, Vscan is disabled on the SVM. • no_data_lif - Disconnected, SVM does not have data LIF. • session_uninitialized - Disconnected, session is not initialized. • remote_closed - Disconnected, server has closed the connection. • invalid_protocol_msg - Disconnected, invalid protocol message received. • invalid_session_id - Disconnected, invalid session ID received. • inactive_connection - Disconnected, no activity on connection. • invalid_user - Connection request by an invalid user. • server_removed - Disconnected, server has been removed from the active Scanners List. enum: • unknown • vscan_disabled • no_data_lif • session_uninitialized • remote_closed • invalid_protocol_msg • invalid_session_id • inactive_connection • invalid_user • server_removed

Name	Type	Description
interface	interface	Address of the interface used for the Vscan connection.
ip	string	IP address of the Vscan server.
node	node	
state	string	<p>Specifies the server connection state indicating if it is in the connected or disconnected state. The following is a list of the possible states:</p> <ul style="list-style-type: none"> • connected - Connected • disconnected - Disconnected <p>enum:</p> <ul style="list-style-type: none"> • connected • disconnected
svm	svm	SVM, applies only to SVM-scoped objects.
type	string	<p>Server type. The possible values are:</p> <ul style="list-style-type: none"> • primary - Primary server • backup - Backup server
update_time	string	Specifies the time the server is in the connected or disconnected state.
vendor	string	Name of the connected virus-scanner vendor.
version	string	Version of the connected virus-scanner.

error_arguments

Name	Type	Description
code	string	Argument code
message	string	Message argument

returned_error

Name	Type	Description
arguments	array[error_arguments]	Message arguments
code	string	Error code
message	string	Error message
target	string	The target parameter that caused the error.

Delete a Vscan configuration

`DELETE /protocols/vscan/{svm.uuid}`

Introduced In: 9.6

Deletes a Vscan configuration.

Important notes:

- The Vscan DELETE endpoint deletes all of the Vscan configuration of an SVM. It first disables the Vscan and then deletes all of the SVM scanner-pools, On-Access policies, and On-Demand policies.
- Disable the active Vscan On-Access policy on an SVM before performing the Vscan delete operation on that SVM.

Related ONTAP commands

- `vserver vscan scanner-pool delete`
- `vserver vscan on-access-policy delete`
- `vserver vscan on-demand-policy delete`

Learn more

- [DOC /protocols/vscan](#)
- [DOC /protocols/vscan/{svm.uuid}/scanner-pools](#)

Parameters

Name	Type	In	Required	Description
svm.uuid	string	path	True	UUID of the SVM to which this object belongs.

Response

Status: 200, Ok

Error

Status: Default

ONTAP Error Response Codes

Error Code	Description
10027259	A scanner-pool, an On-Access policy, or an On-Demand policy might fail to get deleted due to either a systematic error or some hardware failure. The error code returned details the failure along with the reason for the failure. For example, "Failed to delete On-Access policy "sp1". Reason: "Failed to delete policy. Reason: policy must be disabled before being deleted.". Retry the operation."

Name	Type	Description
error	returned_error	

Example error

```
{  
  "error": {  
    "arguments": [  
      {  
        "code": "string",  
        "message": "string"  
      }  
    ],  
    "code": "4",  
    "message": "entry doesn't exist",  
    "target": "uuid"  
  }  
}
```

Definitions

See Definitions

error_arguments

Name	Type	Description
code	string	Argument code
message	string	Message argument

returned_error

Name	Type	Description
arguments	array[error_arguments]	Message arguments
code	string	Error code
message	string	Error message
target	string	The target parameter that caused the error.

Retrieve the Vscan configuration for an SVM

GET /protocols/vscan/{svm.uuid}

Introduced In: 9.6

Retrieves the Vscan configuration for a specified SVM. This includes scanner-pools, On-Access policies, On-Demand policies, and information about whether a Vscan is enabled or disabled on an SVM.

Important note:

- You can enable only one Vscan configuration at a time for an SVM.

Related ONTAP commands

- vserver vscan show
- vserver vscan scanner-pool show
- vserver vscan scanner-pool servers show
- vserver vscan scanner-pool privileged-users show
- vserver vscan on-access-policy show
- vserver vscan on-access-policy file-ext-to-exclude show
- vserver vscan on-access-policy file-ext-to-include show

- vserver vscan on-access-policy paths-to-exclude show
- vserver vscan on-demand-task show

Learn more

- [DOC /protocols/vscan](#)
- [DOC /protocols/vscan/{svm.uuid}/scanner-pools](#)

Parameters

Name	Type	In	Required	Description
svm.uuid	string	path	True	UUID of the SVM to which this object belongs.
fields	array[string]	query	False	Specify the fields to return.

Response

Status: 200, Ok

Name	Type	Description
_links	_links	
cache_clear	boolean	Discards the cached information of the files that have been successfully scanned. Once the cache is cleared, files are scanned again when they are accessed. PATCH only
enabled	boolean	Specifies whether or not Vscan is enabled on the SVM.
on_access_policies	array[vscan_on_access_policy]	
on_demand_policies	array[vscan_on_demand_policy]	
scanner_pools	array[scanner_pool]	
svm	svm	SVM, applies only to SVM-scoped objects.

Example response

```
{  
  "_links": {  
    "self": {  
      "href": "/api/resourcelink"  
    }  
  },  
  "on_access_policies": [  
    {  
      "name": "on-access-test",  
      "protocol": "string",  
      "scope": {  
        "exclude_extensions": [  
          "mp*",  
          "txt"  
        ],  
        "exclude_paths": [  
          "\\\$dir1\\\\dir2\\\\name",  
          "\\\$vol\\\\a b",  
          "\\\$vol\\\\a,b\\\\"  
        ],  
        "include_extensions": [  
          "mp*",  
          "txt"  
        ],  
        "max_file_size": 2147483648  
      }  
    }  
  ],  
  "on_demand_policies": [  
    {  
      "log_path": "/vol0/report_dir",  
      "name": "task-1",  
      "scan_paths": [  
        "/vol1/",  
        "/vol2/cifs/"  
      ],  
      "schedule": {  
        "_links": {  
          "self": {  
            "href": "/api/resourcelink"  
          }  
        },  
        "name": "weekly",  
        "uuid": "1cd8a442-86d1-11e0-a1c-123478563412"  
      }  
    }  
  ]  
}
```

```
        },
        "scope": {
            "exclude_extensions": [
                "mp3",
                "mp4"
            ],
            "exclude_paths": [
                "/vol1/cold-files/",
                "/vol1/cifs/names"
            ],
            "include_extensions": [
                "vmdk",
                "mp*"
            ],
            "max_file_size": 10737418240
        }
    }
],
"scanner_pools": [
{
    "cluster": {
        "_links": {
            "self": {
                "href": "/api/resourcelink"
            }
        },
        "name": "cluster1",
        "uuid": "1cd8a442-86d1-11e0-ae1c-123478563412"
    },
    "name": "scanner-1",
    "privileged_users": [
        "cifs\\u1",
        "cifs\\u2"
    ],
    "role": "string",
    "servers": [
        "1.1.1.1",
        "10.72.204.27",
        "vmwin204-27.fsct.nb"
    ]
}
],
"svm": {
    "_links": {
        "self": {
            "href": "/api/resourcelink"
        }
    }
}
```

```

        }
    },
    "name": "svml",
    "uuid": "02c9e252-41be-11e9-81d5-00a0986138f7"
}
}

```

Error

Status: Default, Error

Name	Type	Description
error	returned_error	

Example error

```

{
  "error": {
    "arguments": [
      {
        "code": "string",
        "message": "string"
      }
    ],
    "code": "4",
    "message": "entry doesn't exist",
    "target": "uuid"
  }
}

```

Definitions

See Definitions

href

Name	Type	Description
href	string	

_links

Name	Type	Description
self	href	

scope

Name	Type	Description
exclude_extensions	array[string]	List of file extensions for which scanning is not performed.
exclude_paths	array[string]	List of file paths for which scanning must not be performed.
include_extensions	array[string]	List of file extensions to be scanned.
max_file_size	integer	Maximum file size, in bytes, allowed for scanning.
only_execute_access	boolean	Scan only files opened with execute-access.
scan_READONLY_volumes	boolean	Specifies whether or not read-only volume can be scanned.
scan_without_extension	boolean	Specifies whether or not files without any extension can be scanned.

vscan_on_access_policy

An On-Access policy that defines the scope of an On-Access scan. Use On-Access scanning to check for viruses when clients open, read, rename, or close files over CIFS. By default, ONTAP creates an On-Access policy named "default_CIFS" and enables it for all the SVMs in a cluster.

Name	Type	Description
enabled	boolean	Status of the On-Access Vscan policy

Name	Type	Description
mandatory	boolean	Specifies if scanning is mandatory. File access is denied if there are no external virus-scanning servers available for virus scanning.
name	string	On-Access policy name
protocol	string	Specifies the file access protocol for the on-access policy. The following lists the possible protocols. CIFS - SMB protocol
scope	scope	

schedule

Schedule of the task.

Name	Type	Description
_links	_links	
name	string	Job schedule name
uuid	string	Job schedule UUID

scope

Name	Type	Description
exclude_extensions	array[string]	List of file extensions for which scanning is not performed.
exclude_paths	array[string]	List of file paths for which scanning must not be performed.
include_extensions	array[string]	List of file extensions to be scanned.
max_file_size	integer	Maximum file size, in bytes, allowed for scanning.
scan_without_extension	boolean	Specifies whether or not files without any extension can be scanned.

`vscan_on_demand_policy`

Use On-Demand scanning to check files for viruses on a schedule. An On-Demand policy defines the scope of an On-Demand scan.

Name	Type	Description
log_path	string	The path from the Vserver root where the task report is created.
name	string	On-Demand task name
scan_paths	array[string]	List of paths that need to be scanned.
schedule	schedule	Schedule of the task.
scope	scope	

`cluster_reference`

Name	Type	Description
<code>_links</code>	_links	
name	string	
uuid	string	

`scanner_pool`

Scanner pool is a set of attributes which are used to validate and manage connections between clustered ONTAP and external virus-scanning server, or "Vscan server".

Name	Type	Description
cluster	cluster_reference	
name	string	Specifies the name of the scanner pool. Scanner pool name can be up to 256 characters long and is a string that can only contain any combination of ASCII-range alphanumeric characters a-z, A-Z, 0-9), "_", "-" and ".".

Name	Type	Description
privileged_users	array[string]	<p>Specifies a list of privileged users. A valid form of privileged user-name is "domain-name\user-name". Privileged user-names are stored and treated as case-insensitive strings. Virus scanners must use one of the registered privileged users for connecting to clustered Data ONTAP for exchanging virus-scanning protocol messages and to access file for scanning, remedying and quarantining operations.</p> <ul style="list-style-type: none"> example: ["cifs\u1", "cifs\u2"] Introduced in: 9.10
role	string	<p>Specifies the role of the scanner pool. The possible values are:</p> <ul style="list-style-type: none"> primary - Always active. secondary - Active only when none of the primary external virus-scanning servers are connected. idle - Always inactive.
servers	array[string]	<p>Specifies a list of IP addresses or FQDN for each Vscan server host names which are allowed to connect to clustered ONTAP.</p> <ul style="list-style-type: none"> example: ["1.1.1.1", "10.72.204.27", "vmwin204-27.fsct.nb"] Introduced in: 9.10

svm

SVM, applies only to SVM-scoped objects.

Name	Type	Description
_links	_links	
name	string	The name of the SVM. This field cannot be specified in a PATCH method.

Name	Type	Description
uuid	string	The unique identifier of the SVM. This field cannot be specified in a PATCH method.

error_arguments

Name	Type	Description
code	string	Argument code
message	string	Message argument

returned_error

Name	Type	Description
arguments	array[error_arguments]	Message arguments
code	string	Error code
message	string	Error message
target	string	The target parameter that caused the error.

Update the Vscan configuration for an SVM

PATCH /protocols/vscan/{svm.uuid}

Introduced In: 9.6

Updates the Vscan configuration of an SVM. Allows you to either enable or disable a Vscan, and allows you to clear the Vscan cache that stores the past scanning data for an SVM.

Important note:

- The Vscan PATCH endpoint does not allow you to modify scanner-pools, On-Demand policies or On-Access policies. Those modifications can only be done through their respective endpoints.

Related ONTAP commands

- vserver vscan enable
- vserver vscan disable
- vserver vscan reset

Learn more

- [DOC /protocols/vscan](#)
- [DOC /protocols/vscan/{svm.uuid}/scanner-pools](#)

Parameters

Name	Type	In	Required	Description
svm.uuid	string	path	True	UUID of the SVM to which this object belongs.

Request Body

Name	Type	Description
cache_clear	boolean	Discards the cached information of the files that have been successfully scanned. Once the cache is cleared, files are scanned again when they are accessed. PATCH only
enabled	boolean	Specifies whether or not Vscan is enabled on the SVM.

Response

```
Status: 200, Ok
```

Error

```
Status: Default
```

ONTAP Error Response Codes

Error Code	Description
10027015	Attempting to enable a Vscan but no active scanner-pool exists for the specified SVM
10027009	Attempting to enable a Vscan for an SVM for which it's already enabled
10027010	Attempting to disable a Vscan for an SVM for which it's already disabled

Error Code	Description
10027011	Attempting to enable a Vscan for an SVM for which no CIFS server exists
10027023	Attempting to enable a Vscan for an SVM for which no active Vscan On-Access policy exists
10027012	Cannot enable Vscan on an administrative SVM.

Definitions

See Definitions

href

Name	Type	Description
href	string	

_links

scope

Name	Type	Description
exclude_extensions	array[string]	List of file extensions for which scanning is not performed.
exclude_paths	array[string]	List of file paths for which scanning must not be performed.
include_extensions	array[string]	List of file extensions to be scanned.
max_file_size	integer	Maximum file size, in bytes, allowed for scanning.
only_execute_access	boolean	Scan only files opened with execute-access.
scan_READONLY_volumes	boolean	Specifies whether or not read-only volume can be scanned.
scan_without_extension	boolean	Specifies whether or not files without any extension can be scanned.

vscan_on_access_policy

An On-Access policy that defines the scope of an On-Access scan. Use On-Access scanning to check for viruses when clients open, read, rename, or close files over CIFS. By default, ONTAP creates an On-Access policy named "default_CIFS" and enables it for all the SVMs in a cluster.

Name	Type	Description
enabled	boolean	Status of the On-Access Vscan policy

Name	Type	Description
mandatory	boolean	Specifies if scanning is mandatory. File access is denied if there are no external virus-scanning servers available for virus scanning.
protocol	string	Specifies the file access protocol for the on-access policy. The following lists the possible protocols. CIFS - SMB protocol
scope	scope	

schedule

Schedule of the task.

Name	Type	Description
name	string	Job schedule name
uuid	string	Job schedule UUID

scope

Name	Type	Description
exclude_extensions	array[string]	List of file extensions for which scanning is not performed.
exclude_paths	array[string]	List of file paths for which scanning must not be performed.
include_extensions	array[string]	List of file extensions to be scanned.
max_file_size	integer	Maximum file size, in bytes, allowed for scanning.
scan_without_extension	boolean	Specifies whether or not files without any extension can be scanned.

vscan_on_demand_policy

Use On-Demand scanning to check files for viruses on a schedule. An On-Demand policy defines the scope of an On-Demand scan.

Name	Type	Description
log_path	string	The path from the Vserver root where the task report is created.
scan_paths	array[string]	List of paths that need to be scanned.
schedule	schedule	Schedule of the task.
scope	scope	

cluster_reference

Name	Type	Description
name	string	
uuid	string	

scanner_pool

Scanner pool is a set of attributes which are used to validate and manage connections between clustered ONTAP and external virus-scanning server, or "Vscan server".

Name	Type	Description
cluster	cluster_reference	
privileged_users	array[string]	<p>Specifies a list of privileged users. A valid form of privileged user-name is "domain-name\user-name". Privileged user-names are stored and treated as case-insensitive strings. Virus scanners must use one of the registered privileged users for connecting to clustered Data ONTAP for exchanging virus-scanning protocol messages and to access file for scanning, remedying and quarantining operations.</p> <ul style="list-style-type: none"> example: ["cifs\u1", "cifs\u2"] Introduced in: 9.10

Name	Type	Description
role	string	<p>Specifies the role of the scanner pool. The possible values are:</p> <ul style="list-style-type: none"> • primary - Always active. • secondary - Active only when none of the primary external virus-scanning servers are connected. • idle - Always inactive.
servers	array[string]	<p>Specifies a list of IP addresses or FQDN for each Vscan server host names which are allowed to connect to clustered ONTAP.</p> <ul style="list-style-type: none"> • example: ["1.1.1.1", "10.72.204.27", "vmwin204-27.fsct.nb"] • Introduced in: 9.10

svm

SVM, applies only to SVM-scoped objects.

Name	Type	Description
name	string	The name of the SVM. This field cannot be specified in a PATCH method.
uuid	string	The unique identifier of the SVM. This field cannot be specified in a PATCH method.

vscan

Vscan can be used to protect data from being compromised by viruses or other malicious code. This combines best-in-class third-party antivirus software with ONTAP features that give you the flexibility you need to control which files get scanned and when. Storage systems offload scanning operations to external servers hosting antivirus software from third-party vendors. An Antivirus Connector on the external server handles communications between the storage system and the antivirus software.

Name	Type	Description
cache_clear	boolean	Discards the cached information of the files that have been successfully scanned. Once the cache is cleared, files are scanned again when they are accessed. PATCH only
enabled	boolean	Specifies whether or not Vscan is enabled on the SVM.

error_arguments

Name	Type	Description
code	string	Argument code
message	string	Message argument

returned_error

Name	Type	Description
arguments	array[error_arguments]	Message arguments
code	string	Error code
message	string	Error message
target	string	The target parameter that caused the error.

Retrieve Vscan events

GET /protocols/vscan/{svm.uuid}/events

Introduced In: 9.11

Retrieves Vscan events, which are generated by the cluster to capture important events.

Related ONTAP commands

- `vserver vscan show-events`

Parameters

Name	Type	In	Required	Description
scan_engine_status	integer	query	False	Filter by scan_engine_status <ul style="list-style-type: none"> • Introduced in: 9.18
type	string	query	False	Filter by type
node.name	string	query	False	Filter by node.name
node.uuid	string	query	False	Filter by node.uuid
vendor	string	query	False	Filter by vendor
server	string	query	False	Filter by server
consecutive_occurrence_count	integer	query	False	Filter by consecutive_occurrence_count <ul style="list-style-type: none"> • Introduced in: 9.18
event_time	string	query	False	Filter by event_time
svm.name	string	query	False	Filter by svm.name
interface.ip.address	string	query	False	Filter by interface.ip.address
interface.name	string	query	False	Filter by interface.name
interface.uuid	string	query	False	Filter by interface.uuid
version	string	query	False	Filter by version
disconnect_reason	string	query	False	Filter by disconnect_reason
file_path	string	query	False	Filter by file_path

Name	Type	In	Required	Description
svm.uuid	string	path	True	UUID of the SVM to which this object belongs.
fields	array[string]	query	False	Specify the fields to return.
max_records	integer	query	False	Limit the number of records returned.
return_records	boolean	query	False	<p>The default is true for GET calls. When set to false, only the number of records is returned.</p> <ul style="list-style-type: none"> Default value: 1
return_timeout	integer	query	False	<p>The number of seconds to allow the call to execute before returning. When iterating over a collection, the default is 15 seconds. ONTAP returns earlier if either max records or the end of the collection is reached.</p> <ul style="list-style-type: none"> Default value: 15 Max value: 120 Min value: 0
order_by	array[string]	query	False	Order results by specified fields and optional [asc

Response

Status: 200, Ok

Name	Type	Description
_links	_links	
num_records	integer	Number of records
records	array[vscan_event]	

Example response

```
{  
  "_links": {  
    "next": {  
      "href": "/api/resourcelink"  
    },  
    "self": {  
      "href": "/api/resourcelink"  
    }  
  },  
  "num_records": 1,  
  "records": [  
    {  
      "consecutive_occurrence_count": 2,  
      "disconnect_reason": "string",  
      "event_time": "2021-11-25 04:29:41 +0000",  
      "file_path": "/1",  
      "interface": {  
        "_links": {  
          "self": {  
            "href": "/api/resourcelink"  
          }  
        },  
        "ip": {  
          "address": "10.10.10.7"  
        },  
        "name": "lif1",  
        "uuid": "1cd8a442-86d1-11e0-ae1c-123478563412"  
      },  
      "node": {  
        "_links": {  
          "self": {  
            "href": "/api/resourcelink"  
          }  
        },  
        "name": "node1",  
        "uuid": "1cd8a442-86d1-11e0-ae1c-123478563412"  
      },  
      "scan_engine_status": 333300005,  
      "server": "192.168.1.1",  
      "svm": {  
        "_links": {  
          "self": {  
            "href": "/api/resourcelink"  
          }  
        }  
      }  
    }  
  ]  
}
```

```

        },
        "name": "svml1",
        "uuid": "02c9e252-41be-11e9-81d5-00a0986138f7"
    },
    "type": "string",
    "vendor": "mighty master anti-evil scanner",
    "version": "1.0"
}
]
}

```

Error

Status: Default, Error

Name	Type	Description
error	returned_error	

Example error

```

{
  "error": {
    "arguments": [
      {
        "code": "string",
        "message": "string"
      }
    ],
    "code": "4",
    "message": "entry doesn't exist",
    "target": "uuid"
  }
}

```

Definitions

See Definitions

href

Name	Type	Description
href	string	

_links

Name	Type	Description
next	href	
self	href	

_links

Name	Type	Description
self	href	

ip

IP information

Name	Type	Description
address	string	IPv4 or IPv6 address

interface

Address of the interface used for the Vscan connection.

Name	Type	Description
_links	_links	
ip	ip	IP information
name	string	The name of the interface. If only the name is provided, the SVM scope must be provided by the object this object is embedded in.
uuid	string	The UUID that uniquely identifies the interface.

node

Name	Type	Description
_links	_links	
name	string	
uuid	string	

svm

SVM, applies only to SVM-scoped objects.

Name	Type	Description
_links	_links	
name	string	The name of the SVM. This field cannot be specified in a PATCH method.
uuid	string	The unique identifier of the SVM. This field cannot be specified in a PATCH method.

vscan_event

Name	Type	Description
consecutive_occurrence_count	integer	Specifies the consecutive occurrence count of the event.

Name	Type	Description
disconnect_reason	string	<p>Specifies the reason of the Vscan server disconnection. The available values are:</p> <ul style="list-style-type: none"> • na Not applicable • vscan_disabled Vscan disabled on the SVM • no_data_lif SVM does not have data lif on the node • session_uninitialized Session not initialized • remote_closed Closure from Server • invalid_protocol_msg Invalid protocol-message received • invalid_session_id Invalid session-id received • inactive_connection No activity on connection • invalid_user Connection request by invalid user • server_removed Server removed from the active scanner-pool
event_time	string	Specifies the Timestamp of the event.
file_path	string	Specifies the file for which event happened.
interface	interface	Address of the interface used for the Vscan connection.
node	node	
scan_engine_status	integer	Specifies the status code of the scan-engine for the event. This field is only generated when there is a proper response from the scan-engine.
server	string	Specifies the IP address of the Vscan server.

Name	Type	Description
svm	svm	SVM, applies only to SVM-scoped objects.
type	string	Specifies the event type.
vendor	string	Specifies the scan-engine vendor.
version	string	Specifies the scan-engine version.

error_arguments

Name	Type	Description
code	string	Argument code
message	string	Message argument

returned_error

Name	Type	Description
arguments	array[error_arguments]	Message arguments
code	string	Error code
message	string	Error message
target	string	The target parameter that caused the error.

Copyright information

Copyright © 2026 NetApp, Inc. All Rights Reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means—graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system—without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

LIMITED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (b)(3) of the Rights in Technical Data -Noncommercial Items at DFARS 252.227-7013 (FEB 2014) and FAR 52.227-19 (DEC 2007).

Data contained herein pertains to a commercial product and/or commercial service (as defined in FAR 2.101) and is proprietary to NetApp, Inc. All NetApp technical data and computer software provided under this Agreement is commercial in nature and developed solely at private expense. The U.S. Government has a non-exclusive, non-transferrable, nonsublicensable, worldwide, limited irrevocable license to use the Data only in connection with and in support of the U.S. Government contract under which the Data was delivered. Except as provided herein, the Data may not be used, disclosed, reproduced, modified, performed, or displayed without the prior written approval of NetApp, Inc. United States Government license rights for the Department of Defense are limited to those rights identified in DFARS clause 252.227-7015(b) (FEB 2014).

Trademark information

NETAPP, the NETAPP logo, and the marks listed at <http://www.netapp.com/TM> are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.