



Quick start

SnapCenter Plug-in for VMware vSphere 6.2

NetApp
October 28, 2025

This PDF was generated from https://docs.netapp.com/us-en/sc-plugin-vmware-vsphere/scpivs44_quick_start_overview.html on October 28, 2025. Always check docs.netapp.com for the latest.

Table of Contents

- Quick start 1
 - Overview 1
 - Deploy SnapCenter Plug-in for VMware vSphere 1
 - Add storage 3
 - Create backup policies 3
 - Create resource groups 3

Quick start

Overview

The quick start documentation provides a condensed set of instructions for deploying the SnapCenter Plug-in for VMware vSphere virtual appliance and enabling the SnapCenter Plug-in for VMware vSphere. These instructions are intended for customers who do not have SnapCenter already installed and who want to protect only VMs and datastores.

Before you begin, refer to [Deployment planning and requirements](#).

Deploy SnapCenter Plug-in for VMware vSphere

To use SnapCenter features to protect VMs, datastores, and application-consistent databases on virtualized machines, you must deploy SnapCenter Plug-in for VMware vSphere.

The [Download the Open Virtual Appliance \(OVA\)](#) page provides instructions to download the OVA files.


1. For VMware vCenter 7.0.3 and later versions, follow the steps in [Download the Open Virtual Appliance \(OVA\)](#) to import the certificates to vCenter.
2. In your browser, navigate to VMware vSphere vCenter.



For IPv6 address HTML web clients, you must use either Chrome or Firefox.

3. Log in to the **VMware vCenter Single Sign-On** page.
4. On the Navigation pane, right-click any inventory object that is a valid parent object of a virtual machine, such as a datacenter, folder, cluster, or host, and select **Deploy OVF Template** to start the VMware deploy wizard.
5. On the **Select an OVF template** page, specify the location of the .ova file (as listed in the following table) and select **Next**.

On this wizard page...	Do this...
Select a name and folder	Enter a unique name for the VM or vApp and select a deployment location.
Select a resource	Select a resource where you want to run the deployed VM template.
Review details	Verify the .ova template details.
License agreements	Select the checkbox for I accept all license agreements .
Select storage	Define where and how to store the files for the deployed OVF template.
Select networks	Select a source network and map it to a destination network.

On this wizard page...	Do this...
Customize template	<p>In Register to existing vCenter, enter the vCenter credentials.</p> <p>In Create SnapCenter Plug-in for VMware vSphere credentials, enter the SnapCenter Plug-in for VMware vSphere credentials.</p> <div>  <p>Make a note of the username and password that you specify. You need to use these credentials if you want to modify the SnapCenter Plug-In for VMware vSphere configuration at a later time.</p> </div> <p>In the Setup Network Properties section, enter the network information.</p> <p>In the Setup Date and Time section, select the time zone where the vCenter is located.</p>
Ready to complete	Review the page and select Finish .



All hosts must be configured with IP addresses (FQDN hostnames are not supported). The deploy operation does not validate your input before deploying.

- Navigate to the VM where SnapCenter Plug-in for VMware vSphere was deployed, then select the **Summary** tab, and then select the **Power On** box to start the SnapCenter Plug-in for VMware vSphere.
- While the SnapCenter Plug-in for VMware vSphere is powering on, right-click the deployed SnapCenter Plug-in for VMware vSphere, select **Guest OS**, and then select **Install VMware tools**.

The deployment might take a few minutes to complete. Successful deployment is indicated when the SnapCenter Plug-in for VMware vSphere is powered on, the VMware tools is installed, and the screen prompts you to log in to the SnapCenter Plug-in for VMware vSphere.

The screen displays the IP address where the SnapCenter Plug-in for VMware vSphere is deployed. Make a note of the IP address. You need to log in to the SnapCenter Plug-in for VMware vSphere management user interface if you want to make changes to the SnapCenter Plug-in for VMware vSphere configuration.

- Log in to the SnapCenter Plug-in for VMware vSphere management user interface using the IP address displayed on the deployment screen using the credentials that you provided in the deployment wizard, then verify on the Dashboard that the SnapCenter Plug-in for VMware vSphere is successfully connected to vCenter and is enabled.

Use the format `https://<appliance-IP-address>:8080` to access the management user interface.

Login with the admin username and password set at the time of deployment and the MFA token generated using the maintenance console.

- Log in to vCenter HTML5 client, then select **Menu** in the toolbar, and then select **SnapCenter Plug-in for VMware vSphere**

Add storage

Follow the steps in this section to add storage.

1. In the left navigator pane of the SCV plug-in, select **Storage Systems** and then select **Add** option.
2. On the Add Storage System dialog box, enter the basic SVM or cluster information, and select **Add**.

Create backup policies

Follow the instructions given below to create backup policies

1. In the left navigator pane of the SCV plug-in, select **Policies**, and then select **New Policy**.
2. On the **New Backup Policy** page, enter the policy configuration information, and then select **Add**.

Create resource groups

Follow the steps below to create resource groups.

1. In the left navigator pane of the SCV plug-in, select **Resource Groups**, and then select **Create**.
2. Enter the required information on each page of the Create Resource Group wizard, select VMs and datastores to be included in the resource group, and then select the backup policies to be applied to the resource group. Add the remote secondary protection details and specify the backup schedule.

Backups are performed as specified in the backup policies that are configured for the resource group.

You can perform a backup on demand from the **Resource Groups** page by selecting  **Run Now**.

Copyright information

Copyright © 2025 NetApp, Inc. All Rights Reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means—graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system—without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

LIMITED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (b)(3) of the Rights in Technical Data -Noncommercial Items at DFARS 252.227-7013 (FEB 2014) and FAR 52.227-19 (DEC 2007).

Data contained herein pertains to a commercial product and/or commercial service (as defined in FAR 2.101) and is proprietary to NetApp, Inc. All NetApp technical data and computer software provided under this Agreement is commercial in nature and developed solely at private expense. The U.S. Government has a non-exclusive, non-transferrable, nonsublicensable, worldwide, limited irrevocable license to use the Data only in connection with and in support of the U.S. Government contract under which the Data was delivered. Except as provided herein, the Data may not be used, disclosed, reproduced, modified, performed, or displayed without the prior written approval of NetApp, Inc. United States Government license rights for the Department of Defense are limited to those rights identified in DFARS clause 252.227-7015(b) (FEB 2014).

Trademark information

NETAPP, the NETAPP logo, and the marks listed at <http://www.netapp.com/TM> are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.