



SnapManager for SAP command reference

SnapManager for SAP

NetApp
November 04, 2025

Table of Contents

SnapManager for SAP command reference	1
The backint register-sld command	1
Syntax	1
Parameters	2
Example command	2
The smsap_server restart command	2
Syntax	3
Parameters	3
Example command	3
The smsap_server start command	3
Syntax	3
Parameters	3
Example command	3
The smsap_server status command	4
Syntax	4
Parameters	4
Example	4
The smsap_server stop command	4
Syntax	4
Parameters	5
Example command	5
The smsap backup create command	5
Syntax	5
Parameters	6
Example command	9
The smsap backup delete command	9
Syntax	9
Parameters	9
Example	10
The smsap backup free command	10
Syntax	10
Parameters	11
Example	12
The smsap backup list command	12
Syntax	12
Parameters	12
Example	13
The smsap backup mount command	13
Syntax	13
Parameters	13
Example	14
The smsap backup restore command	15
Syntax	15

Parameters	16
Example	18
The smsap backup show command	18
Syntax	18
Parameters	19
Example	19
The smsap backup unmount command	20
Syntax	20
Parameters	21
Example	22
The smsap backup update command	22
Syntax	22
Parameters	22
Example	23
The smsap backup verify command	23
Syntax	23
Parameters	24
Example	24
The smsap clone create command	25
Syntax	25
Parameters	25
Example	27
The smsap clone delete command	28
Syntax	28
Parameters	28
Example	29
The smsap clone list command	29
Syntax	29
Parameters	29
Example command	30
The smsap clone show command	30
Syntax	30
Parameters	30
Example	31
The smsap clone template command	32
Syntax	32
Parameters	32
Example command	32
The smsap clone update command	33
Syntax	33
Parameters	33
Example command	33
The smsap clone detach command	34
Syntax	34
Parameters	34

Example	34
The smsap cmdfile command	34
Syntax	34
Parameters	35
The smsap credential clear command	35
Syntax	35
Parameters	35
Example command	35
The smsap credential delete command	35
Syntax	36
Parameters	36
Example command	37
The smsap credential list command	37
Syntax	37
Parameters	38
Example command	38
The smsap credential set command	38
Syntax	39
Parameters	39
Example command for setting repository credentials	40
Example command for setting host credentials	40
The smsap history list command	40
Syntax	40
Parameters	41
Example command	42
The smsap history operation-show command	42
Syntax	42
Parameters	42
Example command	42
The smsap history purge command	43
Syntax	43
Parameters	43
Example command	44
The smsap history remove command	44
Syntax	44
Parameters	44
Example command	45
The smsap history set command	45
Syntax	45
Parameters	46
Example command	47
The smsap history show command	47
Syntax	47
Parameters	47
Example command	48

The smsap help command	48
Syntax	48
Parameters	48
The smsap notification remove-summary-notification command	49
Syntax	49
Parameters	49
The smsap notification update-summary-notification command	50
Syntax	50
Parameters	50
Example	51
The smsap notification set command	52
Syntax	52
Parameters	52
Example	53
The smsap operation dump command	53
Syntax	53
Parameters	54
Example	54
The smsap operation list command	54
Syntax	54
Parameters	55
Example command	55
The smsap operation show command	55
Syntax	56
Parameters	56
Example	56
The smsap password reset command	56
Syntax	56
Parameters	57
The smsap profile create command	57
Syntax	57
Parameters	58
Example	61
The smsap profile delete command	61
Syntax	62
Parameters	62
Example	62
The smsap profile dump command	62
Syntax	62
Parameters	62
Example	63
The smsap profile list command	63
Syntax	63
Parameters	63
Example command	63

The smsap profile show command	65
Syntax	65
Parameters	65
The smsap profile sync command	65
Syntax	65
Parameters	65
Example command	66
The smsap profile update command	66
Syntax	66
Parameters	68
Example	70
The smsap profile verify command	71
Syntax	71
Parameters	71
Example	71
The smsap repository create command	73
Syntax	73
Parameters	73
Command example	74
The smsap repository delete command	74
Syntax	74
Parameters	74
Command example	75
The smsap repository rollback command	75
Syntax	76
Parameters	76
Example command	77
The smsap repository rollingupgrade command	77
Syntax	77
Parameters	77
Example command	78
The smsap repository show command	78
Syntax	79
Parameters	79
Command example	79
The smsap repository update command	80
Syntax	80
Parameters	80
Example command	81
The smsap schedule create command	81
Syntax	81
Parameters	82
The smsap schedule delete command	85
Syntax	85
Parameters	86

The smsap schedule list command	86
Syntax	86
Parameters	86
The smsap schedule resume command	86
Syntax	86
Parameters	86
The smsap schedule suspend command	87
Syntax	87
Parameters	87
The smsap schedule update command	87
Syntax	87
Parameters	88
The smsap storage list command	89
Syntax	89
Parameters	89
Example	89
The smsap storage rename command	89
Syntax	89
Parameters	90
Example	90
The smsap system dump command	90
Syntax	90
Parameters	90
Example of the system dump command	91
The smsap system verify command	91
Syntax	91
Parameters	91
Example of the system verify command	91
The smsap version command	92
Syntax	92
Parameters	92
Example of the version command	92

SnapManager for SAP command reference

The SnapManager command reference includes the valid usage syntax, options, parameters, and arguments you should supply with the commands, along with examples.

The following issues apply to command usage:

- Commands are case-sensitive.
- SnapManager accepts up to 200 characters and labels up to 80 characters.
- If the shell on your host limits the number of characters that can appear on a command line, you can use the cmdfile command.
- Do not use spaces in profile names or label names.
- In the clone specification, do not use spaces in the clone location.

SnapManager can display three levels of messages to the console:

- Error messages
- Warning messages
- Informational messages

You can specify how you want messages displayed. If you specify nothing, SnapManager displays only error messages and warnings to the console. To control the amount of output that SnapManager displays on the console, use one of the following command line options:

- `-quiet`: Displays only error messages to the console.
- `-verbose`: Displays error, warning, and informational messages to the console.



Regardless of the default behavior, or the level of detail you specify for the display, SnapManager always writes all message types to the log files.

The `backint register-sld` command

If you want to use SAP BR*Tools, you can run the `backint register-sld` command with SnapManager for SAP to register the BACKINT interface at your System Landscape Directory (SLD). The BACKINT interface is provided by the storage vendor to make the storage system work with the BR*Tools commands. SnapManager for SAP installs its BACKINT interface file at `C:\Program Files\NetApp\SnapManager for SAP\bin\`.

Syntax

```
backint register-sld
-host host_name
-port port_id
-username username
-password password
-template template_ID
```

Parameters

- **-host *host_name***

Specifies the name of the host on which the SAP SLD is running.

- **-port *port_id***

Specifies the ID of the port on which the SAP SLD accepts HTTP requests. The ID must be numeric and less than or equal to nine digits.

- **-username *username***

Specifies a valid and authorized SAP SLD user name.

- **-password *password***

Specifies a valid and authorized SAP SLD user password. This is optional. If you do not set the password by using **-password**, you will be prompted to enter a password in the following format:

username@http://host:port

If you fail to enter the correct password, after three attempts the command fails and exits.

- **-template *template_id***

Specifies the name of the master template XML file, which can be used as a base for your custom file.

Example command

The following example shows a successful completion of the command:

```
backint register-sld -host jack12 -port 50100
-username j2ee_admin -password user123 -template E:\template.xml
Operation Id [N96f4142a1442b31ee4636841babbc1d7] succeeded.
```

The **smsap_server restart** command

This command restarts the SnapManager host server and is entered as root.

Syntax

```
smsap_server restart
[-quiet | -verbose]
```

Parameters

- **-quiet**

Specifies that only error messages are displayed on the console. The default is to display error and warning messages.

- **-verbose**

Specifies that error, warning, and informational messages are displayed on the console.

Example command

The following example restarts the host server.

```
smsap_server restart
```

The smsap_server start command

This command starts the host server running the SnapManager for SAP software.

Syntax

```
smsap_server start
[-quiet | -verbose]
```

Parameters

- **-quiet**

Specifies that only error messages are displayed on the console. The default is to display error and warning messages.

- **-verbose**

Specifies that error, warning, and informational messages are displayed on the console.

Example command

The following example starts the host server.

```
smsap_server start
SMSAP-17100: SnapManager Server started on secure port 25204 with PID
11250
```

The smsap_server status command

You can run the `smsap_server status` command to view the status of the SnapManager host server.

Syntax

```
smsap_server status
[-quiet | -verbose]
```

Parameters

- **-quiet**

Specifies that only error messages are displayed in the console. The default is to display error and warning messages.

- **-verbose**

Specifies that error, warning, and informational messages are displayed in the console.

Example

The following example displays the status of the host server:

```
smsap_server status
SMSAP-17104: SnapManager Server version 3.3.1 is running on secure port
25204 with PID 11250
and has 0 operations in progress.
```

The smsap_server stop command

This command stops the SnapManager host server and is entered at the root.

Syntax

```
smsap_server stop
[-quiet | -verbose]
```

Parameters

- **-quiet**

Specifies that only error messages are displayed on the console. The default is to display error and warning messages.

- **-verbose**

Specifies that error, warning, and informational messages are displayed on the console.

Example command

The following example uses the `smsap_server stop` command.

```
smsap_server stop
```

The smsap backup create command

You can run the `backup create` command to create database backups on one or more storage systems.

Syntax



Before you run this command, you must create a database profile by using the `profile create` command.

```

smsap backup create
-profile profile_name
{ [-full{-auto | -online | -offline}[-retain {-hourly | -daily | -weekly |
-monthly | -unlimited} [-verify] |
[-data [[-files files [files]] |
[-tablespaces tablespaces [tablespaces]] [-label label] {-auto | -online |
-offline}
[-retain {-hourly | -daily | -weekly | -monthly | -unlimited} [-verify] |
[-archivelogs [-label label]] [-comment comment] }

[-backup-dest path1 [ , path2]]
[-exclude-dest path1 [ , path2]]
[-prunelogs {-all | -until-scn until-scn | -until-date yyyy-MM-
dd:HH:mm:ss} | -before {-months | -days | -weeks | -hours} }
-prune-dest prune_dest1,[prune_dest2]]
[-taskspec taskspec]
[-dump]
-force
[-quiet | -verbose]

```

Parameters

- **`-profile profile_name`**

Specifies the name of the profile related to the database you want to back up. The profile contains the identifier of the database and other database information.

- **`-auto` option**

If the database is in the mounted or offline state, SnapManager performs an offline backup. If the database is in the open or online state, SnapManager performs an online backup. If you use the `-force` option with the `-offline` option, SnapManager forces an offline backup even if the database is currently online.

- **`-online` option**

Specifies an online database backup.

- If the local instance is in the shutdown state and at least one instance is in the open state, you can use the `-force` option to change the local instance to the mounted state.
- If no instance is in open state, you can use the `-force` option to change the local instance to open state.

- **`-offline` option**

Specifies an offline backup while the database is in the shut down state. If the database is in the open or mounted state, the backup fails. If the `-force` option is used, SnapManager attempts to alter the database state to shut down the database for an offline backup.

- **-full option**

Backs up the entire database. This includes all of the data, archived log, and control files. The archived redo logs and control files are backed up no matter what type of backup you perform. If you want to back up only a portion of the database, use the **-files** option or **-tablespaces** option.

- **-data option**

Specifies the data files.

- **-files list**

Backs up only the specified data files plus the archived log and control files. Separate the list of file names with spaces. If the database is in the open state, SnapManager verifies that the appropriate tablespaces are in online backup mode.

- **-tablespaces tablespaces**

Backs up only the specified database tablespaces plus the archived log and control files. Separate the tablespace names with spaces. If the database is in the open state, SnapManager verifies that the appropriate tablespaces are in online backup mode.

- **-label label**

Specifies an optional name for this backup. This name must be unique within the profile. The name can contain letters, numbers, underscores (_), and hyphens (-). It cannot start with a hyphen. If you do not specify a label, SnapManager creates a default label in the `scope_type_date` format:

- Scope is either F to indicate a full backup or P to indicate a partial backup.
- Type is C to indicate an offline (cold) backup, H to indicate an online (hot) backup, or A to indicate auto backup, for example, P_A_20081010060037IST.
- Date is the year, month, day, and time of the backup.

SnapManager uses a 24-hour clock.

For example, if you performed a full backup with the database offline on 16th January 2007, at 5:45:16 p.m. Eastern Standard Time, SnapManager would create the label F_C_20070116174516EST.

- **-comment string**

Specifies an optional comment to describe this backup. Enclose the string in single quotation marks (').



Some shells strip the quotation marks off. In this case, you must include the quotation mark with a backslash (\). For example, you might need to enter the following: \' this is a comment\'.

- **-verify option**

Verifies that the files in the backup are not corrupt by running the Oracle dbv utility.



If you specify the **-verify** option, the backup operation is not completed until the verify operation is complete.

- **-force option**

Forces a state change if the database is not in the correct state. For example, SnapManager might change the state of the database from online to offline, based on the type of backup you specify and the state that the database is in.

- If the local instance is in the shutdown state and at least one instance is in the open state, then using the **-force** option changes the local instance to the mounted state.
- If no instance is in the open state, using the **-force** option changes the local instance to the open state.

- **-quiet**

Displays only error messages in the console. The default is to display error and warning messages.

- **-verbose**

Displays error, warning, and informational messages in the console.

- **-retain { -hourly | -daily | -weekly | -monthly | -unlimited}**

Specifies whether the backup should be retained on an hourly, daily, weekly, monthly, or unlimited basis. If the **-retain** option is not specified, the retention class defaults to **-hourly** option. To retain backups forever, use the **-unlimited** option. The **-unlimited** option makes the backup ineligible for deletion by the retention policy.

- **-archivelogs option**

Creates archive log backup.

- **-backup-dest path1, [, [path2]]**

Specifies the archive log destinations to be backed up for archive log backup.

- **-exclude-dest path1, [, [path2]]**

Specifies the archive log destinations to be excluded from the backup.

- **-prunelogs {-all | -until-scnuntil-scn | -until-date yyyy-MM-dd:HH:mm:ss | -before {-months | -days | -weeks | -hours}}**

Deletes the archive log files from the archive log destinations based on options provided while creating a backup. The **-all** option deletes all of the archive log files from the archive log destinations. The **-until-scn** option deletes the archive log files until a specified System Change Number (SCN). The **-until-date** option deletes the archive log files until the specified time period. The **-before** option deletes the archive log files before the specified time period (days, months, weeks, hours).

- **-prune-dest prune_dest1,prune_dest2**

Deletes the archive log files from the archive log destinations while creating the backup.

- **-taskspec taskspec**

Specifies the task specification XML file that can be used for preprocessing activity or post-processing

activity of the backup operation. The complete path of the XML file should be provided while giving the **-taskspec** option.

- **-dump option**

Collects the dump files after a successful or failed database backup operation.

Example command

The following command creates a full online backup, creates a backup to secondary storage, and sets the retention policy to daily:

```
smsap backup create -profile SALES1 -full -online  
-label full_backup_sales_May -profile SALESDB -force -retain -daily  
Operation Id [8abc01ec0e79356d010e793581f70001] succeeded.
```

The smsap backup delete command

You can run the `backup delete` command to remove backups that are not automatically removed, such as backups that were used to create a clone or backups that failed. You can delete backups retained on an unlimited basis without changing the retention class.

Syntax

```
smsap backup delete  
-profile profile_name  
[-label label [-data | -archivelogs] | [-id guid | -all]  
-force  
[-dump]  
[-quiet | -verbose]
```

Parameters

- **-profile *profile_name***

Specifies the database associated with the backup you want to remove. The profile contains the identifier of the database and other database information.

- **-id *guid***

Specifies the backup with the specified GUID. The GUID is generated by SnapManager when you create a backup. You can use the `smsap backup list` command to display the GUID for each backup.

- **-label *label***

Specifies the backup with the specified label. Optionally, specify the scope of the backup as data file or archive log.

- **-data**

Specifies the data files.

- **-archivelogs**

Specifies the archive log files.

- **-all**

Specifies all backups. To delete only specified backups instead, use the **-id** or **-label** option.

- **-dump**

Collects the dump files after a successful or failed backup delete operation.

- **-force**

Forces the removal of the backup. SnapManager removes the backup even if there are problems in freeing the resources associated with the backup. For example, if the backup was cataloged with Oracle Recovery Manager (RMAN), but the RMAN database no longer exists, including **-force** deletes the backup even though it cannot connect with RMAN.

- **-quiet**

Displays only error messages in the console. The default is to display error and warning messages.

- **-verbose**

Displays error, warning, and informational messages in the console.

Example

The following example deletes the backup:

```
smssap backup delete -profile SALES1 -label full_backup_sales_May
Operation Id [8abc01ec0e79004b010e79006da60001] succeeded.
```

The smssap backup free command

You can run the **backup free** command to free the Snapshot copies of the backups without removing the backup metadata from the repository.

Syntax

```
  smsap backup free
  -profile profile_name
  [-label label [-data | -archivelogs] | [-id guid | -all]
  -force
  [-dump]
  [-quiet | -verbose]
```

Parameters

- **-profile *profile_name***

Specifies the profile associated with the backup you want to free. The profile contains the identifier of the database and other database information.

- **-id *guid***

Specifies the resources of the backup with the specified GUID. The GUID is generated by SnapManager when you create a backup. You can use the `smsap backup list` command to display the GUID for each backup. Include the `-verbose` option to display the backup IDs.

- **-label *label***

Specifies the backup with the specified label.

- **-data**

Specifies the data files.

- **-archivelogs**

Specifies the archive log files.

- **-all**

Specifies all backups. To delete specified backups instead, use the `-id` or `-label` option.

- **-force**

Forces the removal of the Snapshot copies.

- **-quiet**

Displays only error messages in the console. The default is to display error and warning messages.

- **-verbose**

Displays error, warning, and informational messages in the console.

Example

The following example frees the backup:

```
smsap backup free -profile SALES1 -label full_backup_sales_May
Operation Id [8abc01ec0e79004b010e79006da60001] succeeded.
```

The smsap backup list command

You can run the `backup list` command to display information about the backups in a profile, including information about the retention class and protection status.

Syntax

```
smsap backup list
-profile profile_name
-delimiter character
[-data | -archivelogs | -all]
[-quiet | -verbose]
```

Parameters

- **`-profile profile_name`**

Specifies the profile you want to list backups for. The profile contains the identifier of the database and other database information.

- **`-delimiter character`**

Displays each row on a separate line. The attributes in the row are separated by the character specified.

- **`-data`**

Specifies the data files.

- **`-archivelogs`**

Specifies the archive log files.

- **`-quiet`**

Displays only error messages in the console. The default is to display error and warning messages.

- **`-verbose`**

Displays error, warning, and informational messages in the console. Include the `-verbose` option to display the backup IDs.

Example

The following example lists the backups for the SALES1 profile:

```
smsap backup list -profile SALES1 -verbose
Start Date      Status  Scope   Mode    Primary  Label      Retention
Protection
-----
-----
2007-08-10 14:12:31 SUCCESS FULL    ONLINE   EXISTS   backup2   HOURLY
NOT REQUESTED
2007-08-05 12:08:37 SUCCESS FULL    ONLINE   EXISTS   backup4   UNLIMITED
NOT REQUESTED
2007-08-04 22:03:09 SUCCESS FULL    ONLINE   EXISTS   backup6   UNLIMITED
NOT REQUESTED
```

The smsap backup mount command

You can run the `backup mount` command to mount a backup in order to perform a recover operation by using an external tool.

Syntax

```
smsap backup mount
-profile profile_name
[-label label [-data | -archivelogs] | [-id id]
[-host host]

[-dump]
[-quiet | -verbose]
```

Parameters

- **`-profile profile_name`**

Specifies the profile associated with the backup that you want to mount. The profile contains the identifier of the database and other database information.

- **`-id guid`**

Mounts the backup with the specified GUID. The GUID is generated by SnapManager when you create a backup. You can use the `smsap backup list` command to display the GUID for each backup.

- **`-label label`**

Mounts the backup with the specified label.

- **-data**

Specifies the data files.

- **-archivelogs**

Specifies the archive log files.

- **-host host**

Specifies the host on which you want to mount the backup.

- **-dump**

Collects the dump files after the successful or failed mount operation.

- **-quiet**

Displays only error messages in the console. The default setting is to display error and warning messages.

- **-verbose**

Displays error, warning, and informational messages in the console.

 You must use this command only if you are using an external tool such as Oracle Recovery Manager (RMAN). SnapManager automatically handles the mounting of backups if you use the `smsap backup restore` command to restore the backup. This command displays a list, which shows the paths where the Snapshot copies have been mounted. This list is displayed only when the `-verbose` option is specified.

Example

The following example mounts the backup:

```
smsap backup mount -profile S10_BACKUP -label full_monthly_10 -verbose
[INFO ]: SMSAP-13051: Process PID=6852
[INFO ]: SMSAP-13036: Starting operation Backup Mount on host
hadley.domain.private
[INFO ]: SMSAP-13036: Starting operation Backup Mount on host
hadley.domain.private
[INFO ]: SMSAP-13046: Operation GUID 8abc01573883daf0013883daf5ac0001
starting on Profile FAS_P1
[INFO ]: SD-00025: Beginning to connect filesystem(s) [I:\] from snapshot
smsap_fas_p1_fasdb_d_h_2_8abc0157388344bc01388344c2d50001_0.
[INFO ]: SD-00016: Discovering storage resources for
C:\SnapManager_auto_mounts\I-2012071400592328_0.
[INFO ]: SD-00017: Finished storage discovery for
C:\SnapManager_auto_mounts\I-2012071400592328_0
[INFO ]: SD-00026: Finished connecting filesystem(s) [I:\] from snapshot
smsap_fas_p1_fasdb_d_h_2_8abc0157388344bc01388344c2d50001_0.
[INFO ]: SD-00025: Beginning to connect filesystem(s) [H:\] from snapshot
smsap_fas_p1_fasdb_d_h_1_8abc0157388344bc01388344c2d50001_0.
[INFO ]: SD-00016: Discovering storage resources for
C:\SnapManager_auto_mounts\H-2012071400592312_0.
[INFO ]: SD-00017: Finished storage discovery for
C:\SnapManager_auto_mounts\H-2012071400592312_0.
[INFO ]: SD-00026: Finished connecting filesystem(s) [H:\] from snapshot
smsap_fas_p1_fasdb_d_h_1_8abc0157388344bc01388344c2d50001_0.
[INFO ]: SMSAP-13048: Backup Mount Operation Status: SUCCESS
[INFO ]: SMSAP-13049: Elapsed Time: 0:19:05.620
```

The smsap backup restore command

You can run the `backup restore` command to restore backups of a database or a portion of a database, and then optionally recover the database information.

Syntax

```

smsap backup restore
-profile profile_name
[-label label | -id id]
[-files files [files...]] |
-tablespaces tablespaces [tablespaces...]] |
-complete | -controlfiles]
[-recover {-alllogs | -nologs | -until until} [-using-backup-controlfile]]
[-restorespec restorespec | []]
[-preview]

[-recover-from-location path1 [, path2]]
[-taskspec taskspec]
[-dump]
[-force]
[-quiet | -verbose]

```

Parameters

- **-profile *profile_name***

Specifies the database that you want to restore. The profile contains the identifier of the database and other database information.

- **-label *name***

Restores the backup with the specified label.

- **-id *guid***

Restores the backup with the specified GUID. The GUID is generated by SnapManager when you create a backup. You can use the `smsap backup list` command to display the GUID for each backup.

- **Choose all or specified files**

Optionally, you can use one of the following options:

- **-complete:** Restores all the data files in the backup.
- **-tablespaceslist:** Restores only the specified tablespaces from the backup.

You must use spaces to separate the names in the list.

- **-fileslist:** Restores only the specified data files from the backup.

You must use spaces to separate the names in the list. If the database is running, SnapManager ensures that the tablespace containing the files is offline.

- **-controlfiles**

Restores the control files. SnapManager allows you to restore control files along with the data files from the

backups in a single operation. The `-controlfiles` option is independent of other restore scope parameters such as `-complete`, `-tablespaces`, and `-files`.

- **`-recover`**

Recovers the database after restoring it. You must also specify the point to which you want SnapManager to recover the database by using one of the following options:

- `-nologs`: Recovers the database to the time of the backup and applies no logs.

You can use this parameter for online or offline backups.

- `-alllogs`: Recovers the database to the last transaction or commit, and applies all required logs.

- `-until date`: Recovers the database up to the date and time specified.

You must use the year-month-date: hour: minute: second (`yyyy-mm-dd:hh:mm:ss`) format. For hours, use either 12-hour or 24-hour format, depending on the database setting.

- `-until scn`: Rolls forward the data files until it reaches the specified system change number (SCN).

- `-using-backup-controlfile`: Recovers the database using the backup control file.

- **`-restorespec`**

Enables you to restore the data to an active file system and restore from the specified data by providing a mapping of each original Snapshot copy to its active file system. If you do not specify an option, SnapManager restores the data from the Snapshot copies on primary storage. You can specify one of the following options:

- `-restorespec`: Specifies the data to restore and the restore format.

- **`-preview`**

Displays the following information:

- Which restore mechanism (storage-side file system restore, storage-side file restore, or host-side file copy restore) will be used to restore each file
- Why more efficient mechanisms were not used to restore each file, when you specify the `-verbose` option If you are using the `-preview` option, you must know the following:
 - The `-force` option has no impact on the command.
 - The `-recover` option has no impact on the command. To preview the restore operation, the database must be mounted. If you want to preview a restore plan, and the database currently is not mounted, then SnapManager mounts the database. If the database cannot be mounted, then the command will fail, and SnapManager returns the database to its original state.

The `-preview` option displays up to 20 files. You can configure the maximum number of files to be displayed in the `smsap.config` file.

- **`-recover-from-location`**

Specifies the external archive log location of the archive log files. SnapManager takes the archive log files from the external location and uses them for the recovery process.

- **-taskspec**

Specifies the task specification XML file for preprocessing activity or post-processing activity of the restore operation. You must provide the complete path of the task specification XML file.

- **-dump**

Specifies to collect the dump files after the restore operation.

- **-force**

Changes the database state to a lower state than its current state, if necessary.

By default, SnapManager can change the database state to a higher state during an operation. This option is not required for SnapManager to change the database to a higher state.

- **-quiet**

Displays only error messages in the console. The default setting is to display error and warning messages.

- **-verbose**

Displays error, warning, and informational messages in the console. You can use this option to see why more efficient restore processes could not be used to restore the file.

Example

The following example restores a database along with the control files:

```
smsap backup restore -profile SALES1 -label full_backup_sales_May  
-complete -controlfiles -force
```

The smsap backup show command

You can use the `backup show` command to display detailed information about a backup, including its protection status, backup retention class, and backups on primary and secondary storage.

Syntax

```
smsap backup show  
-profile profile_name  
[-label label [-data | -archivelogs] | [-id id]  
[-quiet | -verbose]
```

Parameters

- **-profile *profile_name***

Specifies the profile for which to show backups. The profile contains the identifier of the database and other database information.

- **-label *label***

Specifies the label of the backup.

- **-data**

Specifies the data files.

- **-archivelogs**

Specifies the archive log files.

- **-id *id***

Specifies the backup ID.

- **-quiet**

Displays only error messages in the console. The default is to display error and warning messages.

- **-verbose**

Displays error, warning, and informational messages in the console, as well as any clone and verification information.

Example

The following example shows detailed information about the backup:

```
smsap backup show -profile SALES1 -label BTNFS -verbose
Backup id: 8abc013111a450480111a45066210001
Backup status: SUCCESS
Primary storage resources: EXISTS
Protection state: NOT REQUESTED
Retention class: DAILY
Backup scope: FULL
Backup mode: OFFLINE
Mount status: NOT MOUNTED
Backup label: BTNFS
Backup comment:

Backup start time: 2007-03-30 15:26:30
Backup end time: 2007-03-30 15:34:13
Verification status: OK
Backup Retention Policy: NORMAL
Backup database: hsdb1
Checkpoint: 2700620
Tablespace: SYSAUX
Datafile: E:\disks\data\hsdb\sysaux01.dbf [ONLINE]
...
Control Files:
File: E:\disks\data\control03.ctl
...
Archive Logs:
File: E:\disks\data\archive_logs\2_131_626174106.dbf
...
Volume: hs_data
Snapshot: SMSAP_HSDBR_hsdb1_F_C_1_
8abc013111a450480111a45066210001_0
File: E:\disks\data\hsdb\SMSAPBakCtl_1175283005231_0
...
```

The smsap backup unmount command

You can run the `backup unmount` command to unmount a backup.

Syntax

```
  smsap backup unmount
  -profile profile_name
  [-label label [-data | -archivelogs] | [-id id]
  [-force]
  [-dump]
  [-quiet | -verbose]
```

Parameters

- **-profile *profile_name***

Specifies the profile for which you want to unmount a backup. The profile contains the identifier of the database and other database information.

- **-id *id***

Unmounts the backup with the specified GUID. The GUID is generated by SnapManager when you create a backup. You can use the `smsap backup list` command to display the GUID for each backup.

- **-label *label***

Unmounts the backup with the specified label.

- **-data**

Specifies the data files.

- **-archivelogs**

Specifies the archive log files.

- **-dump**

Collects the dump files after a successful or failed unmount operation.

- **-force**

Unmounts the backup even if there are problems in freeing the resources associated with the backup. SnapManager tries to unmount the backup and clean up any associated resources. The log shows the unmount operation as successful, but you may have to manually clean up resources if there are errors in the log.

- **-quiet**

Displays only error messages in the console. The default is to display error and warning messages.

- **-verbose**

Displays error, warning, and informational messages in the console.

Example

The following is an example of an unmount operation:

```
# smsap backup unmount -label test -profile SALES1 -verbose
```

```
[INFO ]: SMSAP-13051: Process PID=9788
[INFO ]: SMSAP-13036: Starting operation Backup Unmount on host
hadley.domain.private
[INFO ]: SMSAP-13036: Starting operation Backup Unmount on host
hadley.domain.private
[INFO ]: SMSAP-13046: Operation GUID 8abc015738849a3d0138849a43900001
starting on Profile FAS_P1
[INFO ]: SD-00031: Beginning to disconnect filesystem(s)
[C:\SnapManager_auto_mounts\H-2012071400592312_0,
C:\SnapManager_auto_mounts\I-2012071400592328_0].
[INFO ]: SD-00032: Finished disconnecting filesystem(s)
[C:\SnapManager_auto_mounts\H-2012071400592312_0,
C:\SnapManager_auto_mounts\I-2012071400592328_0].
[INFO ]: SMSAP-13048: Backup Unmount Operation Status: SUCCESS
[INFO ]: SMSAP-13049: Elapsed Time: 0:07:26.754
```

The smsap backup update command

You can run the `backup update` command to update the backup retention policy.

Syntax

```
smsap backup update
-profile profile_name
[-label label [-data | -archivelogs] | [-id guid]
[-retain {-hourly | -daily | -weekly | -monthly | -unlimited}]
[-comment comment_text]
[-quiet | -verbose]
```

Parameters

- **`-profile profile_name`**

Specifies the profile for which to update backups. The profile contains the identifier of the database and other database information.

- **`-id guid`**

Verifies the backup with the specified GUID. The GUID is generated by SnapManager when you create a backup. You can use the `smsap backup list` command to display the GUID for each backup.

- **`-label label`**

Specifies the backup label and scope of the backup as data file or archive log.

- **`-data`**

Specifies the data files.

- **`-archivelogs`**

Specifies the archive log files.

- **`-comment comment_text`**

Enter text (up to 200 characters) about the backup update. You can include spaces.

- **`-quiet`**

Displays only error messages in the console. The default is to display error and warning messages.

- **`-verbose`**

Displays error, warning, and informational messages in the console.

- **`-retain {-hourly | -daily | -weekly | -monthly | -unlimited}`**

Specifies whether the backup should be retained on an hourly, daily, weekly, monthly, or unlimited basis. If `-retain` is not specified, the retention class defaults to `-hourly`. To retain backups forever, use the `-unlimited` option. The `-unlimited` option makes the backup ineligible for deletion.

Example

The following example updates the backup to be set the retention policy to unlimited:

```
smsap backup update -profile SALES1 -label full_backup_sales_May  
-retain -unlimited -comment save_forever_monthly_backup
```

The `smsap backup verify` command

You can run the `backup verify` command to see if the backup is in a valid format for Oracle.

Syntax

```
smsap backup verify
-profile profile_name
[-label backup_name | [-id guid]
[-retain {-hourly | -daily | -weekly | -monthly | -unlimited}]
[-force]
[-dump]
[-quiet | -verbose]
```

Parameters

- **-profile *profile_name***

Specifies the profile for which you want to verify a backup. The profile contains the identifier of the database and other database information.

- **-id *guid***

Verifies the backup with the specified GUID. The GUID is generated by SnapManager when you create a backup. You can use the `smsap backup list` command to display the GUID for each backup.

- **-label *label_name***

Verifies the backup with the specified label.

- **-dump**

Collects the dump files after the successful or failed backup verify operation.

- **-force**

Forces the database into the necessary state to perform the verify operation.

- **-quiet**

Displays only error messages in the console. The default is to display error and warning messages.

- **-verbose**

Displays error, warning, and informational messages in the console.

Example

The following is an example of verifying the backup:

```
smsap backup verify -profile SALES1 -label full_backup_sales_May -quiet
```

```
DBVERIFY - Verification starting : FILE = C:\SnapManager_auto_mounts\H-2012071400592312_0\smsap\datafile\data
```

The smsap clone create command

You can run the `clone create` command to create a clone of a backed-up database. You can clone a backup from primary or secondary storage.

Syntax

```
smsap clone create
-profile profile_name
[-backup-id backup_guid | -backup-label backup_label_name | -current]
-newsid new_sid
[-host target_host]
[-label clone_label]
[-comment string]
-clonespec full_path_to_clonespec_file
]
[-syspassword syspassword]
[-reserve {yes | no | inherit}]

[-no-resetlogs | -recover-from-location path1 [, path2]] [-taskspec
taskspec]
[-dump]
[-quiet | -verbose]
```

Parameters

- **`-profile name`**

Specifies the database that you want to clone. The profile contains the identifier of the database and other database information.

- **`-backup-id guid`**

Clones the backup with the specified GUID. The GUID is generated by SnapManager when you create a backup. You can use the `smsap backup list-verbose` command to display the GUID for each backup.

- **`-backup-label backup_label_name`**

Specifies to clone the backup with the specified label name.

- **`-current`**

Specifies to create backup and clone from the current state of the database.



If the database is in the `noarchivelog` mode, SnapManager will create an offline backup.

- **`-newsid new_sid`**

Specifies a new, unique Oracle system identifier for the cloned database. The system identifier value is a maximum of eight characters. Oracle does not allow running two databases with the same system identifier on the same host simultaneously.

- **`-host target_host`**

Specifies the host on which the clone should be created.

- **`-label clone_label`**

Specifies a label for the clone.

- **`-comment string`**

Specifies an optional comment to describe this clone. You must enclose the string within single quotation marks.



Some shells delete the quotation marks. If that is true for your shell, you must escape the quotation with a backslash (\). For example, you might need to enter: `\' this is a comment\'`

- **`-clonespec full_path_to_clonespec_file`**

Specifies the path to the clone specification XML file. This can be a relative or an absolute path name.

- **`-syspassword syspassword`**

Specifies the password for the sys privileged user.



You must provide the password for the sys privileged user if the database credentials that are provided are not the same for the sys privileged user.

- **`-reserve`**

Setting the `-reserve` option to yes ensures that the volume guarantee space reserve is turned on for the new clone volumes. Setting the `-reserve` option to no ensures that the volume guarantee space reserve is turned off for the new clone volumes. Setting the `-reserve` option to inherit ensures that the new clone inherits the space reservation characteristics of the parent Snapshot copy. The default setting is no.

The following table describes the cloning methods and their effect on the clone create operation and its `-reserve` option. A LUN can be cloned by using either method.

Cloning method	Description	Result
----------------	-------------	--------

LUN cloning	A new clone LUN is created within the same volume.	When the -reserve option for a LUN is set to yes, space is reserved for the full LUN size within the volume.
Volume cloning	A new FlexClone is created, and the clone LUN exists within the new clone volume. Uses the FlexClone technology.	When the -reserve option for a volume is set to yes, space is reserved for the full volume size within the aggregate.

- **-no-resetlogs**

Specifies to skip recovering the database, executing the DBNEWID utility, and not opening the database with the resetlogs while creating the clone.

- **-recover-from-location**

Specifies the external archive log location of the archive log backups where SnapManager takes the archive log files from the external location and uses them for cloning.

- **-taskspec**

Specifies the task specification XML file for preprocessing activity or post-processing activity of the clone operation. You must provide the complete path of the task specification XML file.

- **-dump**

Specifies to collect the dump files after the clone create operation.

- **-quiet**

Displays only error messages in the console. The default setting is to display error and warning messages.

- **-verbose**

Displays error, warning, and informational messages in the console.

Example

The following example clones the backup by using a clone specification that is created for this clone:

```
smsap clone create -profile SALES1 -backup-label full_backup_sales_May
-newsid
CLONE -label sales1_clone -clonespec E:\\spec\\clonespec.xml
```

Operation Id [8abc01ec0e794e3f010e794e6e9b0001] succeeded.

The smsap clone delete command

You can run the `clone delete` command to delete a clone. You cannot delete a clone if the clone is used by any operation.

Syntax

```
smsap clone delete
-profile profile_name
[-id guid | -label clone_name]
[-login
[-username db_username -password db_password -port db_port]
]
[-syspassword syspassword]
-force
[-dump]
[-quiet | -verbose]
```

Parameters

- **`-profile profile_name`**

Specifies the name of the profile containing the clone being deleted. The profile contains the identifier of the database and other database information.

- **`-force`**

Deletes the clone even if there are resources associated with the clone.

- **`-id guid`**

Specifies the GUID for the clone being deleted. The GUID is generated by SnapManager when you create a clone. You can use the `smsap clone list` command to display the GUID for each clone.

- **`-label name`**

Specifies the label for the clone being deleted.

- **`-syspassword syspassword`**

Specifies the password for the sys privileged user.



You must provide the password for the sys privileged user if the database credentials provided are not the same for sys privileged user.

- **`-login`**

Allows you to enter the database login details.

- **-username *db_username***

Specifies the user name required to access the database.

- **-password *db_password***

Specifies the password required to access the database.

- **-port *db_port***

Specifies the TCP port number used to access the database that the profile describes.

- **-dump**

Specifies to collect the dump files after the clone delete operation.

- **-quiet**

Displays only error messages in the console. The default is to display error and warning messages.

- **-verbose**

Displays error, warning, and informational messages in the console.

Example

The following example deletes the clone:

```
smsap clone delete -profile SALES1 -label SALES_May
Operation Id [8abc01ec0e79004b010e79006da60001] succeeded.
```

The smsap clone list command

This command lists the clones of the database for a given profile.

Syntax

```
smsap clone list
-profile profile_name
-delimiter character
[-quiet | -verbose]
```

Parameters

- **-profile *profile_name***

Specifies the list of clones associated with the profile. The profile contains the identifier of the database and other database information.

- **-delimiter *character***

When this parameter is specified, the command lists the attributes in each row separated by the character specified.

- **-quiet**

Displays only error messages on the console. The default is to display error and warning messages.

- **-verbose**

Displays error, warning, and informational messages on the console.

Example command

The following example lists the database clones in the SALES1 profile.

```
smsap clone list -profile SALES1 -verbose
```

ID	Status	SID	Host	Label	Comment
8ab...	01	SUCCESS	hsdbc	server1	back1clone test comment

The smsap clone show command

You can run the `clone show` command to display information about the database clones for the specified profile.

Syntax

```
smsap clone show
-profile profile_name
[-id guid | -label clone_name]
[-quiet | -verbose]
```

Parameters

- **-profile *profile_name***

Specifies the list of clones associated with the profile. The profile contains the identifier of the database and other database information.

- **-id *guid***

Shows information about the clone with the specified GUID. The GUID is generated by SnapManager

when you create a clone. You can use the `smsap clone show` command to display the GUID for each clone.

- **`-label label_name`**

Shows information about the clone with the specified label.

- **`-quiet`**

Displays only error messages in the console. The default is to display error and warning messages.

- **`-verbose`**

Displays error, warning, and informational messages in the console.

Example

The following example displays information about the clone:

```
smsap clone show -profile SALES1 -label full_backup_sales_May -verbose
```

The following output shows information about a clone of a backup on primary storage:

```
Clone id: 8abc013111b916e30111b916ffb40001
Clone status: SUCCESS
Clone SID: hsdbc
Clone label: hsdbc
Clone comment: null
Clone start time: 2007-04-03 16:15:50
Clone end time: 2007-04-03 16:18:17
Clone host: Host1
Filesystem: E:\ssys1\data_clone\
File: E:\ssys1\data_clone\hsdb\sysaux01.dbf
File: E:\ssys1\data_clone\hsdb\undotbs01.dbf
File: E:\ssys1\data_clone\hsdb\users01.dbf
File: E:\ssys1\data_clone\hsdb\system01.dbf
File: E:\ssys1\data_clone\hsdb\undotbs02.dbf
Backup id: 8abc013111a450480111a45066210001
Backup label: full_backup_sales_May
Backup SID: hsdb1
Backup comment:
Backup start time: 2007-03-30 15:26:30
Backup end time: 2007-03-30 15:34:13
Backup host: server1
```

The smsap clone template command

This command lets you create a clone specification template.

Syntax

```
smsap clone template
-profile name
[-backup-id guid | -backup-label backup_label_name]
[-quiet | -verbose]
```

Parameters

- **-profile name**

Specifies the database you want to create a clone specification of. The profile contains the identifier of the database and other database information.

- **-backup-id guid**

Creates a clone specification from the backup with the specified GUID. The GUID is generated by SnapManager when you create a backup. Use the `smsap backup list` command to display the GUID for each backup.

- **-backup-label backup_label_name**

Creates a clone specification from the backup with the specified backup label.

- **-quiet**

Displays only error messages on the console. The default is to display error and warning messages.

- **-verbose**

Displays error, warning, and informational messages on the console.

Example command

The following example creates a clone specification template from the backup with the label `full_backup_sales_May`. Once the `smsap clone template` command completes, the clone specification template is complete.

```
smsap clone template -profile SALES1 -backup-label full_backup_sales_May
Operation Id [8abc01ec0e79004b010e79006da60001] succeeded.
```

The smsap clone update command

This command updates information about the clone. You can update the comment.

Syntax

```
smsap clone update
-profile profile_name
[-label label | -id id]
-comment commment_text
[-quiet | -verbose]
```

Parameters

- **-profile *profile_name***

Specifies the name of the profile containing the clone you want to update. The profile contains the identifier of the database and other database information.

- **-id *id***

Specifies the ID for the clone. The ID is generated by SnapManager when you create a clone. Use the `smsap clone list` command to display the ID for each clone.

- **-label *label***

Specifies the label for the clone.

- **-comment**

Shows the comment entered in the clone creation. This is an optional parameter.

- **-quiet**

Displays only error messages on the console. The default is to display error and warning messages.

- **-verbose**

Displays error, warning, and informational messages on the console.

Example command

The following example updates the clone comment.

```
smsap clone update -profile anson.pcrac5
-label clone_pcrac51_20080820141624EDT -comment See updated clone
```

The smsap clone detach command

After splitting a cloned volume from its parent volume in Data ONTAP, you can run the `clone detach` command from SnapManager to let SnapManager know that the volume is no longer a clone.

Syntax

```
smsap clone detach -profile profile_name -label clone_label
```

Parameters

- **`-profile profile_name`**

Specifies the profile name from which the clone is created.

- **`-label clone_label`**

Specifies the name generated by the clone operation.

Example

The following command detaches the clone:

```
smsap clone detach -profile SALES1 -label sales1_clone
```

The smsap cmdfile command

You can use the `cmdfile` command to run any command if the shell on your host limits the number of characters that can appear on a command line.

Syntax

```
smsap cmdfile
-file file_name
[-quiet | -verbose]
```

You can include the command in a text file and use the `smsap cmdfile` command to execute the command. You can add only one command in a text file. You must not include `smsap` in the command syntax.



The `smsap cmdfile` command replaces the `smsap pfile` command. The `smsap cmdfile` is not compatible with the `smsap pfile` command.

Parameters

- **-file *file_name***

Specifies the path to text file containing the command you want to execute.

- **-quiet**

Specifies that only error messages are displayed in the console. The default is to display error and warning messages.

- **-verbose**

Specifies that error, warning, and informational messages are displayed in the console.

The smsap credential clear command

This command clears the cache of the user credentials for all secured resources.

Syntax

```
smsap credential clear  
[-quiet | -verbose]
```

Parameters

- **-quiet**

Displays only error messages on the console. The default is to display error and warning messages.

- **-verbose**

Displays error, warning, and informational messages on the console.

Example command

This example clears all of the credentials for the user running the command.

```
smsap credential clear -verbose
```

```
SMSAP-20024 [INFO ]: Cleared credentials for user "user1".
```

The smsap credential delete command

This command deletes the user credentials for a particular secured resource.

Syntax

```
smssap credential delete
[-host -name host_name
-username username] |
[-repository
-database repo_service_name
-host repo_host
-login -username repo_username
-port repo_port] |
[-profile
-name profile_name]
[-quiet | -verbose]
```

Parameters

- **-host *hostname***

Specifies the name of the host server on which SnapManager is running.

The **-host** parameter includes the following options:

- **-name *host_name***: Specifies the name of the host for which you will delete the password.
- **-username *user_name***: Specifies the user name on the host.

- **-repository -database**

Specifies the name of the database that stores the profile. Use either the global name or the SID.

The **-repository** parameter includes the following options:

- **-database *repo_service_name***: Specifies the name of the database that stores the profile. Use either the global name or the SID.
- **-host *repo_host***: Specifies the name or IP address of the host server the repository database runs on.
- **-login-username *repo_username***: Specifies the user name needed to access the database that stores the repository.
- **-port *repo_port***: Specifies the TCP port number used to access the database that stores the repository.

- **-profile -name *profile_name***

Specifies the profile with which the database is associated.

The **-profile** parameter includes the following option:

- **-name *profile_name***: Specifies the name of the profile for which you will delete the password.

- **-quiet**

Displays only error messages on the console. The default is to display error and warning messages.

- **-verbose**

Displays error, warning, and informational messages on the console.

Example command

This example deletes the credentials of the profile.

```
  smsap credential delete -profile -name user1 -verbose
```

```
SMSAP-20022 [INFO ]: Deleted credentials and repository mapping
for profile "user1" in user credentials for "user1".
```

This example deletes the credentials of the repository.

```
  smsap credential delete -repository -dbname SMSAPREPO -host Host2
  -login -username user1 -port 1521
```

```
SMSAP-20023 [INFO ]: Deleted repository credentials for
"user1@SMSAPREPO/wasp:1521"
and associated profile mappings in user credentials for "user1".
```

This example deletes the credentials of the host.

```
  smsap credential delete -host -name Host2
```

```
SMSAP-20033 [INFO ]: Deleted host credentials for "Host2" in user
credentials for "user1".
```

The smsap credential list command

This command lists all credentials of a user.

Syntax

```
  smsap credential list
  [-quiet | -verbose]
```

Parameters

- **-quiet**

Displays only error messages on the console. The default is to display error and warning messages.

- **-verbose**

Displays error, warning, and informational messages on the console.

Example command

This example displays all of the credentials for the user running the command.

```
smssap credential list
```

```
Credential cache for OS user "user1":  
Repositories:  
Host1_test_user@SMSAPREPO/hotspur:1521  
Host2_test_user@SMSAPREPO/hotspur:1521  
user1_1@SMSAPREPO/hotspur:1521  
Profiles:  
HSDBR (Repository: user1_2_1@SMSAPREPO/hotspur:1521)  
PBCASM (Repository: user1_2_1@SMSAPREPO/hotspur:1521)  
HSDB (Repository: Host1_test_user@SMSAPREPO/hotspur:1521) [PASSWORD NOT  
SET]  
Hosts:  
Host2  
Host5  
Host4  
Host1
```

The smssap credential set command

This command lets you set the credentials for users to access secure resources, such as hosts, repositories, and database profiles. The host password is the user's password on the host on which SnapManager is running. The repository password is the password of the Oracle user that contains the SnapManager repository schema. The profile password is a password that is made up by the person who creates the profile. For the host and repository options, if the optional **-password** option is not included, you will be prompted to enter a password of the type specified in the command arguments.

Syntax

```
smssap credential set
[-host
-name host_name
-username username]
[-password password]] |
[-repository
-dbname repo_service_name
-host repo_host
-login -username repo_username] [-password repo_password] ]
-port repo_port |
[-profile
-name profile_name]
[-password password]]
[-quiet | -verbose]
```

Parameters

- **-host *hostname***

Specifies the name or IP address of the host server on which SnapManager is running.

The **-host** parameter includes the following options:

- **-name host_name**: Specifies the name of the host for which you will set the password.
- **-username user_name**: Specifies the user name on the host.
- **-password password**: Specifies the password of the user on the host.

- **-repository -dbname**

Specifies the name of the database that stores the profile. Use either the global name or the SID.

The **-repository** parameter includes the following options:

- **-dbnamerepo_service_name**: Specifies the name of the database that stores the profile. Use either the global name or the SID.
- **-host repo_host**: Specifies the name or IP address of the host server the repository database runs on.
- **-login-username repo_username**: Specifies the user name needed to access the database that stores the repository.
- **-password password**: Specifies the password needed to access the database that stores the repository.
- **-port repo_port**: Specifies the TCP port number used to access the database that stores the repository.

- **-profile -name *profile_name***

Specifies the profile with which the database is associated.

The `-profile` parameter includes the following option:

- `-name filename`: Specifies the name of the profile for which you will set the password.
- `-password password`: Specifies the password needed to access the profile.

- **-quiet**

Displays only error messages on the console. The default is to display error and warning messages.

- **-verbose**

Displays error, warning, and informational messages on the console.

Example command for setting repository credentials

The following example sets credentials for a repository.

```
smsap credential set -repository -dbname SMSAPREPO -host hotspur -port  
1527 -login -username chris  
Password for chris@hotspur:1527/SMSAPREPO : *****  
Confirm password for chris@hotspur:1527/SMSAPREPO : *****
```

```
SMSAP-12345 [INFO ]: Updating credential cache for OS user "admin1"  
SMSAP-12345 [INFO ]: Set repository credential for user "user1" on  
repo1@Host2.  
Operation Id [Nff8080810da9018f010da901a0170001] succeeded.
```

Example command for setting host credentials

Because a host credential represents an actual operating system credential, it must include the username in addition to the password.

```
smsap credential set -host -name bismarck -username avida  
Password for avida@bismarck : *****  
Confirm password for avida@bismarck : *****
```

The smsap history list command

This command enables you to view a list of history details of the SnapManager operation.

Syntax

```
smsap history list
-profile {-name profile_name [profile_name1, profile_name2] | -all
-repository
-login [-password repo_password]
-username repo_username
-host repo_host
-dbname repo_dbname
-port repo_port}
-operation {-operations operation_name [operation_name1, operation_name2]
| -all}
[-delimiter character]
[-quiet | -verbose]
```

Parameters

- **-profile *profile***

Specifies the name of the profile. This name can be up to 30 characters long and must be unique within the host.

- **-repository**

The options that follow -repository specify the details of the database that stores the profile.

- **-dbname *repo_dbname***

Specifies the name of the database that stores the profile. Use either the global name or the SID.

- **-host *repo_host***

Specifies the name or IP address of the host computer the repository database runs on.

- **-login**

Starts the repository login details.

- **-username *repo_username***

Specifies the user name needed to access the database that stores the repository.

- **-port *repo_port***

Specifies the TCP port number used to access the database that stores the repository.

- **-operation {-operations *operation_name* [*operation_name1, operation_name2*] | -all}**

Specifies the SnapManager operation for which you configure the history.

- **-quiet**

Displays only error messages on the console. The default is to display error and warning messages.

- **-verbose**

Displays error, warning, and informational messages on the console.

Example command

```
  smsap history list -profile -name PROFILE1 -operation -operations backup  
  -verbose
```

The smsap history operation-show command

This command enables you to view the history of a specific SnapManager operation associated with a profile.

Syntax

```
  smsap history operation-show  
  -profile profile  
  {-label label | -id id}  
  [-quiet | -verbose]
```

Parameters

- **-profile *profile***

Specifies the name of the profile. This name can be up to 30 characters long and must be unique within the host.

- **-label *label* | -id *id***

Specifies the SnapManager operation ID or label for which you want to view the history.

- **-quiet**

Displays only error messages on the console. The default is to display error and warning messages.

- **-verbose**

Displays error, warning, and informational messages on the console.

Example command

```
  smsap history operation-show -profile PROFILE1 -label backup1 -verbose
```

The smsap history purge command

This command enables you to delete the history of SnapManager operation.

Syntax

```
smsap history purge
-profile {-name profile_name [profile_name1, profile_name2] | -all
-repository
-login [-password repo_password]
-username repo_username
-host repo_host
-dbname repo_dbname
-port repo_port}
-operation {-operations operation_name [operation_name1, operation_name2]
| -all}
[-quiet | -verbose]
```

Parameters

- **-profile *profile***

Specifies the name of the profile. This name can be up to 30 characters long and must be unique within the host.

- **-repository**

The options that follow -repository specify the details of the database that stores the profile.

- **-dbname *repo_dbname***

Specifies the name of the database that stores the profile. Use either the global name or the SID.

- **-host *repo_host***

Specifies the name or IP address of the host computer the repository database runs on.

- **-login**

Starts the repository login details.

- **-username *repo_username***

Specifies the user name needed to access the database that stores the repository.

- **-port *repo_port***

Specifies the TCP port number used to access the database that stores the repository.

- **-operation** {**-operations***operation_name* [*operation_name1*, *operation_name2*] | **-all**}

Specifies the SnapManager operation for which you configure the history.

- **-quiet**

Displays only error messages on the console. The default is to display error and warning messages.

- **-verbose**

Displays error, warning, and informational messages on the console.

Example command

```
smssap history purge -profile -name PROFILE1 -operation -operations backup  
-verbose
```

The smssap history remove command

This command enables you to remove the history of SnapManager operations associated with a single profile, multiple profiles, or all profiles under a repository.

Syntax

```
smssap history remove  
-profile {-name profile_name [profile_name1, profile_name2] | -all  
-repository  
-login [-password repo_password]  
-username repo_username  
-host repo_host  
-dbname repo_dbname  
-port repo_port}  
-operation {-operations operation_name [operation_name1, operation_name2] |  
-all}  
[-quiet | -verbose]
```

Parameters

- **-profile** *profile*

Specifies the name of the profile. This name can be up to 30 characters long and must be unique within the host.

- **-repository**

The options that follow `-repository` specify the details of the database that stores the profile.

- **`-dbname repo_dbname`**

Specifies the name of the database that stores the profile. Use either the global name or the SID.

- **`-host repo_host`**

Specifies the name or IP address of the host computer the repository database runs on.

- **`-login`**

Starts the repository login details.

- **`-username repo_username`**

Specifies the user name needed to access the database that stores the repository.

- **`-port repo_port`**

Specifies the TCP port number used to access the database that stores the repository.

- **`-operation {-operations operation_name [operation_name1, operation_name2] | -all}`**

Specifies the SnapManager operation for which you configure the history.

- **`-quiet`**

Displays only error messages on the console. The default is to display error and warning messages.

- **`-verbose`**

Displays error, warning, and informational messages on the console.

Example command

```
smsap history purge -profile -name PROFILE1 -operation -operations backup  
-verbose
```

The smsap history set command

You can run the `history set` command to configure the operations for which you want to view the history.

Syntax

```
smsap history set
-profile {-name profile_name [profile_name1, profile_name2] | -all
-repository
-login [password repo_password]
-username repo_username
-host repo_host
-database repo_dbname
-port repo_port}
-operation {-operations operation_name [operation_name1, operation_name2]
| -all}
-retain
{-count retain_count | -daily daily_count | -monthly monthly_count |
-weekly weekly_count}
[-quiet | -verbose]
```

Parameters

- **-profile profile**

Specifies the name of the profile. The name can be up to 30 characters long and must be unique within the host.

- **-repository**

Specifies the details of the database that stores the profile.

- **-dbname repo_dbname**

Specifies the name of the database that stores the profile. You can use either the global name or the system identifier.

- **-host repo_host**

Specifies the name or IP address of the host where the repository database resides.

- **-login**

Specifies the repository login details.

- **-username repo_username**

Specifies the user name required to access the repository database.

- **-port repo_port**

Specifies the Transmission Control Protocol (TCP) port number used to access the repository database.

- **-operation {-operations operation_name [operation_name1, operation_name2] | -all}**

Specifies the SnapManager operations for which you want to configure the history.

- **-retain {-countretain_count | -dailydaily_count | -monthlymonthly_count | -weeklyweekly_count}**

Specifies the retention class of the create backup, verify backup, restore and recover, and create clone operations. The retention class is set based on the operation count number, number of days, weeks, or months.

- **-quiet**

Displays only error messages in the console. The default is to display error and warning messages.

- **-verbose**

Displays error, warning, and informational messages in the console.

Example command

The following example displays information about the backup operation:

```
  smsap history set -profile -name PROFILE1 -operation -operations backup  
  -retain -daily 6  
  -verbose
```

The smsap history show command

This command enables you to view a detailed history information for a specific profile.

Syntax

```
  smsap history show  
  -profile profile
```

Parameters

- **-profile profile**

Specifies the name of the profile. This name can be up to 30 characters long and must be unique within the host.

- **-quiet**

Displays only error messages on the console. The default is to display error and warning messages.

- **-verbose**

Displays error, warning, and informational messages on the console.

Example command

```
smsap history show -profile -name PROFILE1  
-verbose
```

The smsap help command

You can run the `help` command to display information about the SnapManager commands and their options. If you do not supply a command name, it displays a list of valid commands. If you supply a command name, it displays the syntax for that command.

Syntax

```
smsap help  
[] [backup|cmdfile|clone|credential|help|operation|profile|repository|system|version|plugin|diag|history|schedule|notification|storage|get]  
[-quiet | -verbose]
```

Parameters

The following are some command names you can use with this command:

- `backup`
- `clone`
- `cmdfile`
- `credential`
- `diag`
- `get`
- `notification`
- `help`
- `history`
- `operation`
- `plugin`
- `profile`
- `repository`
- `schedule`
- `storage`

- system
- version

The smsap notification remove-summary-notification command

This command disables summary notification for multiple profiles on a repository database.

Syntax

```
smsap notification remove-summary-notification
-repository
-database repo_service_name
-port repo_port
-host repo_host
-login -username repo_username
[-quiet | -verbose]
```

Parameters

- **-repository**

The options that follow **-repository** specify the details of the database for the repository.

- **-port repo_port**

Specifies the TCP port number used to access the database that stores the repository.

- **-dbname repo_service_name**

Specifies the name of the database that stores the repository. Use either the global name or the SID.

- **-host repo_host**

Specifies the name or IP address of the host computer the repository database runs on.

- **-login repo_username**

Specifies the login name needed to access the database that stores the repository.

- **-quiet**

Displays only error messages on the console. The default is to display error and warning messages.

- **-verbose**

Displays error, warning, and informational messages on the console.

The following example disables summary notification for multiple profiles on a repository database.

```
smssp notification remove-summary-notification -repository -port 1521  
-dbname repo2 -host 10.72.197.133 -login -username oba5
```

The **smssp notification update-summary-notification** command

You can run the **notification update-summary-notification** command to enable summary notification for a repository database.

Syntax

```
smssp notification update-summary-notification  
-repository  
-port repo_port  
-dbname repo_service_name  
-host repo_host  
-login -username repo_username  
-email email-address1,email-address2  
-subject subject-pattern  
-frequency  
[-daily -time daily_time |  
-hourly -time hourly_time |  
-monthly -time monthly_time -date [1|2|3|...|31] |  
-weekly -time weekly_time -day [1|2|3|4|5|6|7]]  
-profiles profile1,profile2  
-notification-host notification-host  
[-quiet | -verbose]
```

Parameters

- **-repository**

Specifies the details of the repository database.

- **-port repo_port**

Specifies the TCP port number used to access the repository database.

- **-dbname repo_service_name**

Specifies the name of the repository database. You can use either the global name or the system identifier.

- **-host repo_host**

Specifies the name or IP address of the host on which the repository database resides.

- **-login**

Specifies the repository login details. This is optional. If not specified, SnapManager defaults to OS Authentication Connection Mode.

- **-username *repo_username***

Specifies the user name required to access the repository database.

- **-email *email-address1*,*e-mail-address2***

Specifies email addresses of the recipients.

- **-subject *subject-pattern***

Specifies the email subject pattern.

- **-frequency { -daily --time *daily_time* | -hourly --time *hourly_time* | -monthly --time *monthly_time* -date {1|2|3...|31} | -weekly --time *weekly_time* -day {1|2|3|4|5|6|7} }**

Specifies schedule type and schedule time when you want the email notification.

- **-profiles *profile1*, *profile2***

Specifies profile names that require email notification.

- **-notification-host *notification-host***

Specifies SnapManager server host from which the summary notification email is sent to the recipients. You can provide host name, or IP address for the notification host. You can also update the host IP or host name.

- **-quiet**

Displays only error messages in the console. The default is to display error and warning messages.

- **-verbose**

Displays error, warning, and informational messages in the console.

Example

The following example enables summary notification for a repository database:

```
smasap notification update-summary-notification -repository -port 1521
-dbname repo2 -host 10.72.197.133 -login -username oba5 -email
admin@org.com -subject success -frequency -daily -time 19:30:45 -profiles
sales1
```

The smsap notification set command

You can use the `notification set` command to configure the mail server.

Syntax

```
smsap notification set
-sender-email email_address
-mailhost mailhost
-mailport mailport
[-authentication
-username username
-password password]
getRepository
-dbname repo_service_name
-port repo_port]
-host repo_host
-login -username repo_username
[-quiet | -verbose]
```

Parameters

- **-sender-email *email_address***

Specifies the sender's email address from which the email alerts are sent. From SnapManager 3.2 for SAP, you can include a hyphen (-) while specifying the domain name of the email address. For example, you can specify the sender email address as `-sender-email071bfmdatacenter@continental-corporation.com`.

- **-mailhost *mailhost***

Specifies the name or IP address of the host server that handles email notifications.

- **-mailport *mailport***

Specifies the mail server port number.

- **-authentication -username *username* -password *password***

Specifies authentication details for the email address. You must specify the user name and password.

- **-repository**

Specifies the details of the repository database.

- **-port *repo_port***

Specifies the Transmission Control Protocol (TCP) port number used to access the repository database.

- **-dbname *repo_service_name***

Specifies the name of the repository database. You can use either the global name or the system identifier.

- **-host *repo_host***

Specifies the name or IP address of the host where the repository database resides.

- **-login**

Specifies the repository login details. This is optional. If not specified, SnapManager defaults to OS Authentication Connection Mode.

- **-username *repo_username***

Specifies the user name required to access the repository database.

- **-quiet**

Displays only error messages in the console. The default is to display error and warning messages.

- **-verbose**

Displays error, warning, and informational messages in the console.

Example

The following example configures the mail server:

```
smsap notification set -sender-email admin@org.com -mailhost
hostname.org.com -mailport 25 authentication -username davis -password
davis -repository -port 1521 -dbname SMSAPREPO -host hotspur
-login -username grabal21 -verbose
```

The smsap operation dump command

You can run the `operation dump` command to create a JAR file that contains diagnostic information about an operation.

Syntax

```
smsap operation dump
-profile profile_name
[-label label_name | -id guid]
[-quiet | -verbose]
```

Parameters

- **-profile *profile_name***

Specifies the profile for which you want to create the dump files. The profile contains the identifier of the database and other database information.

- **-label *label_name***

Creates dump files for the operation and assigns the specified label.

- **-id *guid***

Creates dump files for the operation with the specified GUID. The GUID is generated by SnapManager when the operation begins.

- **-quiet**

Displays only error messages in the console. The default is to display error and warning messages.

- **-verbose**

Displays error, warning, and informational messages in the console.

Example

The following example creates the dump file for the backup:

```
smsap operation dump -profile SALES1  
-id 8abc01ec0e78f3e2010e78f3fdd00001
```

```
Dump file created Path:  
C:\userhomedirectory\netapp\smsap\3.3\smsap_dump_8abc01ec0e78f3e2010e78f3fdd00001.jar
```

The smsap operation list command

This command lists the summary information of all operations recorded against a specified profile.

Syntax

```
smsap operation list  
-profile profile_name  
[-delimiter character]  
[-quiet | -verbose]
```

Parameters

- **-profile *profile_name***

Specifies the name of the profile. This name can be up to 30 characters long and must be unique within the host.

- **-delimiter *character***

(Optional) When this parameter is specified, the command lists each row on a separate line and the attributes in that row are separated by the character specified.

- **-quiet**

(Optional) Displays only error messages on the console. The default is to display error and warning messages.

- **-verbose**

(Optional) Displays error, warning, and informational messages on the console.

Example command

The following example lists the summary information of all the operations logged against the specified profile.

```
smssap operation list -profile myprofile
```

Start	Date	Status	Operation	ID	Type	Host
2007-07-16	16:03:57	SUCCESS	8abc01c813d0a1530113d0a15c5f0005	Profile Create	Host3	Profile
2007-07-16	16:04:55	FAILED	8abc01c813d0a2370113d0a241230001	Backup	Host3	Backup
2007-07-16	16:50:56	SUCCESS	8abc01c813d0cc580113d0cc60ad0001	Profile Update	Host3	Profile
2007-07-30	15:44:30	SUCCESS	8abc01c81418a88e011418a8973e0001	Remove Backup	Host3	Remove Backup
2007-08-10	14:31:27	SUCCESS	8abc01c814510ba20114510bac320001	Backup	Host3	Backup
2007-08-10	14:34:43	SUCCESS	8abc01c814510e9f0114510ea98f0001	Mount	Host3	Mount
2007-08-10	14:51:59	SUCCESS	8abc01c814511e6e0114511e78d40001	Unmount	Host3	Unmount

The smssap operation show command

You can run the `operation show` command to list the summary information of all the operations performed against the specified profile. The output lists the client user (the user for the client PC) and the effective user (the user in SnapManager who is valid on

the selected host).

Syntax

```
smsap operation show
-profile profile_name
[-label label | -id id]
[-quiet | -verbose]
```

Parameters

- **-profile profile_name**

Specifies the name of the profile. This name can be up to 30 characters long and must be unique within the host.

- **-label label**

Specifies the label for the operation.

- **-id id**

Specifies the identifier for the operation.

- **-quiet**

Optional: Displays only error messages in the console. The default is to display error and warning messages.

- **-verbose**

Optional: Displays error, warning, and informational messages in the console.

Example

The following command line shows detailed information about an operation:

```
smsap operation show -id 8ac861781d0ac992011d0ac999680001 -profile CER
```

The smsap password reset command

You can run the `password reset` command to reset the password of a profile.

Syntax

```
  smsap password reset
  -profile profile
  [-profile-password profile_password]
  [-repository-hostadmin-password repository_hostadmin_password]
  [-quiet | -verbose]
```

Parameters

- **-profile profile**

Specifies the name of the profile for which you want to reset the password.

- **-profile-password profile_password**

Specifies the new password for the profile.

- **-repository-hostadmin-password admin_password**

Specifies the authorized user credential with local administrator privilege for the repository database.

- **-quiet**

Displays only error messages in the console. The default is to display error and warning messages.

- **-verbose**

Displays error, warning, and informational messages in the console.

The smsap profile create command

You can run the `profile create` command to create a profile of a database in a repository. You must mount the database before you run this command.

Syntax

```
  smsap profile create
  -profile profile
  [-profile-password profile_password]
  -repository
  -dbname repo_service_name
  -host repo_host
  -port repo_port
  -login -username repo_username
  -database
  -dbname db_dbname
  -host db_host
```

```

[-sid db_sid]
[-login
[-username db_username -password db_password -port db_port]
]
[-rman {-controlfile | {-login
-username rman_username -password rman_password}
-tnsname rman_tnsname}}]

[-retain
[-hourly [-count n] [-duration m]]
[-daily [-count n] [-duration m]]
[-weekly [-count n] [-duration m]]
[-monthly [-count n] [-duration m]]]
-comment comment
-snapname-pattern pattern
[]
[-summary-notification]
[-notification
[-success
-email email_address1,email_address2
-subject subject_pattern]
[-failure
-email email_address1,email_address2
-subject subject_pattern]
[-separate-archivelog-backups
-retain-archivelog-backups
-hours hours |
-days days |
-weeks weeks |
-months months
[]
[-include-with-online-backups | -no-include-with-online-backups]]
[-dump]
[-quiet | -verbose]

```

Parameters

- **-profile *profile***

Specifies the name of the profile. This name can be up to 30 characters long and must be unique within the host.

- **-profile-password *profile_password***

Specify the password for the profile.

- **-repository**

The options that follow `-repository` specify the details of the database that stores the profile.

- **-dbname *repo_service_name***

Specifies the name of the database that stores the profile. Use either the global name or the SID.

- **-host *repo_host***

Specifies the name or IP address of the host computer the repository database runs on.

- **-sid *db_sid***

Specifies the system identifier of the database that the profile describes. By default, SnapManager uses the database name as the system identifier. If the system identifier is different from the database name, you must specify it with the `-sid` option.

- **-login**

Specifies the repository login details.

- **-username *repo_username***

Specifies the user name needed to access the repository database.

- **-port *repo_port***

Specifies the TCP port number used to access the repository database.

- **-database**

Specifies the details of the database that the profile describes. This is the database that will be backed up, restored, or cloned.

- **-dbname *db_dbname***

Specifies the name of the database that the profile describes. You can use either the global name or the system identifier.

- **-host *db_host db_host***

Specifies the name or IP address of the host computer on which the database runs.

- **-login**

Specifies the database login details.

- **-username *db_username***

Specifies the user name needed to access the database that the profile describes.

- **-password *db_password***

Specifies the password needed to access the database that the profile describes.

- **-port *db_port***

Specifies the TCP port number used to access the database that the profile describes.

- **-retain [-hourly [-count *n*] [-duration *m*]] [-daily [-count *n*] [-duration *m*]] [-weekly [-count *n*] [-duration *m*]] [-monthly [-count *n*] [-duration *m*]]**

Specifies the retention policy for a backup where either or both of a retention count along with a retention duration for a retention class (hourly, daily, weekly, monthly).

For each retention class, either or both of a retention count or a retention duration may be specified. The duration is in units of the class (for example, hours for hourly, days for daily). For instance, if the user specifies only a retention duration of 7 for daily backups, then SnapManager will not limit the number of daily backups for the profile (because the retention count is 0), but SnapManager will automatically delete daily backups created over 7 days ago.

- **-comment *comment***

Specifies the comment for a profile describing the profile domain.

- **-snapname-pattern *pattern***

Specifies the naming pattern for Snapshot copies. You can also include custom text, for example, HAOPS for highly available operations, in all Snapshot copy names. You can change the Snapshot copy naming pattern when you create a profile or after the profile has been created. The updated pattern applies only to Snapshot copies that have not yet been created. Snapshot copies that exist retain the previous Snapname pattern. You can use several variables in the pattern text.

- **-summary-notification**

Specifies that summary email notification is enabled for the new profile.

- **-notification -success-email *e-mail_address1, e-mail_address2* -subject *subject_pattern***

Specifies that email notification is enabled for the new profile so that emails are received by recipients when the SnapManager operation succeeds. You must enter a single email address or multiple email addresses to which email alerts will be sent and an email subject pattern for the new profile.

You can also include custom subject text for the new profile. You can change the subject text when you create a profile or after the profile has been created. The updated subject applies only to the emails that are not sent. You can use several variables for the email subject.

- **-notification -failure -email *e-mail_address1, e-mail_address2* -subject *subject_pattern***

Specifies that enable email notification is enabled for the new profile so that emails are received by recipients when the SnapManager operation fails. You must enter a single email address or multiple email addresses to which email alerts will be sent and an email subject pattern for the new profile.

You can also include custom subject text for the new profile. You can change the subject text when you create a profile or after the profile has been created. The updated subject applies only to the emails that are not sent. You can use several variables for the email subject.

- **-separate-archivelog-backups**

Specifies that the archive log backup is separated from datafile backup. This is an optional parameter you can provide while creating the profile. After you separate the backup using this option, you can either take data files-only backup or archive logs-only backup.

- **-retain-archivelog-backups -hours hours | -days days | -weeks weeks | -months months**

Specifies that the archive log backups are retained based on the archive log retention duration (hourly, daily, weekly, monthly).

- **-quiet**

Displays only error messages in the console. The default is to display error and warning messages.

- **-verbose**

Displays error, warning, and informational messages in the console.

- **-include-with-online-backups**

Specifies that the archive log backup is included along with the online database backup.

- **-no-include-with-online-backups**

Specifies that the archive log backups are not included along with the online database backup.

- **-dump**

Specifies that the dump files are collected after the successful profile create operation.

Example

The following example shows the creation of a profile with hourly retention policy and email notification:

```
smsap profile create -profile test_rbac -profile-password netapp
-repository -dbname SMSAPREP -host hostname.org.com -port 1521 -login
-username smsaprep -database -dbname RACB -host saal -sid racb1 -login
-username sys -password netapp -port 1521 -rman -controlfile -retain
-hourly -count 30 -verbose
Operation Id [8abc01ec0e78ebda010e78ebe6a40005] succeeded.
```

The smsap profile delete command

You can run the `profile delete` command to delete a profile of the database.

Syntax

```
smsap profile delete
-profile profile
[-quiet | -verbose]
```

Parameters

- **-profile profile**

Specifies the profile to be deleted.

- **-quiet**

Displays only error messages in the console. The default is to display error and warning messages.

- **-verbose**

Displays error, warning, and informational messages in the console.

Example

The following example deletes the profile:

```
smsap profile delete -profile SALES1
Operation Id [Ncaf00af0242b3e8dba5c68a57a5ae932] succeeded.
```

The smsap profile dump command

You can run the `profile dump` command to create the `.jar` file that contains diagnostic information about a profile.

Syntax

```
smsap profile dump
-profile profile_name
[-quiet | -verbose]
```

Parameters

- **-profile profile_name**

Specifies the profile for which you want to create the dump files. The profile contains the identifier of the database and other database information.

- **-quiet**

Displays only error messages in the console. The default is to display error and warning messages.

- **-verbose**

Displays error, warning, and informational messages in the console.

Example

The following example creates a dump for the profile SALES1:

```
smsap profile dump -profile SALES1
Dump file created
Path:
C:\\userhomedirectory\\netapp\\smsap\\3.3.0\\smsap_dump_SALES1_hostname.ja
r
```

The smsap profile list command

This command displays a list of the current profiles.

Syntax

```
smsap profile list
[-quiet | -verbose]
```

Parameters

- **-quiet**

Displays only error messages on the console. The default is to display error and warning messages.

- **-verbose**

Displays error, warning, and informational messages on the console.

Example command

The following example displays existing profiles with their details.

```
smsap profile list -verbose
Profile name: FGTER
Repository:
Database name: SMSAPREPO
```

```
SID: SMSAPREPO
Host: hotspur
Port: 1521
Username: swagrahn
Password: *****

Profile name: TEST_RBAC
Repository:
  Database name: smsaprep
  SID: smsaprep
  Host: elbe.rtp.org.com
  Port: 1521
  Username: smsapsaal
  Password: *****

Profile name: TEST_RBAC_DP_PROTECT
Repository:
  Database name: smsaprep
  SID: smsaprep
  Host: elbe.rtp.org.com
  Port: 1521
  Username: smsapsaal
  Password: *****

Profile name: TEST_HOSTCREDEN_OFF
Repository:
  Database name: smsaprep
  SID: smsaprep
  Host: elbe.rtp.org.com
  Port: 1521
  Username: smsapsaal
  Password: *****

Profile name: SMK_PRF
Repository:
  Database name: smsaprep
  SID: smsaprep
  Host: elbe.rtp.org.com
  Port: 1521
  Username: smsapsaal
  Password: *****

Profile name: FGLEX
Repository:
  Database name: SMSAPREPO
  SID: SMSAPREPO
  Host: hotspur
  Port: 1521
  Username: swagrahn
  Password: *****
```

The smsap profile show command

You can run the `profile show` command to display the information about a profile.

Syntax

```
smsap profile show
-profile profile_name
[-quiet | -verbose]
```

Parameters

- **`-profile profile_name`**

Specifies the name of the profile. This name can be up to 30 characters long and must be unique within the host.

- **`-quiet`**

Displays only error messages in the console. The default is to display error and warning messages.

- **`-verbose`**

Displays error, warning, and informational messages in the console.

The smsap profile sync command

This command loads the profile-to-repository mappings for that repository to a file in your home directory on the local host.

Syntax

```
smsap profile sync
-repository
-dlname repo_service_name
-host repo_host
-port repo_port
-login
-username repo_username
[-quiet | -verbose]
```

Parameters

- **`-repository`**

The options that follow `-repository` specify the details of the database for the repository.

- **`-dbname repo_service_name`**

Specifies the repository database for the profile to synchronize.

- **`-host`**

Specifies the database host.

- **`-port`**

Specifies the port for the host.

- **`-login`**

Specifies the log in process for the host user.

- **`-username`**

Specifies the username for the host.

- **`-quiet`**

Displays only error messages on the console. The default is to display error and warning messages.

- **`-verbose`**

Displays error, warning, and informational messages on the console.

Example command

The following example shows the result of the command to synchronize the profile-to-repository mappings for the database.

```
smsap profile sync -repository -dbname smrepo -host Host2 -port 1521
-login -username user2
SMSAP-12345 [INFO ]: Loading profile mappings for repository
"user2@Host2:smrepo" into cache for OS User "admin".
Operation Id [Nff8080810da9018f010da901a0170001] succeeded.
```

The smsap profile update command

You can run the `profile update` command to update the information for an existing profile.

Syntax

```
  smsap profile update
  -profile profile
  [-new-profile new_profile_name]
  [-profile-password profile_password]
  [-database
  -dbname db_dbname
  -host db_host
  [-sid db_sid]
  [-login
  [-username db_username -password db_password -port db_port]
  ]
  [{-rman {-controlfile | {-login
  -username rman_username
  -password rman_password }
  [-tnsname tnsname]} } | -remove-rman]

  [-retain
  [-hourly [-count n] [-duration m] ]
  [-daily [-count n] [-duration m] ]
  [-weekly [-count n] [-duration m] ]
  [-monthly [-count n] [-duration m]]]
  -comment comment
  -snapname-patternpattern
  []
  [-summary-notification]
  [-notification
  -success
  -email email_address1,email_address2
  -subject subject_pattern]
  [-failure
  -email email_address1,email_address2
  -subject subject_pattern]
  [-separate-archivelog-backups
  -retain-archivelog-backups
  -hours hours |
  -days days |
  -weeks weeks |
  -months months
  []
  [-include-with-online-backups | -no-include-with-online-backups]]
  [-dump]
  [-quiet | -verbose]
```

Parameters

- **-profile *profile***

Specifies the name of the profile. This name can be up to 30 characters long and must be unique within the host.

- **-profile-password *profile_password***

Specifies the password for the profile.

- **-new-profile *new_profile_name***

Specifies the new name that you can provide for a profile.

- **-database**

Specifies the details of the database that the profile describes. This is the database that will be backed up, restored, and so on.

- **-dbname *db_dbname***

Specifies the name of the database that the profile describes. You can use either the global name or the system identifier.

- **-host *db_host***

Specifies the name or IP address of the host computer on which the database runs.

- **-sid *db_sid***

Specifies the system identifier of the database that the profile describes. By default, SnapManager uses the database name as the system identifier. If the system identifier is different from the database name, you must specify it using the **-sid** option.

- **-login**

Specifies the repository login details.

- **-username *repo_username***

Specifies the user name required to access the repository database.

- **-port *repo_port***

Specifies the TCP port number required to access the repository database.

- **-database**

Specifies the details of the database that the profile describes. This is the database that will be backed up, restored, or cloned.

- **-dbname *db_dbname***

Specifies the name of the database that the profile describes. You can use either the global name or the system identifier.

- **-host *db_host***

Specifies the name or IP address of the host computer on which the database runs.

- **-login**

Specifies the database login details.

- **-username *db_username***

Specifies the user name required to access the database that the profile describes.

- **-password *db_password***

Specifies the password required to access the database that the profile describes.

- **-port *db_port***

Specifies the TCP port number required to access the database that the profile describes.

- **-retain [-hourly [-countn] [-duration m]] [-daily [-count n] [-duration m]] [-weekly [-count n] [-duration m]] [-monthly [-count n] [-duration m]]**

Specifies the retention class (hourly, daily, weekly, monthly) for a backup.

For each retention class, a retention count or a retention duration or both can be specified. The duration is in units of the class (for example, hours for hourly or days for daily). For instance, if the user specifies only a retention duration of 7 for daily backups, then SnapManager will not limit the number of daily backups for the profile (because the retention count is 0), but SnapManager will automatically delete daily backups created over 7 days ago.

- **-comment *comment***

Specifies the comment for a profile.

- **-snapname-pattern *pattern***

Specifies the naming pattern for Snapshot copies. You can also include custom text, for example, HAOPS for highly available operations, in all Snapshot copy names. You can change the Snapshot copy naming pattern when you create a profile or after the profile has been created. The updated pattern applies only to Snapshot copies that have not yet occurred. Snapshot copies that exist retain the previous Snapname pattern. You can use several variables in the pattern text.

- **-summary-notification**

Specifies that summary email notification is enabled for the existing profile.

- **-notification [-success-email *e-mail_address1,e-mail address2 -subject subject_pattern*]**

Enables email notification for the existing profile so that emails are received by recipients when the

SnapManager operation succeeds. You must enter a single email address or multiple email addresses to which email alerts will be sent and an email subject pattern for the existing profile.

You can change the subject text while updating the profile or include custom subject text. The updated subject applies only to the emails that are not sent. You can use several variables for the email subject.

- **-notification [-failure -email *e-mail_address1,e-mail address2* -subject *subject_pattern*]**

Enables email notification for the existing profile so that emails are received by recipients when the SnapManager operation fails. You must enter a single email address or multiple email addresses to which email alerts will be sent and an email subject pattern for the existing profile.

You can change the subject text while updating the profile or include custom subject text. The updated subject applies only to the emails that are not sent. You can use several variables for the email subject.

- **-separate-archivelog-backups**

Separates the archive log backup from datafile backup. This is an optional parameter you can provide while creating the profile. After you separate the backups are separated using this option, you can create either data files-only backup or archive logs-only backup.

- **-retain-archivelog-backups -hours *hours* | -days *days* | -weeks *weeks* | -months *months***

Specifies that the archive log backups are retained based on the archive log retention duration (hourly, daily, weekly, monthly).

- **-include-with-online-backups | -no-include-with-online-backups**

Specifies that the archive log backup is included along with the online database backup.

Specifies that the archive log backups are not included along with the online database backup.

- **-dump**

Specifies that the dump files are collected after the successful profile create operation.

- **-quiet**

Displays only error messages in the console. The default is to display error and warning messages.

- **-verbose**

Displays error, warning, and informational messages in the console.

Example

The following example changes the login information for the database described by the profile and the email notification is configured for this profile:

```
smsap profile update -profile SALES1 -database -dbname SALESDB  
-sid SALESDB -login -username admin2 -password d4jPe7bw -port 1521  
-host server1 -profile-notification -success -e-mail Preston.Davis@org.com  
-subject success  
Operation Id [8abc01ec0e78ec33010e78ec3b410001] succeeded.
```

The smsap profile verify command

You can run the `profile verify` command to verify the profile set up. You must mount the database before running this command.

Syntax

```
smsap profile verify  
-profile profile_name  
[-quiet | -verbose]
```

Parameters

- **-profile**

Specifies the profile to verify. The profile contains the identifier of the database and other database information.

- **-quiet**

Displays only error messages in the console. The default is to display error and warning messages.

- **-verbose**

Displays error, warning, and informational messages in the console.

Example

The following example verifies the profile:

```
smsap profile verify -profile profileA -verbose  
[ INFO] SMSAP-13505: SnapDrive environment verification passed.  
[ INFO] SMSAP-13507: JDBC verification for "OS authenticated:  
NEWDB/hostA.rtp.com" passed.  
[ INFO] SMSAP-13506: SQLPlus verification for database SID "NEWDB" passed.  
Environment: [ORACLE_HOME=E:\app\Administrator\product\11.2.0\dbhome_1]  
[ INFO] SMSAP-07431: Saving starting state of the database:  
Database[NEWDB(OPEN)], Service[RUNNING].  
[ INFO] SMSAP-07431: Saving starting state of the database:
```

```
Database[NEWDB(OPEN)], Service[RUNNING].  
[ INFO] SD-00016: Discovering storage resources for F:\  
[ INFO] SD-00017: Finished storage discovery for F:\  
[ INFO] SD-00016: Discovering storage resources for F:\  
[ INFO] SD-00017: Finished storage discovery for F:\  
[ INFO] SD-00016: Discovering storage resources for H:\  
[ INFO] SD-00017: Finished storage discovery for H:\  
[ INFO] SD-00016: Discovering storage resources for G:\  
[ INFO] SD-00017: Finished storage discovery for G:\  
[ INFO] SD-00016: Discovering storage resources for I:\  
[ INFO] SD-00017: Finished storage discovery for I:\  
[ WARN] SMSAP-05071: Database profile HADLEY is not eligible for fast  
restore: Restore Plan:
```

Preview:

The following components will be restored completely via: host side
file copy restore

```
F:\NEWDB\SYSAUX01.DBF  
F:\NEWDB\SYSTEM01.DBF  
F:\NEWDB\UNDOTBS01.DBF  
F:\NEWDB\USERS01.DBF
```

Analysis:

The following reasons prevent certain components from being restored
completely via: storage side file system restore

* Files in file system F:\ not part of the restore scope will be
reverted.

Components not in restore scope:

```
F:\_TESTCLN\CONTROL01.CTL  
F:\_TESTCLN\REDO_1.LOG  
F:\_TESTCLN\REDO_2.LOG  
F:\_TESTCLN\REDO_3.LOG
```

Components to restore:

```
F:\NEWDB\SYSAUX01.DBF  
F:\NEWDB\SYSTEM01.DBF  
F:\NEWDB\UNDOTBS01.DBF  
F:\NEWDB\USERS01.DBF
```

* Reasons denoted with an asterisk (*) are overridable.

```
[ INFO] SMSAP-07433: Returning the database to its initial state: Database  
[NEWDB(OPEN)], Service[RUNNING].  
[ INFO] SMSAP-13048: Profile Verify Operation Status: SUCCESS  
[ INFO] SMSAP-13049: Elapsed Time: 0:19:06.949  
Operation Id [N5bc18bd5c3be27a795ce3857093a926a] succeeded.
```

The smsap repository create command

Syntax

This command creates a repository in which to store database profiles and associated credentials. This command also checks to see that the block size is adequate.

```
smsap repository create
-repository
-port repo_port
-dbname repo_service_name
-host repo_host
-login -username repo_username
[-force] [-noprompt]
[-quiet | -verbose]
```

Parameters

- **-repository**

The options that follow -repository specify the details of the database for the repository

- **-port repo_port**

Specifies the TCP port number used to access the database that stores the repository.

- **-dbname repo_service_name**

Specifies the name of the database that stores the repository. Use either the global name or the SID.

- **-host repo_host**

Specifies the name or IP address of the host computer the repository database runs on.

- **-login**

Starts the repository login details.

- **-username repo_username**

Specifies the user name needed to access the database that stores the repository.

- **-force**

Attempts to force the creation of the repository. Using this option results in SnapManager prompting you to backup the repository before creating the repository.

- **-noprompt**

Does not display the prompt to backup the repository before creating it if you use the -force option. Using

the `-noprompt` option ensures the prompt does not appear, making it easier to create repositories using a script.

- **-quiet**

Displays only error messages on the console. The default is to display error and warning messages.

- **-verbose**

Displays error, warning, and informational messages on the console.

Command example

The following example creates a repository in the database SMSAPREPO on the host hotspur.

```
smsap repository create -repository -port 1521 -dbname SMSAPREPO -host
hotspur -login -username grabal21 -verbose
SMSAP-09202 [INFO ]: Creating new schema as grabal21 on
jdbc:oracle:thin:@//hotspur:1521/SMSAPREPO.
SMSAP-09205 [INFO ]: Schema generation complete.
SMSAP-09209 [INFO ]: Performing repository version INSERT.
SMSAP-09210 [INFO ]: Repository created with version: 30
SMSAP-13037 [INFO ]: Successfully completed operation: Repository Create
SMSAP-13049 [INFO ]: Elapsed Time: 0:00:08.844
```

The smsap repository delete command

This command deletes a repository used to store database profiles and associated credentials. You can delete a repository only if there are no profiles in the repository.

Syntax

```
smsap repository delete
-repository
-port repo_port
-dbname repo_service_name
-host repo_host
-login -username repo_username
[-force] [-noprompt]
[-quiet | -verbose]
```

Parameters

- **-repository**

The options that follow `-repository` specify the details of the database for the repository.

- **`-port repo_port`**

Specifies the TCP port number used to access the database that stores the repository.

- **`-dbname repo_service_name`**

Specifies the name of the database that stores the repository. Use either the global name or the SID.

- **`-host repo_host`**

Specifies the name or IP address of the host computer the repository database runs on.

- **`-login`**

Starts the repository login details.

- **`-username repo_username`**

Specifies the user name needed to access the database that stores the repository.

- **`-force`**

Attempts to force the deletion of the repository, even if there are incomplete operations. SnapManager issues a prompt if there are incomplete operations, asking if you are sure you want to delete the repository.

- **`-noprompt`**

Does not prompt you before deleting the repository. Using the `-noprompt` option ensures the prompt does not appear, making it easier to delete repositories using a script.

- **`-quiet`**

Displays only error messages on the console. The default is to display error and warning messages.

- **`-verbose`**

Displays error, warning, and informational messages on the console.

Command example

The following example deletes the repository in the SALESDB database.

```
smsap repository delete -repository -dbname SALESDB
-host server1 -login -username admin -port 1527 -force -verbose
```

The smsap repository rollback command

This command enables you to roll back or revert from a higher version of SnapManager to the original version from which you upgraded.

Syntax

```
smssap repository rollback
-repository
-database repo_service_name
-host repo_host
-login -username repo_username
-port repo_port
-rollbackhost host_with_target_database
[-force]
[-quiet | -verbose]
```

Parameters

- **-repository**

The options that follow `-repository` specify the details of the database for the repository.

- **-dbname repo_service_name**

Specifies the name of the database that stores the repository. Use either the global name or the SID.

- **-host repo_host**

Specifies the name or IP address of the host computer the repository database runs on.

- **-login**

Starts the repository login details.

- **-username repo_username**

Specifies the user name needed to access the database that stores the repository.

- **-rollbackhost host_with_target_database**

Specifies the name of the host which will be rolled back from a higher version of SnapManager to the original lower version.

- **-port repo_port**

Specifies the TCP port number used to access the database that stores the repository.

- **-force**

Attempts to force the update of the repository. SnapManager prompts you to make a backup of the current repository before updating.

- **-noprompt**

Does not display the prompt before updating the repository database. Using the `-noprompt` option ensures the prompt does not appear, making it easier to update repositories using a script.

- **`-quiet`**

Displays only error messages on the console. The default is to display error and warning messages.

- **`-verbose`**

Displays error, warning, and informational messages on the console.

Example command

The following example updates the repository in the SALESDB database.

```
smsap repository rollback -repository -dbname SALESDB  
-host server1 -login -username admin -port 1521 -rollbackhost hostA
```

The `smsap repository rollingupgrade` command

This command performs rolling upgrade on a single host or multiple hosts and their associated target databases from a lower version of SnapManager to a higher version. The upgraded host is managed only with the higher version of SnapManager.

Syntax

```
smsap repository rollingupgrade  
-repository  
-dbname repo_service_name  
-host repo_host  
-login -username repo_username  
-port repo_port  
-upgradehost host_with_target_database  
[-force] [-noprompt]  
[-quiet | -verbose]
```

Parameters

- **`-repository`**

The options that follow `-repository` specify the details of the database for the repository.

- **`-dbname repo_service_name`**

Specifies the name of the database that stores the repository. Use either the global name or the SID.

- **-host *repo_host***

Specifies the name or IP address of the host computer the repository database runs on.

- **-login**

Starts the repository login details.

- **-username *repo_username***

Specifies the user name needed to access the database that stores the repository.

- **-upgradehost *host_with_target_database***

Specifies the name of the host which will be rolling upgraded from a lower version of SnapManager to a higher version.

- **-port *repo_port***

Specifies the TCP port number used to access the database that stores the repository.

- **-force**

Attempts to force the update of the repository. SnapManager prompts you to make a backup of the current repository before updating.

- **-noprompt**

Does not display the prompt before updating the repository database. Using the **-noprompt** option ensures the prompt does not appear, making it easier to update repositories using a script.

- **-quiet**

Displays only error messages on the console. The default is to display error and warning messages.

- **-verbose**

Displays error, warning, and informational messages on the console.

Example command

The following example updates the repository in the SALESDB database.

```
smssap repository rollingupgrade -repository -dbname SALESDB  
-host server1 -login -username admin -port 1521 -upgradehost hostA
```

The smssap repository show command

This command displays information about the repository.

Syntax

```
smssap repository show
-repository
-database repo_service_name
-host repo_host
-port repo_port
-login -username repo_username
[-quiet | -verbose]
```

Parameters

- **-repository**

The options that follow `-repository` specify the details of the database for the repository.

- **-dbname *repo_service_name***

Specifies the name of the database that stores the repository. Use either the global name or the SID.

- **-host *repo_host***

Specifies the name or IP address of the host computer the repository database runs on.

- **-login**

Starts the repository login details.

- **-username *repo_username***

Specifies the user name needed to access the database that stores the repository.

- **-port *repo_port***

Specifies the TCP port number used to access the database that stores the repository.

- **-quiet**

Displays only error messages on the console. The default is to display error and warning messages.

- **-verbose**

Displays error, warning, and informational messages on the console.

Command example

The following example shows details about the repository in the SALESDB database.

```
smsap repository show -repository -dbname SALESDB -host server1
-port 1521 -login -username admin
Repository Definition:
User Name: admin
Host Name: server1
Database Name: SALESDB
Database Port: 1521
Version: 28
Hosts that have run operations using this repository: 2
server2
server3
Profiles defined in this repository: 2
GSF5A
GSF3A
Incomplete Operations: 0
```

The smsap repository update command

This command updates the repository that stores database profiles and associated credentials when you upgrade SnapManager. Any time you install a new version of SnapManager, you must run the repository update command before you can use the new version. You are able to use this command only if there are no incomplete commands in the repository.

Syntax

```
smsap repository update
-repository
-database repo_service_name
-host repo_host
-login -username repo_username
-port repo_port
[-force] [-noprompt]
[-quiet | -verbose]
```

Parameters

- **-repository**

The options that follow `-repository` specify the details of the database for the repository.

- **-dbname *repo_service_name***

Specifies the name of the database that stores the repository. Use either the global name or the SID.

- **`-host repo_host`**

Specifies the name or IP address of the host computer the repository database runs on.

- **`-login`**

Starts the repository login details.

- **`-username repo_username`**

Specifies the user name needed to access the database that stores the repository.

- **`-port repo_port`**

Specifies the TCP port number used to access the database that stores the repository.

- **`-force`**

Attempts to force the update of the repository. SnapManager prompts you to make a backup of the current repository before updating.

- **`-noprompt`**

Does not display the prompt before updating the repository database. Using the `-noprompt` option ensures the prompt does not appear, making it easier to update repositories using a script.

- **`-quiet`**

Displays only error messages on the console. The default is to display error and warning messages.

- **`-verbose`**

Displays error, warning, and informational messages on the console.

Example command

The following example updates the repository in the SALESDB database.

```
smsap repository update -repository -dbname SALESDB  
-host server1 -login -username admin -port 1521
```

The smsap schedule create command

You can use the `schedule create` command to schedule a backup to be created at a specific time.

Syntax

```

smsap schedule create
-profile profile_name
[-full{-auto | -online | -offline}
[-retain -hourly | -daily | -weekly | -monthly | -unlimited]
[-verify]] |
[-data [[-files files [files]] |
[-tablespaces tablespaces [tablespaces]] {-auto | -online | -offline}
[-retain -hourly | -daily | -weekly | -monthly | -unlimited]
[-verify]] |
[-archivelogs}]
[-label label]
[-comment comment]

[-backup-dest path1 [ , path2]]
[-exclude-dest path1 [ , path2]]
[-prunelogs {-all | -until-scn until-scn | -until -date yyyy-MM-
dd:HH:mm:ss} | -before {-months | -days | -weeks | -hours}}
-prune-dest prune_dest1,[prune_dest2]]
-schedule-name schedule_name
[-schedule-comment schedule_comment]
-interval {-hourly | -daily | -weekly | -monthly | -onetimeonly}
-cronstring cron_string
-start-time {start_time <yyyy-MM-dd HH:mm>}
-runasuser runasuser
[-taskspec taskspec]
-force
[-quiet | -verbose]

```

Parameters

- **-profile profile_name**

Specifies the name of the profile related to the database that you want to schedule the backup for. The profile contains the identifier of the database and other database information.

- **-auto option**

If the database is in the mounted or offline state, SnapManager performs an offline backup. If the database is in the open or online state, SnapManager performs an online backup. If you use the **-force** option with the **-offline** option, SnapManager forces an offline backup even if the database is currently online.

- **-online option**

Specifies an online database backup.

- **-offline option**

Specifies an offline backup while the database is in the shutdown state. If the database is in the open or mounted state, the backup fails. If the **-force** option is used, SnapManager attempts to alter the database state to shut down the database for an offline backup.

- **-full option**

Backs up the entire database. This includes all of the data, archived log, and control files. The archived redo logs and control files are backed up no matter what type of backup you perform. If you want to back up only a portion of the database, use the **-files** option or **-tablespaces** option.

- **-files list**

Backs up only the specified data files plus the archived log and control files. Separate the list of file names with spaces. If the database is in open state, SnapManager verifies that the appropriate tablespaces are in online backup mode.

- **-tablespaces tablespaces**

Backs up only the specified database tablespaces plus the archived log and control files. Separate the tablespace names with spaces. If the database is in open state, SnapManager verifies that the appropriate tablespaces are in online backup mode.

- **-label name**

Specifies an optional name for this backup. This name must be unique within the profile. The name can contain letters, numbers, underscore (_), and hyphen (-). It cannot start with a hyphen.

If you do not specify a label, SnapManager creates a default label in the `scope_type_date` format:

- Scope is either F to indicate a full backup or P to indicate a partial backup.
- Type is C to indicate an offline (cold) backup, H to indicate an online (hot) backup, or A to indicate auto backup, for example, P_A_20081010060037IST.
- Date is the year, month, day, and time of the backup.

SnapManager uses a 24-hour clock.

For example, if you performed a full backup with the database offline on 16th January 2007, at 5:45:16 p.m. Eastern Standard Time, SnapManager would create the label F_C_20070116174516EST.

- **-comment string**

Specifies an optional comment to describe this backup. Enclose the string within single quotation marks (').



Some shells strip quotation marks off. If that is true for your shell, you must include the quotation mark with a backslash (\). For example, you might need to enter: \` this is a comment\`.

- **-verify option**

Verifies that the files in the backup are not corrupt by running the Oracle dbv utility.



If you specify the `-verify` option, the backup operation is not completed until the verify operation is complete.

- **`-force` option**

Forces a state change if the database is not in the correct state. For example, SnapManager might change the state of the database from online to offline, based on the type of backup you specify and the state that the database is in.

- If the local instance is in shutdown state and at least one instance is open, you can change the local instance to mounted by using `-force` option.
- If no instance is open, you can change the local instance to open by using `-force` option.

- **`-retain { -hourly | -daily | -weekly | -monthly | -unlimited}`**

Specifies whether the backup should be retained on an hourly, daily, weekly, monthly, or unlimited basis. If `-retain` option is not specified, the retention class defaults to `-hourly`. To retain backups forever, use the `-unlimited` option. The `-unlimited` option makes the backup ineligible for deletion by the retention policy.

- **`-archivelogs`**

Specifies creation of an archive log backup.

- **`-backup-dest path1, [, [path2]]`**

Specifies the archive log destinations for archive log backup.

- **`-exclude-dest path1, [, [path2]]`**

Specifies the archive log destinations to be excluded from the backup.

- **`-prunelogs {-all | -until-scnuntil-scn | -until-date yyyy-MM-dd:HH:mm:ss | -before {-months | -days | -weeks | -hours}}`**

Specifies whether to delete the archive log files from the archive log destinations based on options provided while creating a backup. The `-all` option deletes all of the archive log files from the archive log destinations. The `-until-scn` option deletes the archive log files until a specified system change number (SCN). The `-until-date` option deletes the archive log files until the specified time period. The `-before` option deletes the archive log files before the specified time period (days, months, weeks, hours).

- **`-schedule-name schedule_name`**

Specifies the name that you provide for the schedule.

- **`-schedule-comment schedule_comment`**

Specifies an optional comment to describe about scheduling the backup.

- **`-interval { -hourly | -daily | -weekly | -monthly | -onetimeonly}`**

Specifies the time interval by which the backups are created. You can schedule the backup on an hourly, daily, weekly, monthly, or one time only basis.

- **-cronstring *cron_string***

Specifies scheduling the backup using cronstring. Cron expressions are used to configure instances of CronTrigger. Cron expressions are strings that are made up of the following subexpressions:

- 1 refers to seconds.
- 2 refers to minutes.
- 3 refers to hours.
- 4 refers to a day in a month.
- 5 refers to the month.
- 6 refers to a day in a week.
- 7 refers to the year (optional).

- **-start-time *yyyy-MM-dd HH:mm***

Specifies the start time of the scheduled operation. The schedule start time should be included in the yyyy-MM-dd HH:mm format.

- **-runasuser *runasuser***

Specifies changing the user (root user or Oracle user) of the scheduled backup operation while scheduling the backup.

- **-taskspec *taskspec***

Specifies the task specification XML file that can be used for preprocessing activity or post-processing activity of the backup operation. The complete path of the XML file must be provided with the -taskspec option.

- **-quiet**

Displays only error messages in the console. The default is to display error and warning messages.

- **-verbose**

Displays error, warning, and informational messages in the console.

The smsap schedule delete command

This command deletes a backup schedule when it is no longer necessary.

Syntax

```
smsap schedule delete
-profile profile_name
-schedule-name schedule_name
[-quiet | -verbose]
```

Parameters

- **-profile *profile_name***

Specifies the name of the profile related to the database you want to delete a backup schedule. The profile contains the identifier of the database and other database information.

- **-schedule-name *schedule_name***

Specifies the schedule name you provided while creating a backup schedule.

The smsap schedule list command

This command lists the scheduled operations associated with a profile.

Syntax

```
smsap schedule list
-profile profile_name
[-quiet | -verbose]
```

Parameters

- **-profile *profile_name***

Specifies the name of the profile related to the database, using which you can view a list of scheduled operations. The profile contains the identifier of the database and other database information.

The smsap schedule resume command

This command resumes the suspended backup schedule.

Syntax

```
smsap schedule resume
-profile profile_name
-schedule-name schedule_name
[-quiet | -verbose]
```

Parameters

- **-profile *profile_name***

Specifies the name of the profile related to the database you want to resume the suspended backup schedule. The profile contains the identifier of the database and other database information.

- **-schedule-name *schedule_name***

Specifies the schedule name you provided while creating a backup schedule.

The smsap schedule suspend command

This command suspends a backup schedule until the backup schedule is resumed.

Syntax

```
smsap schedule suspend
-profile profile_name
-schedule-name schedule_name
[-quiet | -verbose]
```

Parameters

- **-profile *profile_name***

Specifies the name of the profile related to the database you want to suspend a backup schedule. The profile contains the identifier of the database and other database information.

- **-schedule-name *schedule_name***

Specifies the schedule name you provided while creating a backup schedule.

The smsap schedule update command

This command updates the schedule for a backup.

Syntax

```
smsap schedule update
-profile profile_name
-schedule-name schedule_name
[-schedule-comment schedule_comment]
-interval {-hourly | -daily | -weekly | -monthly | -onetimeonly}
-cronstring cron_string
-start-time {start_time <yyyy-MM-dd HH:mm>}
-runasuser runasuser
[-taskspec taskspec]
-force
[-quiet | -verbose]
```

Parameters

- **-profile *profile_name***

Specifies the name of the profile related to the database you want to schedule the back up. The profile contains the identifier of the database and other database information.

- **-schedule-name *schedule_name***

Specifies the name that you provide for the schedule.

- **-schedule-comment *schedule_comment***

Specifies an optional comment to describe about scheduling the backup.

- **-interval { -hourly | -daily | -weekly | -monthly | -onetimeonly}**

Indicates the time interval by which the backups are created. You can schedule the backup on an hourly, daily, weekly, monthly, or one time only.

- **-cronstring *cron_string***

Specifies to schedule the backup using cronstring. Cron expressions are used to configure instances of CronTrigger. Cron expressions are strings that are actually made up of seven sub-expressions:

- 1 refers to seconds
- 2 refers to minutes
- 3 refers to hours
- 4 refers to a day in a month
- 5 refers to the month
- 6 refers to a day in a week
- 7 refers to the year (optional)

- **-start-time *yyyy-MM-dd HH:mm***

Specifies the start time of the schedule operation. The schedule start time should be included in the format of yyyy-MM-dd HH:mm.

- **-runasuser *runasuser***

Specifies to change the user of the scheduled backup operation while scheduling the backup.

- **-taskspec *taskspec***

Specifies the task specification XML file that can be used for pre-processing activity or post-processing activity of the backup operation. The complete path of the XML file should be provided which give the -taskspec option.

The smsap storage list command

You can run the `storage list` command to display the list of storage systems associated with a particular profile.

Syntax

```
smsap storage list
-profile profile
```

Parameters

- **`-profile profile`**

Specifies the name of the profile. The name can be up to 30 characters long and must be unique within the host.

Example

The following example displays the storage systems associated with the profile `mjullian`:

```
smsap storage list -profile mjullian
```

Sample Output:

Storage Controllers

FAS3020-RTP07OLD

The smsap storage rename command

This command updates the name or IP address of the storage system.

Syntax

```
smsap storage rename
-profile profile
-oldname old_storage_name
-newname new_storage_name
[-quiet | -verbose]
```

Parameters

- **-profile *profile***

Specifies the name of the profile. This name can be up to 30 characters long and must be unique within the host.

- **-oldname *old_storage_name***

Specifies the IP address or name of the storage system before the storage system is renamed. You must enter the IP address or name of the storage system that is displayed when you run the `smsap storage list` command.

- **-newname *new_storage_name***

Specifies the IP address or name of the storage system after the storage system is renamed.

- **-quiet**

Displays only error messages in the console. The default is to display error and warning messages.

- **-verbose**

Displays error, warning, and informational messages in the console.

Example

The following example uses the `smsap storage rename` command to rename the storage system:

```
smsap storage rename -profile mjullian -oldname lech -newname hudson  
-verbose
```

The `smsap system dump` command

You can run the `system dump` command to create a JAR file that contains diagnostic information about the server environment.

Syntax

```
smsap system dump  
[-quiet | -verbose]
```

Parameters

- **-quiet**

Displays only error messages in the console. The default is to display error and warning messages.

- **-verbose**

Displays error, warning, and informational messages in the console.

Example of the system dump command

The following example uses the `smsap system dump` command to create a JAR file:

```
smsap system dump
Path: C:\\userhomedirectory\\netapp\\smsap\\3.3.0\\smsap_dump_hostname.jar
```

The smsap system verify command

This command confirms that all the components of the environment required to run SnapManager are set up correctly.

Syntax

```
smsap system verify
[-quiet | -verbose]
```

Parameters

- **-quiet**

Displays only error messages on the console. The default is to display error and warning messages.

- **-verbose**

Displays error, warning, and informational messages on the console.

Example of the system verify command

The following example uses the `smsap system verify` command.

```
smsap system verify
SMSAP-13505 [INFO ]: Snapdrive verify passed.
SMSAP-13037 [INFO ]: Successfully completed operation: System Verify
SMSAP-13049 [INFO ]: Elapsed Time: 0:00:00.559
Operation Id [N4f4e910004b36cfec74c710de02e44] succeeded.
```

The smsap version command

You can run the `version` command to determine which version of SnapManager you are running on your local host.

Syntax

```
smsap version  
[-quiet | -verbose]
```

Parameters

- **-quiet**

Displays only error messages in the console. The default is to display error and warning messages.

- **-verbose**

Displays the build date and contents of each profile. Also displays error, warning, and informational messages in the console.

Example of the version command

The following example displays the version of the SnapManager:

```
smsap version  
SnapManager for SAP Version: 3.3.1
```

Copyright information

Copyright © 2025 NetApp, Inc. All Rights Reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means—graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system—with prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

LIMITED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (b)(3) of the Rights in Technical Data -Noncommercial Items at DFARS 252.227-7013 (FEB 2014) and FAR 52.227-19 (DEC 2007).

Data contained herein pertains to a commercial product and/or commercial service (as defined in FAR 2.101) and is proprietary to NetApp, Inc. All NetApp technical data and computer software provided under this Agreement is commercial in nature and developed solely at private expense. The U.S. Government has a non-exclusive, non-transferrable, nonsublicensable, worldwide, limited irrevocable license to use the Data only in connection with and in support of the U.S. Government contract under which the Data was delivered. Except as provided herein, the Data may not be used, disclosed, reproduced, modified, performed, or displayed without the prior written approval of NetApp, Inc. United States Government license rights for the Department of Defense are limited to those rights identified in DFARS clause 252.227-7015(b) (FEB 2014).

Trademark information

NETAPP, the NETAPP logo, and the marks listed at <http://www.netapp.com/TM> are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.