



Google Cloud NetApp Volumes

Trident

NetApp
January 15, 2026

This PDF was generated from <https://docs.netapp.com/us-en/trident-2506/trident-use/gcnv.html> on January 15, 2026. Always check docs.netapp.com for the latest.

Table of Contents

- Google Cloud NetApp Volumes 1
 - Configure a Google Cloud NetApp Volumes backend 1
 - Google Cloud NetApp Volumes driver details 1
 - Cloud identity for GKE 1
 - Prepare to configure a Google Cloud NetApp Volumes backend 3
 - Prerequisites for NFS volumes 3
 - Google Cloud NetApp Volumes backend configuration options and examples 3
 - Backend configuration options 3
 - Volume provisioning options 5
 - Example configurations 5
 - What's next? 13
 - Storage class definitions 14

Google Cloud NetApp Volumes

Configure a Google Cloud NetApp Volumes backend

You can now configure Google Cloud NetApp Volumes as the backend for Trident. You can attach NFS and SMB volumes using a Google Cloud NetApp Volumes backend.

Google Cloud NetApp Volumes driver details

Trident provides the `google-cloud-netapp-volumes` driver to communicate with the cluster. Supported access modes are: *ReadWriteOnce* (RWO), *ReadOnlyMany* (ROX), *ReadWriteMany* (RWX), *ReadWriteOncePod* (RWOP).

Driver	Protocol	volumeMode	Access modes supported	File systems supported
<code>google-cloud-netapp-volumes</code>	NFS SMB	Filesystem	RWO, ROX, RWX, RWOP	<code>nfs</code> , <code>smb</code>

Cloud identity for GKE

Cloud identity enables Kubernetes pods to access Google Cloud resources by authenticating as a workload identity instead of by providing explicit Google Cloud credentials.

To take advantage of cloud identity in Google Cloud, you must have:

- A Kubernetes cluster deployed using GKE.
- Workload identity configured on the GKE cluster and GKE MetaData Server configured on the node pools.
- A GCP Service account with the Google Cloud NetApp Volumes Admin (`roles/netapp.admin`) role or a custom role.
- Trident installed that includes the `cloudProvider` to specify "GCP" and `cloudIdentity` specifying the new GCP service account. An example is given below.

Trident operator

To install Trident using the Trident operator, edit `tridentorchestrator_cr.yaml` to set `cloudProvider` to "GCP" and set `cloudIdentity` to `iam.gke.io/gcp-service-account: cloudvolumes-admin-sa@mygcpproject.iam.gserviceaccount.com`.

For example:

```
apiVersion: trident.netapp.io/v1
kind: TridentOrchestrator
metadata:
  name: trident
spec:
  debug: true
  namespace: trident
  imagePullPolicy: IfNotPresent
  cloudProvider: "GCP"
  cloudIdentity: 'iam.gke.io/gcp-service-account: cloudvolumes-
admin-sa@mygcpproject.iam.gserviceaccount.com'
```

Helm

Set the values for **cloud-provider (CP)** and **cloud-identity (CI)** flags using the following environment variables:

```
export CP="GCP"
export ANNOTATION="'iam.gke.io/gcp-service-account: cloudvolumes-admin-
sa@mygcpproject.iam.gserviceaccount.com'"
```

The following example installs Trident and sets `cloudProvider` to GCP using the environment variable `$CP` and sets the `cloudIdentity` using the environment variable `$ANNOTATION`:

```
helm install trident trident-operator-100.6.0.tgz --set
cloudProvider=$CP --set cloudIdentity="$ANNOTATION"
```

`tridentctl`

Set the values for **cloud provider** and **cloud identity** flags using the following environment variables:

```
export CP="GCP"
export ANNOTATION="'iam.gke.io/gcp-service-account: cloudvolumes-admin-
sa@mygcpproject.iam.gserviceaccount.com'"
```

The following example installs Trident and sets the `cloud-provider` flag to `$CP`, and `cloud-identity` to `$ANNOTATION`:

```
tridentctl install --cloud-provider=$CP --cloud
-identity="$ANNOTATION" -n trident
```

Prepare to configure a Google Cloud NetApp Volumes backend

Before you can configure your Google Cloud NetApp Volumes backend, you need to ensure the following requirements are met.

Prerequisites for NFS volumes

If you are using Google Cloud NetApp Volumes for the first time or in a new location, some initial configuration is required to set up Google Cloud NetApp Volumes and create an NFS volume. Refer to [Before you begin](#).

Ensure that you have the following before configuring Google Cloud NetApp Volumes backend:

- A Google Cloud account configured with Google Cloud NetApp Volumes service. Refer to [Google Cloud NetApp Volumes](#).
- Project number of your Google Cloud account. Refer to [Identifying projects](#).
- A Google Cloud service account with the NetApp Volumes Admin (`roles/netapp.admin`) role. Refer to [Identity and Access Management roles and permissions](#).
- API key file for your GCNV account. Refer to [Create a service account key](#)
- A storage pool. Refer to [Storage pools overview](#).

For more information about how to set up access to Google Cloud NetApp Volumes, refer to [Set up access to Google Cloud NetApp Volumes](#).

Google Cloud NetApp Volumes backend configuration options and examples

Learn about backend configuration options for Google Cloud NetApp Volumes and review configuration examples.

Backend configuration options

Each backend provisions volumes in a single Google Cloud region. To create volumes in other regions, you can define additional backends.

Parameter	Description	Default
version		Always 1

Parameter	Description	Default
storageDriverName	Name of the storage driver	The value of storageDriverName must be specified as "google-cloud-netapp-volumes".
backendName	(Optional) Custom name of the storage backend	Driver name + "_" + part of API key
storagePools	Optional parameter used to specify storage pools for volume creation.	
projectNumber	Google Cloud account project number. The value is found on the Google Cloud portal home page.	
location	The Google Cloud location where Trident creates GCNV volumes. When creating cross-region Kubernetes clusters, volumes created in a location can be used in workloads scheduled on nodes across multiple Google Cloud regions. Cross-region traffic incurs an additional cost.	
apiKey	API key for the Google Cloud service account with the netapp.admin role. It includes the JSON-formatted contents of a Google Cloud service account's private key file (copied verbatim into the backend configuration file). The apiKey must include key-value pairs for the following keys: type, project_id, client_email, client_id, auth_uri, token_uri, auth_provider_x509_cert_url, and client_x509_cert_url.	
nfsMountOptions	Fine-grained control of NFS mount options.	"nfsvers=3"
limitVolumeSize	Fail provisioning if the requested volume size is above this value.	"" (not enforced by default)
serviceLevel	The service level of a storage pool and its volumes. The values are flex, standard, premium, or extreme.	
labels	Set of arbitrary JSON-formatted labels to apply on volumes	""
network	Google Cloud network used for GCNV volumes.	
debugTraceFlags	Debug flags to use when troubleshooting. Example, {"api":false, "method":true}. Do not use this unless you are troubleshooting and require a detailed log dump.	null

Parameter	Description	Default
<code>nasType</code>	Configure NFS or SMB volumes creation. Options are <code>nfs</code> , <code>smb</code> or <code>null</code> . Setting to <code>null</code> defaults to NFS volumes.	<code>nfs</code>
<code>supportedTopologies</code>	Represents a list of regions and zones that are supported by this backend. For more information, refer to Use CSI Topology . For example: <code>supportedTopologies:</code> - <code>topology.kubernetes.io/region: asia-east1</code> <code>topology.kubernetes.io/zone: asia-east1-a</code>	

Volume provisioning options

You can control default volume provisioning in the `defaults` section of the configuration file.

Parameter	Description	Default
<code>exportRule</code>	The export rules for new volumes. Must be a comma-separated list of any combination of IPv4 addresses.	<code>"0.0.0.0/0"</code>
<code>snapshotDir</code>	Access to the <code>.snapshot</code> directory	<code>"true"</code> for NFSv4 <code>"false"</code> for NFSv3
<code>snapshotReserve</code>	Percentage of volume reserved for snapshots	<code>""</code> (accept default of 0)
<code>unixPermissions</code>	The unix permissions of new volumes (4 octal digits).	<code>""</code>

Example configurations

The following examples show basic configurations that leave most parameters to default. This is the easiest way to define a backend.

Minimal configuration

This is the absolute minimum backend configuration. With this configuration, Trident discovers all of your storage pools delegated to Google Cloud NetApp Volumes in the configured location, and places new volumes on one of those pools randomly. Because `nasType` is omitted, the `nfs` default applies and the backend will provision for NFS volumes.

This configuration is ideal when you are just getting started with Google Cloud NetApp Volumes and trying things out, but in practice you will most likely need to provide additional scoping for the volumes you provision.

```

---
apiVersion: v1
kind: Secret
metadata:
  name: backend-tbc-gcnv-secret
type: Opaque
stringData:
  private_key_id: f2cb6ed6d7cc10c453f7d3406fc700c5df0ab9ec
  private_key: |
    -----BEGIN PRIVATE KEY-----\n
    znHczZsrtrHisIsAbOguSaPIKeyAZNchRAGz1zZE4jK3bl/qp8B4Kws8zX5ojY9m\n
    znHczZsrtrHisIsAbOguSaPIKeyAZNchRAGz1zZE4jK3bl/qp8B4Kws8zX5ojY9m\n
    znHczZsrtrHisIsAbOguSaPIKeyAZNchRAGz1zZE4jK3bl/qp8B4Kws8zX5ojY9m\n
    XsYg6gyxy4zq7OlwWgLwGa==\n
    -----END PRIVATE KEY-----\n

---
apiVersion: trident.netapp.io/v1
kind: TridentBackendConfig
metadata:
  name: backend-tbc-gcnv
spec:
  version: 1
  storageDriverName: google-cloud-netapp-volumes
  projectNumber: "123455380079"
  location: europe-west6
  serviceLevel: premium
  apiKey:
    type: service_account
    project_id: my-gcnv-project
    client_email: myproject-prod@my-gcnv-
project.iam.gserviceaccount.com
    client_id: "103346282737811234567"
    auth_uri: https://accounts.google.com/o/oauth2/auth
    token_uri: https://oauth2.googleapis.com/token
    auth_provider_x509_cert_url:
https://www.googleapis.com/oauth2/v1/certs
    client_x509_cert_url:
https://www.googleapis.com/robot/v1/metadata/x509/myproject-prod%40my-
gcnv-project.iam.gserviceaccount.com
  credentials:
    name: backend-tbc-gcnv-secret

```

Configuration for SMB volumes

```
apiVersion: trident.netapp.io/v1
kind: TridentBackendConfig
metadata:
  name: backend-tbc-gcnv1
  namespace: trident
spec:
  version: 1
  storageDriverName: google-cloud-netapp-volumes
  projectNumber: "123456789"
  location: asia-east1
  serviceLevel: flex
  nasType: smb
  apiKey:
    type: service_account
    project_id: cloud-native-data
    client_email: trident-sample@cloud-native-
data.iam.gserviceaccount.com
    client_id: "123456789737813416734"
    auth_uri: https://accounts.google.com/o/oauth2/auth
    token_uri: https://oauth2.googleapis.com/token
    auth_provider_x509_cert_url:
https://www.googleapis.com/oauth2/v1/certs
    client_x509_cert_url:
https://www.googleapis.com/robot/v1/metadata/x509/trident-
sample%40cloud-native-data.iam.gserviceaccount.com
  credentials:
    name: backend-tbc-gcnv-secret
```

Configuration with StoragePools filter



```

---
apiVersion: v1
kind: Secret
metadata:
  name: backend-tbc-gcnv-secret
type: Opaque
stringData:
  private_key_id: f2cb6ed6d7cc10c453f7d3406fc700c5df0ab9ec
  private_key: |
    -----BEGIN PRIVATE KEY-----
    znHczZsrtrHisIsAbOguSaPIKeyAZNchRAGz1zZE4jK3bl/qp8B4Kws8zX5ojY9m
    znHczZsrtrHisIsAbOguSaPIKeyAZNchRAGz1zZE4jK3bl/qp8B4Kws8zX5ojY9m
    znHczZsrtrHisIsAbOguSaPIKeyAZNchRAGz1zZE4jK3bl/qp8B4Kws8zX5ojY9m
    XsYg6gyxy4zq7OlwWgLwGa==
    -----END PRIVATE KEY-----

---
apiVersion: trident.netapp.io/v1
kind: TridentBackendConfig
metadata:
  name: backend-tbc-gcnv
spec:
  version: 1
  storageDriverName: google-cloud-netapp-volumes
  projectNumber: "123455380079"
  location: europe-west6
  serviceLevel: premium
  storagePools:
    - premium-pool1-europe-west6
    - premium-pool2-europe-west6
  apiKey:
    type: service_account
    project_id: my-gcnv-project
    client_email: myproject-prod@my-gcnv-
project.iam.gserviceaccount.com
    client_id: "103346282737811234567"
    auth_uri: https://accounts.google.com/o/oauth2/auth
    token_uri: https://oauth2.googleapis.com/token
    auth_provider_x509_cert_url:
https://www.googleapis.com/oauth2/v1/certs
    client_x509_cert_url:
https://www.googleapis.com/robot/v1/metadata/x509/myproject-prod%40my-
gcnv-project.iam.gserviceaccount.com
  credentials:
    name: backend-tbc-gcnv-secret

```

Virtual pool configuration

This backend configuration defines multiple virtual pools in a single file. Virtual pools are defined in the storage section. They are useful when you have multiple storage pools supporting different service levels and you want to create storage classes in Kubernetes that represent those. Virtual pool labels are used to differentiate the pools. For instance, in the example below `performance` label and `serviceLevel` type is used to differentiate virtual pools.

You can also set some default values to be applicable to all virtual pools, and overwrite the default values for individual virtual pools. In the following example, `snapshotReserve` and `exportRule` serve as defaults for all virtual pools.

For more information, refer to [Virtual pools](#).

```
---
apiVersion: v1
kind: Secret
metadata:
  name: backend-tbc-gcnv-secret
type: Opaque
stringData:
  private_key_id: f2cb6ed6d7cc10c453f7d3406fc700c5df0ab9ec
  private_key: |
    -----BEGIN PRIVATE KEY-----
    znHczZsrrtHisIsAbOguSaPIKeyAZNchRAGz1zZE4jK3b1/qp8B4Kws8zX5ojY9m
    znHczZsrrtHisIsAbOguSaPIKeyAZNchRAGz1zZE4jK3b1/qp8B4Kws8zX5ojY9m
    znHczZsrrtHisIsAbOguSaPIKeyAZNchRAGz1zZE4jK3b1/qp8B4Kws8zX5ojY9m
    znHczZsrrtHisIsAbOguSaPIKeyAZNchRAGz1zZE4jK3b1/qp8B4Kws8zX5ojY9m
    XsYg6gyxy4zq70lwWgLwGa==
    -----END PRIVATE KEY-----

---
apiVersion: trident.netapp.io/v1
kind: TridentBackendConfig
metadata:
  name: backend-tbc-gcnv
spec:
  version: 1
  storageDriverName: google-cloud-netapp-volumes
  projectNumber: "123455380079"
  location: europe-west6
  apiKey:
    type: service_account
    project_id: my-gcnv-project
    client_email: myproject-prod@my-gcnv-
project.iam.gserviceaccount.com
    client_id: "103346282737811234567"
```

```

auth_uri: https://accounts.google.com/o/oauth2/auth
token_uri: https://oauth2.googleapis.com/token
auth_provider_x509_cert_url:
https://www.googleapis.com/oauth2/v1/certs
client_x509_cert_url:
https://www.googleapis.com/robot/v1/metadata/x509/myproject-prod%40my-
gcnv-project.iam.gserviceaccount.com
credentials:
  name: backend-tbc-gcnv-secret
defaults:
  snapshotReserve: "10"
  exportRule: 10.0.0.0/24
storage:
- labels:
  performance: extreme
  serviceLevel: extreme
  defaults:
    snapshotReserve: "5"
    exportRule: 0.0.0.0/0
- labels:
  performance: premium
  serviceLevel: premium
- labels:
  performance: standard
  serviceLevel: standard

```

Cloud identity for GKE

```

apiVersion: trident.netapp.io/v1
kind: TridentBackendConfig
metadata:
  name: backend-tbc-gcp-gcnv
spec:
  version: 1
  storageDriverName: google-cloud-netapp-volumes
  projectNumber: '012345678901'
  network: gcnv-network
  location: us-west2
  serviceLevel: Premium
  storagePool: pool-premium1

```

Supported topologies configuration

Trident facilitates provisioning of volumes for workloads based on regions and availability zones. The `supportedTopologies` block in this backend configuration is used to provide a list of regions and zones per backend. The region and zone values specified here must match the region and zone values from the labels on each Kubernetes cluster node. These regions and zones represent the list of permissible values that can be provided in a storage class. For storage classes that contain a subset of the regions and zones provided in a backend, Trident creates volumes in the mentioned region and zone. For more information, refer to [Use CSI Topology](#).

```
---
version: 1
storageDriverName: google-cloud-netapp-volumes
subscriptionID: 9f87c765-4774-fake-ae98-a721add45451
tenantID: 68e4f836-edc1-fake-bff9-b2d865ee56cf
clientID: dd043f63-bf8e-fake-8076-8de91e5713aa
clientSecret: SECRET
location: asia-east1
serviceLevel: flex
supportedTopologies:
  - topology.kubernetes.io/region: asia-east1
    topology.kubernetes.io/zone: asia-east1-a
  - topology.kubernetes.io/region: asia-east1
    topology.kubernetes.io/zone: asia-east1-b
```

What's next?

After you create the backend configuration file, run the following command:

```
kubectl create -f <backend-file>
```

To verify that the backend is successfully created, run the following command:

```
kubectl get tridentbackendconfig
```

NAME	BACKEND NAME	BACKEND UUID
PHASE STATUS		
backend-tbc-gcnv	backend-tbc-gcnv	b2fd1ff9-b234-477e-88fd-713913294f65
Bound Success		

If the backend creation fails, something is wrong with the backend configuration. You can describe the backend using the `kubectl get tridentbackendconfig <backend-name>` command or view the logs to determine the cause by running the following command:

```
tridentctl logs
```

After you identify and correct the problem with the configuration file, you can delete the backend and run the create command again.

Storage class definitions

The following is a basic `StorageClass` definition that refers to the backend above.

```
apiVersion: storage.k8s.io/v1
kind: StorageClass
metadata:
  name: gcnv-nfs-sc
provisioner: csi.trident.netapp.io
parameters:
  backendType: "google-cloud-netapp-volumes"
```

Example definitions using the `parameter.selector` field:

Using `parameter.selector` you can specify for each `StorageClass` the [virtual pool](#) that is used to host a volume. The volume will have the aspects defined in the chosen pool.

```

apiVersion: storage.k8s.io/v1
kind: StorageClass
metadata:
  name: extreme-sc
provisioner: csi.trident.netapp.io
parameters:
  selector: performance=extreme
  backendType: google-cloud-netapp-volumes

---
apiVersion: storage.k8s.io/v1
kind: StorageClass
metadata:
  name: premium-sc
provisioner: csi.trident.netapp.io
parameters:
  selector: performance=premium
  backendType: google-cloud-netapp-volumes

---
apiVersion: storage.k8s.io/v1
kind: StorageClass
metadata:
  name: standard-sc
provisioner: csi.trident.netapp.io
parameters:
  selector: performance=standard
  backendType: google-cloud-netapp-volumes

```

For more details on storage classes, refer to [Create a storage class](#).

Example definitions for SMB volumes

Using `nasType`, `node-stage-secret-name`, and `node-stage-secret-namespace`, you can specify an SMB volume and provide the required Active Directory credentials. Any Active Directory user/password with any/no permissions can be used for the node stage secret.

Basic configuration on default namespace

```
apiVersion: storage.k8s.io/v1
kind: StorageClass
metadata:
  name: gcnv-sc-smb
provisioner: csi.trident.netapp.io
parameters:
  backendType: "google-cloud-netapp-volumes"
  trident.netapp.io/nasType: "smb"
  csi.storage.k8s.io/node-stage-secret-name: "smbcreds"
  csi.storage.k8s.io/node-stage-secret-namespace: "default"
```

Using different secrets per namespace

```
apiVersion: storage.k8s.io/v1
kind: StorageClass
metadata:
  name: gcnv-sc-smb
provisioner: csi.trident.netapp.io
parameters:
  backendType: "google-cloud-netapp-volumes"
  trident.netapp.io/nasType: "smb"
  csi.storage.k8s.io/node-stage-secret-name: "smbcreds"
  csi.storage.k8s.io/node-stage-secret-namespace: ${pvc.namespace}
```

Using different secrets per volume

```
apiVersion: storage.k8s.io/v1
kind: StorageClass
metadata:
  name: gcnv-sc-smb
provisioner: csi.trident.netapp.io
parameters:
  backendType: "google-cloud-netapp-volumes"
  trident.netapp.io/nasType: "smb"
  csi.storage.k8s.io/node-stage-secret-name: ${pvc.name}
  csi.storage.k8s.io/node-stage-secret-namespace: ${pvc.namespace}
```



nasType: smb filters for pools which support SMB volumes. nasType: nfs or nasType: null filters for NFS pools.

PVC definition example

```
kind: PersistentVolumeClaim
apiVersion: v1
metadata:
  name: gcnv-nfs-pvc
spec:
  accessModes:
    - ReadWriteMany
  resources:
    requests:
      storage: 100Gi
  storageClassName: gcnv-nfs-sc
```

To verify if the PVC is bound, run the following command:

```
kubectl get pvc gcnv-nfs-pvc
```

NAME	STATUS	VOLUME	CAPACITY
ACCESS MODES	STORAGECLASS	AGE	
gcnv-nfs-pvc	Bound	pvc-b00f2414-e229-40e6-9b16-ee03eb79a213	100Gi
RWX	gcnv-nfs-sc	1m	

Copyright information

Copyright © 2026 NetApp, Inc. All Rights Reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means—graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system—without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

LIMITED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (b)(3) of the Rights in Technical Data -Noncommercial Items at DFARS 252.227-7013 (FEB 2014) and FAR 52.227-19 (DEC 2007).

Data contained herein pertains to a commercial product and/or commercial service (as defined in FAR 2.101) and is proprietary to NetApp, Inc. All NetApp technical data and computer software provided under this Agreement is commercial in nature and developed solely at private expense. The U.S. Government has a non-exclusive, non-transferrable, nonsublicensable, worldwide, limited irrevocable license to use the Data only in connection with and in support of the U.S. Government contract under which the Data was delivered. Except as provided herein, the Data may not be used, disclosed, reproduced, modified, performed, or displayed without the prior written approval of NetApp, Inc. United States Government license rights for the Department of Defense are limited to those rights identified in DFARS clause 252.227-7015(b) (FEB 2014).

Trademark information

NETAPP, the NETAPP logo, and the marks listed at <http://www.netapp.com/TM> are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.