



# Azure NetApp Files documentation

## Azure NetApp Files

NetApp  
June 07, 2022

# Table of Contents

- Azure NetApp Files documentation ..... 1
- What's new ..... 2
  - 11 April 2021 ..... 2
  - 8 March 2021 ..... 2
  - 3 August 2020 ..... 2
  - 5 April 2020 ..... 2
- Get started ..... 3
  - Learn about Azure NetApp Files ..... 3
  - Quick start for Azure NetApp Files ..... 4
  - Set up an Azure AD application ..... 4
  - Create an Azure NetApp Files working environment ..... 8
- Use Azure NetApp Files ..... 10
  - Create and mount volumes for Azure NetApp Files ..... 10
  - Manage volumes for Azure NetApp Files ..... 14
  - Remove Azure NetApp Files ..... 15
- Knowledge and support ..... 16
  - Register for support ..... 16
  - Get help ..... 17
- Legal notices ..... 19
  - Copyright ..... 19
  - Trademarks ..... 19
  - Patents ..... 19
  - Privacy policy ..... 19
  - Open source ..... 19

# Azure NetApp Files documentation

# What's new

Learn what's new with Azure NetApp Files in Cloud Manager.

## 11 April 2021

### Support for volume templates

A new Application Templates service enables you to set up a volume template for Azure NetApp Files. The template should make your job easier because certain volume parameters will already be defined in the template, such as capacity pool, size, protocol, VNet and subnet where the volume should reside, and more. When a parameter is already predefined, you can just skip to the next volume parameter.

- [Learn about Application Templates and how you can use them in your environment](#)
- [Learn how to create an Azure NetApp Files volume from a template](#)

## 8 March 2021

### Dynamically change service levels

You can now dynamically change the service level for a volume to meet workload needs and optimize your costs. The volume is moved to the other capacity pool with no impact to the volume.

[Learn how to change a volume's service level.](#)

## 3 August 2020

### Azure NetApp Files set up and management

Set up and manage Azure NetApp Files directly from Cloud Manager. After you create an Azure NetApp Files working environment, you can complete the following tasks:

- Create NFS and SMB volumes.
- Manage capacity pools and volume snapshots

Cloud Manager enables you to create, delete, and restore volume snapshots. You can also create new capacity pools and specify their service levels.

- Edit a volume by changing its size and managing tags.

The ability to create and manage Azure NetApp Files directly from Cloud Manager replaces the previous data migration functionality.

## 5 April 2020

### Data migration to Azure NetApp Files

You can now migrate NFS or SMB data to Azure NetApp Files directly from Cloud Manager. Data syncs are powered by NetApp's Cloud Sync service.

# Get started

## Learn about Azure NetApp Files

Azure NetApp Files enables enterprises to migrate and run their performance-intensive and latency-sensitive core, business-critical applications in Azure with no need to refactor for the cloud.

### Features

- Support for multiple protocols enables "lift & shift" of both Linux & Windows applications to run seamlessly in Azure.
- Multiple performance tiers allow for close alignment with workload performance requirements.
- Leading certifications including SAP HANA, GDPR, and HIPAA enables migration of the most demanding workloads to Azure.

### Additional features in Cloud Manager

- Migrate NFS or SMB data to Azure NetApp Files directly from Cloud Manager. Data migrations are powered by NetApp's Cloud Sync service.

[Learn more about Cloud Sync](#)

- Using Artificial Intelligence (AI) driven technology, Cloud Data Sense can help you understand data context and identify sensitive data that resides in your Azure NetApp Files accounts.

[Learn more about Cloud Data Sense](#)

### Cost

[View Azure NetApp Files pricing](#)

Note that your subscription and charging are maintained by the Azure NetApp Files service and not by Cloud Manager.

### Supported regions

[View supported Azure regions](#)

### Getting help

For technical support issues associated with Azure NetApp Files, use the Azure portal to log a support request to Microsoft. Select your associated Microsoft subscription and select the **Azure NetApp Files** service name under **Storage**. Provide the remaining information required to create your Microsoft support request.

### Related links

- [NetApp Cloud Central: Azure NetApp Files](#)
- [Azure NetApp Files documentation](#)

- [Cloud Sync documentation](#)

## Quick start for Azure NetApp Files

Get started quickly by following these steps or follow the links for full details.

1

### Set up an Azure AD application

From Azure, grant permissions to an Azure AD application and copy the application (client) ID, the directory (tenant) ID, and the value of a client secret.

[Learn how to set up an Azure AD application.](#)

2

### Create an Azure NetApp Files working environment

In Cloud Manager, click **Add Working Environment > Microsoft Azure > Azure NetApp Files** and then provide details about the AD application.

[Learn how to create a working environment.](#)

## Set up an Azure AD application

Cloud Manager needs permissions to set up and manage Azure NetApp Files. You can grant the required permissions to an Azure account by creating and setting up an Azure Active Directory (AD) application and by obtaining the Azure credentials that Cloud Manager needs.

### Create the AD application


Create an Azure AD application and service principal that Cloud Manager can use for role-based access control.

#### Before you begin


You must have the right permissions in Azure to create an Active Directory application and to assign the application to a role. For details, refer to [Microsoft Azure Documentation: Required permissions](#).

#### Steps

1. From the Azure portal, open the **Azure Active Directory** service.




2. In the menu, click **App registrations**.
3. Create the application:
  - a. Click **New registration**.
  - b. Specify details about the application:
    - **Name**: Enter a name for the application.
    - **Account type**: Select an account type (any will work with Cloud Manager).
    - **Redirect URI**: You can leave this blank.
  - c. Click **Register**.
4. Copy the **Application (client) ID** and the **Directory (tenant) ID**.



When you create the Azure NetApp Files working environment in Cloud Manager, you need to provide the application (client) ID and the directory (tenant) ID for the application. Cloud Manager uses the IDs to programmatically sign in.

5. Create a client secret for the application so Cloud Manager can use it to authenticate with Azure AD:
  - a. Click **Certificates & secrets > New client secret**.
  - b. Provide a description of the secret and a duration.
  - c. Click **Add**.
  - d. Copy the value of the client secret.



## Result

Your AD application is now setup and you should have copied the application (client) ID, the directory (tenant) ID, and the value of the client secret. You need to enter this information in Cloud Manager when you add an Azure NetApp Files working environment.

## Assign the app to a role


You must bind the service principal to your Azure subscription and assign it a custom role that has the required permissions.

### Steps

1. [Create a custom role in Azure.](#)

The following steps describe how to create the role from the Azure portal.

- a. Open the subscription and click **Access control (IAM)**.
- b. Click **Add > Add custom role**.






- c. In the **Basics** tab, enter a name and description for the role.
- d. Click **JSON** and click **Edit** which appears at the top right of the JSON format.
- e. Add the following permission under *actions*:


```
"actions": [  
  "Microsoft.NetApp/*"  
],
```

- f. Click **Save**, click **Next**, and then click **Create**.
2. Now assign the application to the role that you just created:
- a. From the Azure portal, open the **Subscriptions** service.
  - b. Select the subscription.
  - c. Click **Access control (IAM) > Add > Add role assignment**.
  - d. In the **Role** tab, select the custom role that you created and click **Next**.
  - e. In the **Members** tab, complete the following steps:
    - Keep **User, group, or service principal** selected.
    - Click **Select members**.



- Search for the name of the application.

Here's an example:



- Select the application and click **Select**.
  - Click **Next**.
- f. Click **Review + assign**.

The service principal for Cloud Manager now has the required Azure permissions for that subscription.

## Create an Azure NetApp Files working environment

After you set up an Azure Active Directory application, create an Azure NetApp Files working environment in Cloud Manager so that you can start creating the volumes that you need.

### Steps

1. From the Canvas page, click **Add Working Environment**.
2. Select **Microsoft Azure** and then **Azure NetApp Files**.
3. Provide details about the AD application that you previously set up.

## Azure NetApp Files Credentials

Working Environment Name

ANF

Application (client) ID

e461f4ca-9d9a-4aec-8f39-fc842b684c97

Client Secret

.....


Directory (tenant) ID

8e21f23a-10b9-46fb-9d50-720ef604be98

4. Click **Add**.

### Result

You should now have an Azure NetApp Files working environment.



### What's next?

[Start creating and managing volumes.](#)

# Use Azure NetApp Files

## Create and mount volumes for Azure NetApp Files

After you set up your working environment, you can create Azure NetApp Files accounts, capacity pools, and volumes.

### Create volumes

You can create NFS or SMB volumes in a new or existing Azure NetApp Files account.

A Cloud Manager feature called "templates" enables you to create volumes that are optimized for the workload requirements for certain applications; such as databases or streaming services. If your organization has created volume templates that you should use, follow [these steps](#).

### Before you begin

- If you want to use SMB, you must have set up DNS and Active Directory.
- When planning to create an SMB volume, you must have a Windows Active Directory server available to which you can connect. You will enter this information when creating the volume.

### Steps

1. Open the Azure NetApp Files working environment.
2. Click **Add New Volume**.
3. Provide the required information on each page:
  - **Azure NetApp Files Account:** Choose an existing Azure NetApp Files account or create a new account. When creating a new account you can also choose the Resource Group that you want to use.
  - **Capacity Pool:** Select an existing capacity pool or create a new capacity pool.  
  
If you create a new capacity pool, you need to specify a size and select a [service level](#).  
  
The minimum size for the capacity pool is 4 TB. You can specify a size in multiples of 4 TB.
  - **Details & Tags:** Enter a volume name and size, the VNet and subnet where the volume should reside, and optionally specify tags for the volume.
  - **Protocol:** Choose the NFS or SMB protocol and enter the required information.

Here's an example of details for NFS.

Protocol

Select the volume's protocol:  NFS Protocol  SMB Protocol

Protocol: NFS  
Export Policy: 2 rules

Volume Path: vol1

Select NFS Version:  
 NFSv3  NFSv4.1

Allowed Client & Access:

Client	Access
192.168.1.22/24	<input checked="" type="radio"/> Read & Write <input type="radio"/> Read Only
192.168.1.22/24	<input checked="" type="radio"/> Read & Write <input type="radio"/> Read Only

+ Add Export Policy Rule (Up to 5)

Here's an example of details for SMB. You'll need to provide Active Directory information on the next page when you set up your first SMB volume.

Protocol

Select the volume's protocol:  NFS Protocol  SMB Protocol

Share Name: vol1

4. If you want this volume to be created based on a snapshot of an existing volume, select the snapshot from the Snapshot Name drop-down list.
5. Click **Add Volume**.

### Result

The new volume is added to the working environment.


Continue with [mounting the cloud volume](#).


## Create volumes from templates

If your organization has created Azure NetApp Files volume templates so that you can deploy volumes that are optimized for the workload requirements for certain applications, follow the steps in this section.


The template should make your job easier because certain volume parameters will already be defined in the template, such as capacity pool, size, protocol, VNet and subnet where the volume should reside, and more. When a parameter is already predefined, you can just skip to the next volume parameter.

### Steps


1. On the Canvas page, click the Azure NetApp Files working environment on which you want to provision a volume.
2. Click  > **Add Volume From Template**.



3. In the *Select Template* page, select the template that you want to use to create the volume and click **Next**.



The *Define Parameters* page is displayed.




**Note:** You can click the checkbox **Show read-only parameters** to show all the fields that have been locked by the template if you want to see the values for those parameters. By default these predefined

fields are hidden and only the fields you need to complete are shown.

4. Add values for all of the parameters that are not hard-coded from the template. See [creating volumes](#) for details about all the parameters you need to complete to deploy an Azure NetApp Files volume.
5. Click **Run Template** after you have defined all the parameters needed for this volume.

## Result

Cloud Manager provisions the volume and displays a page so that you can see the progress.



Then the new volume is added to the working environment.


Continue with mounting the cloud volume.

## Mount volumes

Access mounting instructions from within Cloud Manager so you can mount the volume to a host.

### Steps

1. Open the working environment.
2. Hover over the volume and select **Mount the volume**.



3. Follow the instructions to mount the volume.

# Manage volumes for Azure NetApp Files

You can manage existing volumes as your storage needs change. You can edit volumes, change a volume's service level, manage Snapshot copies, and delete volumes.

## Edit a volume's size and tags

After you create a volume, you can modify its size and tags at any time.

### Steps

1. Open the working environment.
2. Hover over the volume and select **Edit**.
3. Modify the size and tags as needed.
4. Click **Apply**.

## Change the volume's service level

After you create a volume, you can change the service level at any time as long as the destination capacity pool already exists.

### Steps

1. Open the working environment.
2. Hover over the volume and select **Change service level**.
3. Select the capacity pool that provides the service level that you want.
4. Click **Change**.

### Result

The volume is moved to the other capacity pool with no impact to the volume.

## Manage Snapshot copies

Snapshot copies provide a point-in-time copy of your volume. Create Snapshot copies, restore the data to a new volume, and delete Snapshot copies.

### Steps

1. Open the working environment.
2. Hover over the volume and choose one of the available options to manage Snapshot copies:
  - **Create a Snapshot copy**
  - **Revert volume to Snapshot**
  - **Delete a Snapshot copy**
3. Follow the prompts to complete the selected action.

## Delete volumes

Delete the volumes that you no longer need.

### Steps




1. Open the working environment.
2. Hover over the volume and click **Delete**.
3. Confirm that you want to delete the volume.

## Remove Azure NetApp Files

This action removes Azure NetApp Files from Cloud Manager. It doesn't delete your Azure NetApp Files account or volumes. You can add Azure NetApp Files back to Cloud Manager at any time.

### Steps

1. Open the Azure NetApp Files working environment.
2. At the top right of the page, select the actions menu and click **Remove Azure NetApp Files**.



3. Click **Remove** to confirm.

# Knowledge and support

## Register for support


Before you can open a support case with NetApp technical support, you need to add a NetApp Support Site account to Cloud Manager and then register for support.

### Add an NSS account

The Support Dashboard enables you to add and manage all of your NetApp Support Site accounts from a single location.

#### Steps

1. If you don't have a NetApp Support Site account yet, [register for one](#).
2. In the upper right of the Cloud Manager console, click the Help icon, and select **Support**.



3. Click **NSS Management > Add NSS Account**.
4. When you're prompted, click **Continue** to be redirected to a Microsoft login page.  
  
NetApp uses Microsoft Azure Active Directory as the identity provider for authentication services specific to support and licensing.
5. At the login page, provide your NetApp Support Site registered email address and password to perform the authentication process.

This action enables Cloud Manager to use your NSS account.


Note the account must be a customer-level account (not a guest or temp account).

### Register your account for support

Support registration is available from Cloud Manager in the Support Dashboard.

#### Steps

1. In the upper right of the Cloud Manager console, click the Help icon, and select **Support**.



2. In the **Resources** tab, click **Register for Support**.
3. Select the NSS credentials that you want to register and then click **Register**.

## Get help

NetApp provides support for Cloud Manager and its cloud services in a variety of ways. Extensive free self-support options are available 24x7, such as knowledgebase (KB) articles and a community forum. Your support registration includes remote technical support via web ticketing.

### Self support

These options are available for free, 24 hours a day, 7 days a week:

- [Knowledge base](#)

Search through the Cloud Manager knowledge base to find helpful articles to troubleshoot issues.

- [Communities](#)

Join the Cloud Manager community to follow ongoing discussions or create new ones.

- Documentation

The Cloud Manager documentation that you're currently viewing.

- [Feedback email](#)

We value your input. Submit feedback to help us improve Cloud Manager.

### NetApp support

In addition to the self-support options above, you can work with a NetApp Support Engineer to resolve any issues after you activate support.

## Steps

1. In Cloud Manager, click **Help > Support**.
2. Choose one of the available options under Technical Support:
  - a. Click **Call Us** to find phone numbers for NetApp technical support.
  - b. Click **Open an Issue**, select one the options, and then click **Send**.

A NetApp representative will review your case and get back to you soon.

# Legal notices

Legal notices provide access to copyright statements, trademarks, patents, and more.

## Copyright

<http://www.netapp.com/us/legal/copyright.aspx>

## Trademarks

NETAPP, the NETAPP logo, and the marks listed on the NetApp Trademarks page are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.

<http://www.netapp.com/us/legal/netapptmlist.aspx>

## Patents

A current list of NetApp owned patents can be found at:

<https://www.netapp.com/us/media/patents-page.pdf>

## Privacy policy

<https://www.netapp.com/us/legal/privacypolicy/index.aspx>

## Open source

Notice files provide information about third-party copyright and licenses used in NetApp software.

[Notice for Cloud Manager 3.9](#)

## Copyright Information

Copyright © 2022 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system-without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP "AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

## Trademark Information

NETAPP, the NETAPP logo, and the marks listed at <http://www.netapp.com/TM> are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.