



Get started

NetApp Replication

NetApp
November 10, 2025

This PDF was generated from <https://docs.netapp.com/us-en/data-services-replication/concept-replication.html> on November 10, 2025. Always check docs.netapp.com for the latest.

Table of Contents

- Get started 1
 - Learn about NetApp Replication 1
 - NetApp Console 1
 - Features 1
 - Cost 1
 - Supported systems 1
 - How data replication works 2
 - Supported data protection configurations 2
 - Replicate data using NetApp Backup and Recovery 2
 - Log in to NetApp Replication 3
 - Set up data replication in NetApp Replication 3
 - Step 1: Review data replication requirements 3
 - Step 2: Replicate data between systems 4

Get started

Learn about NetApp Replication

NetApp SnapMirror replicates data at high speeds over LAN or WAN, so you get high data availability and fast data replication in both virtual and traditional environments. When you replicate data to NetApp storage systems using NetApp Replication and continually update the secondary data, your data is kept current and remains available whenever you need it. No external replication servers are required.

NetApp Console

NetApp Replication is accessible through the NetApp Console.

The NetApp Console provides centralized management of NetApp storage and data services across on-premises and cloud environments at enterprise grade. The Console is required to access and use NetApp data services. As a management interface, it enables you to manage many storage resources from one interface. Console administrators can control access to storage and services for all systems within the enterprise.

You don't need a license or subscription to start using NetApp Console and you only incur charges when you need to deploy Console agents in your cloud to ensure connectivity to your storage systems or NetApp data services. However, some NetApp data services accessible from the Console are licensed or subscription-based.

Learn more about the [NetApp Console](#).

Features

- Replicate data between ONTAP storage systems to support backup and disaster recovery to the cloud or between clouds.
- Ensure the reliability of your DR environment with high availability.
- Efficient block-level replication between ONTAP storage is fast and efficient, with granular recovery points for both DR and backup.

Cost

NetApp doesn't charge you for using NetApp Replication, but you'll need to check your cloud provider for applicable data ingress and egress charges.

Supported systems

NetApp Replication enables data replication between the following types of systems.

Source system	Supported target systems
Cloud Volumes ONTAP	<ul style="list-style-type: none">• Amazon FSx for ONTAP• Cloud Volumes ONTAP• On-prem ONTAP cluster

Source system	Supported target systems
On-prem ONTAP cluster	<ul style="list-style-type: none"> • Amazon FSx for ONTAP • Cloud Volumes ONTAP • On-prem ONTAP cluster
Amazon FSx for ONTAP	<ul style="list-style-type: none"> • Amazon FSx for ONTAP • Cloud Volumes ONTAP • On-prem ONTAP cluster

How data replication works

NetApp Replication simplifies data replication between volumes on separate ONTAP systems using SnapMirror and SnapVault technologies. You simply need to identify the source volume and the destination volume, and then choose a replication policy and schedule.

For Cloud Volumes ONTAP, NetApp Replication purchases the required disks, configures relationships, applies the replication policy, and then initiates the baseline transfer between volumes.



The baseline transfer includes a full copy of the source data. Subsequent transfers contain differential copies of the source data.

Supported data protection configurations

NetApp Replication supports simple, fanout, and cascade data protection configurations:

- In a simple configuration, replication occurs from volume A to volume B.
- In a fanout configuration, replication occurs from volume A to multiple destinations.
- In a cascade configuration, replication occurs from volume A to volume B and from volume B to volume C.

Replicate data using NetApp Backup and Recovery

Starting with the NetApp Console agent 3.9.31 release, NetApp Backup and Recovery enables you to replicate data between volumes on separate ONTAP systems using SnapMirror and SnapVault technologies. So if you plan to replicate data to other ONTAP systems, and you also want to create backups of the same data to object storage, you may want to use [NetApp Backup and Recovery](#) so that you can manage your data protection needs with a single service.

Currently, the following functionality is only supported in NetApp Replication - not when using the replication feature of NetApp Backup and Recovery.

- There is no support for a cascade configuration where replication occurs from volume A to volume B, and then from volume B to volume C.
- There is no support for replicating data to or from FSx for ONTAP systems.
- There is no support for creating a one-time replication of a volume.

So if you require any of this functionality, use NetApp Replication.

Log in to NetApp Replication

Use the NetApp Console to log in to NetApp Replication.

To log in to the Console, you can use your NetApp Support Site credentials or you can sign up for a NetApp cloud login using your email and a password. [Learn more about logging in.](#)

Steps

1. Open a web browser and go to the [NetApp Console](#).

The NetApp Console login page appears.

2. Log in to the Console.
3. From the Console left navigation, select **Protection > Replication**.

Set up data replication in NetApp Replication

Using NetApp Replication, replicate data between ONTAP systems by choosing a one-time data replication for data transfer, or a recurring schedule for disaster recovery or long-term retention. For example, you can set up data replication from an on-premises ONTAP system to Cloud Volumes ONTAP for disaster recovery.

Step 1: Review data replication requirements

Before you can replicate data, you should confirm that specific requirements are met for Cloud Volumes ONTAP, on-prem ONTAP clusters, or Amazon FSx for ONTAP.

systems

If you haven't done so already, you need to create the systems for the source and target in the data replication relationship.

- [Create an Amazon FSx for ONTAP system](#)
- [Create a Cloud Volumes ONTAP system](#)
- [Add existing Cloud Volumes ONTAP systems](#)
- [Discover ONTAP clusters](#)

Version requirements

You should verify that the source and destination volumes are running compatible ONTAP versions before replicating data.

[View compatible ONTAP versions for SnapMirror relationships](#)

Requirements specific to Cloud Volumes ONTAP

- The instance's security group must include the required inbound and outbound rules: specifically, rules for ICMP and ports 11104 and 11105.

These rules are included in the predefined security group.

- To replicate data between two Cloud Volumes ONTAP systems in different subnets, the subnets must be routed together (this is the default setting).

- To replicate data between two Cloud Volumes ONTAP systems in different cloud providers, you must have a VPN connection between the virtual networks.

Requirements specific to ONTAP clusters

- An active SnapMirror license must be installed.
- If the cluster is on your premises, you should have a connection from your corporate network to your virtual network in the cloud. This is typically a VPN connection.
- ONTAP clusters must meet additional subnet, port, firewall, and cluster requirements.

[View prerequisites for cluster peering in the ONTAP documentation](#)

Requirements specific to Amazon FSx for ONTAP

- If Cloud Volumes ONTAP is part of the relationship, ensure connectivity between VPCs by enabling VPC peering or by using a Transit Gateway.
- If an on-prem ONTAP cluster is part of the relationship, ensure connectivity between your on-premises network and the AWS VPC by using a Direct Connect or VPN connection.

Step 2: Replicate data between systems

You can replicate data by choosing a one-time data replication, which can help you move data to and from the cloud, or a recurring schedule, which can help with disaster recovery or long-term retention.

Steps

1. From the navigation menu, select **Storage > Management**.
2. On the Systems page, select the system that contains the source volume, drag it to the system to which you want to replicate the volume, and then select **Replication**.

The remaining steps provide an example of how to create a sync relationship between Cloud Volumes ONTAP or on-prem ONTAP clusters.

3. **Source and Destination Peering Setup:** If this page appears, select all of the intercluster LIFs for the cluster peer relationship.

The intercluster network should be configured so that cluster peers have *pair-wise full-mesh connectivity*, which means that each pair of clusters in a cluster peer relationship has connectivity among all of their intercluster LIFs.

These pages appear if an ONTAP cluster that has multiple LIFs is the source or destination.

4. **Source Volume Selection:** Select the volume that you want to replicate.
5. **Destination Disk Type and Tiering:** If the target is a Cloud Volumes ONTAP system, select the destination disk type and choose whether you want to enable data tiering.
6. **Destination Volume Name:** Specify the destination volume name and choose the destination aggregate.

If the destination is an ONTAP cluster, you must also specify the destination storage VM.

7. **Max Transfer Rate:** Specify the maximum rate (in megabytes per second) at which data can be transferred.

You should limit the transfer rate. An unlimited rate might negatively impact the performance of other applications and it might impact your internet performance.

8. **Replication Policy:** Choose a default policy or select **Additional Policies**, and then select one of the advanced policies.

For help, [learn about replication policies](#).

If you choose a custom backup (SnapVault) policy, the labels associated with the policy must match the labels of the snapshot copies on the source volume. For more information, [learn how backup policies work](#).

9. **Schedule:** Choose a one-time copy or a recurring schedule.

Several default schedules are available. If you want a different schedule, you must create a new schedule on the *destination* cluster using System Manager.

10. **Review:** Review your selections and select **Go**.

Result

NetApp Replication starts the data replication process. You can view details about the volume relationship from NetApp Replication.

Copyright information

Copyright © 2025 NetApp, Inc. All Rights Reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means—graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system—without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

LIMITED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (b)(3) of the Rights in Technical Data -Noncommercial Items at DFARS 252.227-7013 (FEB 2014) and FAR 52.227-19 (DEC 2007).

Data contained herein pertains to a commercial product and/or commercial service (as defined in FAR 2.101) and is proprietary to NetApp, Inc. All NetApp technical data and computer software provided under this Agreement is commercial in nature and developed solely at private expense. The U.S. Government has a non-exclusive, non-transferrable, nonsublicensable, worldwide, limited irrevocable license to use the Data only in connection with and in support of the U.S. Government contract under which the Data was delivered. Except as provided herein, the Data may not be used, disclosed, reproduced, modified, performed, or displayed without the prior written approval of NetApp, Inc. United States Government license rights for the Department of Defense are limited to those rights identified in DFARS clause 252.227-7015(b) (FEB 2014).

Trademark information

NETAPP, the NETAPP logo, and the marks listed at <http://www.netapp.com/TM> are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.