



volume object-store commands

ONTAP 9.10.1 commands

NetApp
September 27, 2022

Table of Contents

- volume object-store commands 1
- volume object-store tiering show 1
- volume object-store tiering trigger 3

volume object-store commands

volume object-store tiering show

Display Tiering Status of FabricPool Volumes

Availability: This command is available to *cluster* administrators at the *advanced* privilege level.

Description

The `volume object-store tiering show` command displays information about the tiering scanner status of FabricPool aggregate volumes. The tiering scanner will, depending on the combination of the tiering-policy and cloud-retrieval-policy settings, both retrieve from and tier to the capacity tier. This show command can be used to display the status of the scanner, whether it has aborted, what errors it has encountered and when it will be scheduled to run again.

Parameters

{ [-fields <fieldname>,...]

If you specify the `-fields <fieldname>, ...` parameter, the command output also includes the specified field or fields. You can use `'-fields ?'` to display the fields to specify.

| [-instance] }

If you specify the `-instance` parameter, the command displays detailed information about all fields.

[-vserver <vserver name>] - Vserver

vserver name

[-volume <volume name>] - Volume

volume name

[-node <nodename>] - Node Name

node name

[-vol-dsid <integer>] - Volume DSID

volume dsid

[-aggregate <aggregate name>] - Aggregate Name

aggregate name

[-scanner-state {ready|active|waiting}] - State

The state of the scanner. The values `active`, `ready` and `waiting` may appear in this field. `Active` means the scanner is currently running, `waiting` means the scanner is waiting to be scheduled, and `ready` means the scanner is ready to run. Once a scanner is ready to run, it must be scheduled by the system's scan scheduler, the amount of time it takes for it to become active is variable and depends on how busy the system is..

[-scanner-last-status {aborted-nospace-promote|aborted-fabricpool|aborted-nospace-defrag|aborted-nospace|aborted-exception|aborted-policy|aborted|completed|prev-not-run|aborted-defrag-throttled|aborted-nospace-revert-format|aborted-revert-format-paused|aborted-dual-tier-dirty-failed}] - Previous Run Status

The status of the tiering scanner the last time it ran. This field will indicate if the scanner has aborted or completed.

[-scanner-abort-exception <integer>] - Aborted Exception Status

If the scanner last status indicates the scanner aborted with an exception then this field is set to the exception error code that caused the abort.

[-time-last-scan <Date>] - Time Scanner Last Finished

This field displays the date and time the last scanner status field was set.

[-scan-percent <percent>] - Scanner Percent Complete

This field displays the completion percentage of scans in the active state.

[-time-next-scan <Date>] - Time Waiting Scan will be scheduled

This field displays the date and time scans in the waiting state will enter the ready state.

[-tiering-policy {snapshot-only|auto|none|all}] - Tiering Policy

The tiering policy. This field displays the current tiering-policy in effect on the volume.

[-promotion-space-needed {<integer>[KB|MB|GB|TB|PB]}] - Estimated Space Needed for Promotion

If the scanner aborted due to no space for promote, then this field is set to the estimated minimum space required for promotion to take effect.

[-scan-start-time <Date>] - Time Scan Started

This field displays the date and time the scan, if in active state, started.

[-cloud-retrieval-policy {default|on-read|never|promote}] - Cloud Retrieval Policy

The cloud retrieval policy. This field displays the current cloud-retrieval-policy in effect on the volume.

[-scan-elapsed-time <[<integer>h] [<integer>m] [<integer>s]>] - Elapsed Time Scanner Ran

This field displays the time it took for the last scan to run to complete or abort.

Examples

```

cluster1::> volume object-store tiering show
                                     Policy
Vserver Volume Aggregate State   %Complete Tiering CloudRetrieve
LastStatus
-----
vs1      vol      aggr1      waiting      - snapshot-only
                                     default
completed

```

Shows the tiering status for all FabricPool volumes.

volume object-store tiering trigger

Trigger a tiering scan

Availability: This command is available to *cluster* administrators at the *advanced* privilege level.

Description

The `volume object-store tiering trigger` command triggers a tiering and retrieve scan. Tiering and retrieval behavior is driven by the tiering and cloud retrieve policy settings on the volume. The cloud retrieve policy must be set to promote to enable scanner based retrieval.

Parameters

-vserver <vserver name> - VServer Name

vserver name

-volume <volume name> - Volume Name

volume name

Copyright Information

Copyright © 2022 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system-without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP "AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at <http://www.netapp.com/TM> are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.