



Managing OnCommand Workflow Automation SSL certificate

OnCommand Workflow Automation 5.0

NetApp
May 03, 2022

Table of Contents

- Managing OnCommand Workflow Automation SSL certificate 1
 - Replace the default Workflow Automation SSL certificate 1
 - Create a certificate signing request for Workflow Automation 2

Managing OnCommand Workflow Automation SSL certificate

You can replace the default OnCommand Workflow Automation (WFA) SSL certificate with a self-signed certificate or a certificate signed by a Certificate Authority (CA).

The default self-signed WFA SSL certificate is generated during the installation of WFA. When you are upgrading, the certificate for the previous installation is replaced with the new certificate. If you are using a non-default self-signed certificate or a certificate signed by a CA, you must replace the default WFA SSL certificate with your certificate.

Replace the default Workflow Automation SSL certificate

You can replace the default Workflow Automation (WFA) SSL certificate if the certificate has expired or if you want to increase the validity period of the certificate.

What you'll need

You must have Windows admin privileges on the WFA server.

About this task

The default WFA installation path is used in this procedure. If you changed the default location during installation, you must use the custom WFA installation path.

Steps

1. Log in as the admin user on the WFA host machine.
2. Use the Windows Services console to stop the following WFA services:
 - NetApp WFA Database
 - NetApp WFA Server
3. Delete the `wfa.keystore` file from the following location:
`<WFA_install_location>\WFA\jboss\standalone\configuration\keystore`
4. Open a command prompt on the WFA server, and change directories to the following location:
`<WFA_install_location>\WFA\jre\bin`
5. Obtain the database key: `keytool -keysize 2048 -genkey -alias "ssl keystore" -keyalg RSA -keystore "<WFA_install_location>\WFA\jboss\standalone\configuration\keystore\wfa.keystore" -validity xxxx`

xxxx is the number of days for the new certificate's validity.
6. When prompted, provide the password (default or new).

`changeit` is the default password. If you do not want to use the default password, you must change the password attribute of the SSL element in the `standalone-full.xml` file from the following location:

```
<WFA_install_location>\WFA\jboss\standalone\configuration\
```

Example

```
<ssl name="ssl" password="new_password" certificate-key-  
file="{jboss.server.config.dir}/keystore/wfa.keystore"
```

7. Enter the required details for the certificate.
8. Review the displayed information, and enter `Yes`.
9. Press **Enter** when prompted by the following message: Enter key password for <SSL keystore>
<RETURN if same as keystore password>.
10. Restart the WFA services by using the Windows Services console.

Create a certificate signing request for Workflow Automation

You can create a certificate signing request (CSR) in Windows so that you can use the SSL certificate that is signed by a Certificate Authority (CA) instead of the default SSL certificate for Workflow Automation (WFA).

What you'll need

- You must have Windows admin privileges on the WFA server.
- You must have replaced the default SSL certificate that is provided by WFA.

About this task

The default WFA installation path is used in this procedure. If you have changed the default path during installation, then you must use the custom WFA installation path.

Steps

1. Log in as an admin user on the WFA host machine.
2. Open a command prompt on the WFA server, and then change directories to the following location:
`WFA_install_location\WFA\jre\bin`
3. Create a CSR:

```
keytool -certreq -keystore  
WFA_install_location\WFA\jboss\standalone\configuration\keystore\wfa.keystore  
-alias "ssl keystore" -file C:\file_name.csr
```

file_name is the name of the CSR file.

4. When prompted, provide the password (default or new).

`changeit` is the default password. If you do not want to use the default password, you must change the password attribute of the SSL element in the `standalone-full.xml` file from the `WFA_install_location\WFA\jboss\standalone\configuration\location`.

Example

```
<ssl name="ssl" password="new_password" certificate-key-  
file="{jboss.server.config.dir}/keystore/wfa.keystore"
```

5. Send the `file_name.csr` file to the CA to obtain a signed certificate.

See the CA web site for details.

6. Download a chain certificate from the CA, and then import the chain certificate to your keystore:

```
keytool -import -alias "ssl keystore CA certificate" -keystore  
"WFA_install_location\WFA\jboss\standalone\configuration\keystore\wfa.keystore  
" -trustcacerts -file C:\chain_cert.cer
```

`C:\chain_cert.cer` is the chain certificate file that is received from the CA. The file must be in the X.509 format.

7. Import the signed certificate that you received from the CA: `keytool -import -alias "ssl keystore" -keystore "WFA_install_location\WFA\jboss\standalone\configuration\keystore\wfa.keystore" -file C:\certificate.cer`

`C:\certificate.cer` is the chain certificate file that is received from the CA.

8. Start the following WFA services:

- NetApp WFA Database
- NetApp WFA Server

Copyright Information

Copyright © 2022 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system- without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP "AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at <http://www.netapp.com/TM> are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.