



Reference

Cloud Manager

NetApp
December 05, 2020

This PDF was generated from https://docs.netapp.com/us-en/occm/reference_user_roles.html on December 05, 2020. Always check docs.netapp.com for the latest.

Table of Contents

- Reference 1
- Roles 1
- How Cloud Manager uses cloud provider permissions 2
- AWS Marketplace pages for Cloud Manager and Cloud Volumes ONTAP 12

Reference

Roles

The Account Admin, Workspace Admin, and Cloud Compliance Viewer roles provide specific permissions to users.

Task	Account Admin	Workspace Admin	Cloud Compliance Viewer
Manage working environments	Yes	Yes	No
Enable services on working environments	Yes	Yes	No
View data replication status	Yes	Yes	No
View the timeline	Yes	Yes	No
Switch between workspaces	Yes	Yes	Yes
View Compliance scan results	Yes	Yes	Yes
Delete working environments	Yes	No	No
Connect Kubernetes clusters to working environments	Yes	No	No
Receive the Cloud Volumes ONTAP report	Yes	No	No
Create Connectors	Yes	No	No
Manage Cloud Central accounts	Yes	No	No
Manage credentials	Yes	No	No
Modify Cloud Manager settings	Yes	No	No
View and manage the Support Dashboard	Yes	No	No
Remove working environments from Cloud Manager	Yes	No	No
Install an HTTPS certificate	Yes	No	No

Related links

- [Setting up workspaces and users in the Cloud Central account](#)

- [Managing workspaces and users in the Cloud Central account](#)

How Cloud Manager uses cloud provider permissions

Cloud Manager requires permissions to perform actions in your cloud provider. These permissions are included in [the policies provided by NetApp](#). You might want to understand what Cloud Manager does with these permissions.

What Cloud Manager does with AWS permissions

Cloud Manager uses an AWS account to make API calls to several AWS services, including EC2, S3, CloudFormation, IAM, the Security Token Service (STS), and the Key Management Service (KMS).

Actions	Purpose
"ec2:StartInstances", "ec2:StopInstances", "ec2:DescribeInstances", "ec2:DescribeInstanceStatus", "ec2:RunInstances", "ec2:TerminateInstances", "ec2:ModifyInstanceAttribute",	Launches a Cloud Volumes ONTAP instance and stops, starts, and monitors the instance.
"ec2:DescribeInstanceAttribute",	Verifies that enhanced networking is enabled for supported instance types.
"ec2:DescribeRouteTables", "ec2:DescribeImages",	Launches a Cloud Volumes ONTAP HA configuration.
"ec2:CreateTags",	Tags every resource that Cloud Manager creates with the "WorkingEnvironment" and "WorkingEnvironmentId" tags. Cloud Manager uses these tags for maintenance and cost allocation.
"ec2:CreateVolume", "ec2:DescribeVolumes", "ec2:ModifyVolumeAttribute", "ec2:AttachVolume", "ec2>DeleteVolume", "ec2:DetachVolume",	Manages the EBS volumes that Cloud Volumes ONTAP uses as back-end storage.

Actions	Purpose
"ec2:CreateSecurityGroup", "ec2>DeleteSecurityGroup", "ec2:DescribeSecurityGroups", "ec2:RevokeSecurityGroupEgress", "ec2:AuthorizeSecurityGroupEgress", "ec2:AuthorizeSecurityGroupIngress", "ec2:RevokeSecurityGroupIngress",	Creates predefined security groups for Cloud Volumes ONTAP.
"ec2:CreateNetworkInterface", "ec2:DescribeNetworkInterfaces", "ec2>DeleteNetworkInterface", "ec2:ModifyNetworkInterfaceAttribute",	Creates and manages network interfaces for Cloud Volumes ONTAP in the target subnet.
"ec2:DescribeSubnets", "ec2:DescribeVpcs",	Gets the list of destination subnets and security groups, which is needed when creating a new working environment for Cloud Volumes ONTAP.
"ec2:DescribeDhcpOptions",	Determines DNS servers and the default domain name when launching Cloud Volumes ONTAP instances.
"ec2:CreateSnapshot", "ec2>DeleteSnapshot", "ec2:DescribeSnapshots",	Takes snapshots of EBS volumes during initial setup and whenever a Cloud Volumes ONTAP instance is stopped.
"ec2:GetConsoleOutput",	Captures the Cloud Volumes ONTAP console, which is attached to AutoSupport messages.
"ec2:DescribeKeyPairs",	Obtains the list of available key pairs when launching instances.
"ec2:DescribeRegions",	Gets a list of available AWS regions.
"ec2>DeleteTags", "ec2:DescribeTags",	Manages tags for resources associated with Cloud Volumes ONTAP instances.
"cloudformation:CreateStack", "cloudformation>DeleteStack", "cloudformation:DescribeStacks", "cloudformation:DescribeStackEvents", "cloudformation:ValidateTemplate",	Launches Cloud Volumes ONTAP instances.

Actions	Purpose
"iam:PassRole", "iam:CreateRole", "iam>DeleteRole", "iam:PutRolePolicy", "iam>CreateInstanceProfile", "iam>DeleteRolePolicy", "iam:AddRoleToInstanceProfile", "iam:RemoveRoleFromInstanceProfile", "iam>DeleteInstanceProfile",	Launches a Cloud Volumes ONTAP HA configuration.
"iam>ListInstanceProfiles", "sts:DecodeAuthorizationMessage", "ec2:AssociateIamInstanceProfile", "ec2:DescribeIamInstanceProfileAssociations", "ec2:DisassociateIamInstanceProfile",	Manages instance profiles for Cloud Volumes ONTAP instances.
"s3:GetBucketTagging", "s3:GetBucketLocation", "s3>ListAllMyBuckets", "s3>ListBucket"	Obtains information about AWS S3 buckets so Cloud Manager can integrate with the NetApp Data Fabric Cloud Sync service.
"s3>CreateBucket", "s3>DeleteBucket", "s3:GetLifecycleConfiguration", "s3:PutLifecycleConfiguration", "s3:PutBucketTagging", "s3>ListBucketVersions", "s3:GetBucketPolicyStatus", "s3:GetBucketPublicAccessBlock", "s3:GetBucketAcl", "s3:GetBucketPolicy", "s3:PutBucketPublicAccessBlock"	Manages the S3 bucket that a Cloud Volumes ONTAP system uses as a capacity tier for data tiering.
"kms:List*", "kms:ReEncrypt*", "kms:Describe*", "kms>CreateGrant",	Enables data encryption of Cloud Volumes ONTAP using the AWS Key Management Service (KMS).
"ce:GetReservationUtilization", "ce:GetDimensionValues", "ce:GetCostAndUsage", "ce:GetTags"	Obtains AWS cost data for Cloud Volumes ONTAP.

Actions	Purpose
"ec2:CreatePlacementGroup", "ec2>DeletePlacementGroup"	When you deploy an HA configuration in a single AWS Availability Zone, Cloud Manager launches the two HA nodes and the mediator in an AWS spread placement group.
"ec2:DescribeReservedInstancesOfferings"	Cloud Manager uses the permission as part of Cloud Compliance deployment to choose which instance type to use.
"s3:DeleteBucket", "s3:GetLifecycleConfiguration", "s3:PutLifecycleConfiguration", "s3:PutBucketTagging", "s3:ListBucketVersions", "s3:GetObject", "s3:ListBucket", "s3:ListAllMyBuckets", "s3:GetBucketTagging", "s3:GetBucketLocation", "s3:GetBucketPolicyStatus", "s3:GetBucketPublicAccessBlock", "s3:GetBucketAcl", "s3:GetBucketPolicy", "s3:PutBucketPublicAccessBlock"	Cloud Manager uses these permissions when you enable the Backup to S3 service.

What Cloud Manager does with Azure permissions

The Cloud Manager Azure policy includes the permissions that Cloud Manager needs to deploy and manage Cloud Volumes ONTAP in Azure.

Actions	Purpose
<p>"Microsoft.Compute/locations/operations/read", "Microsoft.Compute/locations/vmSizes/read", "Microsoft.Compute/operations/read", "Microsoft.Compute/virtualMachines/instanceView/read", "Microsoft.Compute/virtualMachines/powerOff/action", "Microsoft.Compute/virtualMachines/read", "Microsoft.Compute/virtualMachines/restart/action", "Microsoft.Compute/virtualMachines/start/action", "Microsoft.Compute/virtualMachines/deallocate/action", "Microsoft.Compute/virtualMachines/vmSizes/read", "Microsoft.Compute/virtualMachines/write",</p>	<p>Creates Cloud Volumes ONTAP and stops, starts, deletes, and obtains the status of the system.</p>
<p>"Microsoft.Compute/images/write", "Microsoft.Compute/images/read",</p>	<p>Enables Cloud Volumes ONTAP deployment from a VHD.</p>
<p>"Microsoft.Compute/disks/delete", "Microsoft.Compute/disks/read", "Microsoft.Compute/disks/write", "Microsoft.Storage/checknameavailability/read", "Microsoft.Storage/operations/read", "Microsoft.Storage/storageAccounts/listkeys/action", "Microsoft.Storage/storageAccounts/read", "Microsoft.Storage/storageAccounts/regeneratekey/action", "Microsoft.Storage/storageAccounts/write", "Microsoft.Storage/storageAccounts/delete", "Microsoft.Storage/usages/read",</p>	<p>Manages Azure storage accounts and disks, and attaches the disks to Cloud Volumes ONTAP.</p>
<p>"Microsoft.Network/networkInterfaces/read", "Microsoft.Network/networkInterfaces/write", "Microsoft.Network/networkInterfaces/join/action",</p>	<p>Creates and manages network interfaces for Cloud Volumes ONTAP in the target subnet.</p>
<p>"Microsoft.Network/networkSecurityGroups/read", ", "Microsoft.Network/networkSecurityGroups/write", ", "Microsoft.Network/networkSecurityGroups/join/action",</p>	<p>Creates predefined network security groups for Cloud Volumes ONTAP.</p>

Actions	Purpose
<p>"Microsoft.Resources/subscriptions/locations/read", ", "Microsoft.Network/locations/operationResults/read", ", "Microsoft.Network/locations/operations/read", "Microsoft.Network/virtualNetworks/read", "Microsoft.Network/virtualNetworks/checkIpAddressAvailability/read", "Microsoft.Network/virtualNetworks/subnets/read", ", "Microsoft.Network/virtualNetworks/subnets/virtualMachines/read", "Microsoft.Network/virtualNetworks/virtualMachines/read", "Microsoft.Network/virtualNetworks/subnets/join/action",</p>	<p>Gets network information about regions, the target VNet and subnet, and adds Cloud Volumes ONTAP to VNets.</p>
<p>"Microsoft.Network/virtualNetworks/subnets/write", ", "Microsoft.Network/routeTables/join/action",</p>	<p>Enables VNet service endpoints for data tiering.</p>
<p>"Microsoft.Resources/deployments/operations/read", ", "Microsoft.Resources/deployments/read", "Microsoft.Resources/deployments/write",</p>	<p>Deploys Cloud Volumes ONTAP from a template.</p>
<p>"Microsoft.Resources/deployments/operations/read", ", "Microsoft.Resources/deployments/read", "Microsoft.Resources/deployments/write", "Microsoft.Resources/resources/read", "Microsoft.Resources/subscriptions/operationresults/read", ", "Microsoft.Resources/subscriptions/resourceGroups/delete", "Microsoft.Resources/subscriptions/resourceGroups/read", "Microsoft.Resources/subscriptions/resourcegroups/resources/read", "Microsoft.Resources/subscriptions/resourceGroups/write",</p>	<p>Creates and manages resource groups for Cloud Volumes ONTAP.</p>
<p>"Microsoft.Compute/snapshots/write", "Microsoft.Compute/snapshots/read", "Microsoft.Compute/disks/beginGetAccess/action"</p>	<p>Creates and manages Azure managed snapshots.</p>

Actions	Purpose
"Microsoft.Compute/availabilitySets/write", "Microsoft.Compute/availabilitySets/read",	Creates and manages availability sets for Cloud Volumes ONTAP.
"Microsoft.MarketplaceOrdering/offertypes/publishers/offers/plans/agreements/read", "Microsoft.MarketplaceOrdering/offertypes/publishers/offers/plans/agreements/write"	Enables programmatic deployments from the Azure Marketplace.
"Microsoft.Network/loadBalancers/read", "Microsoft.Network/loadBalancers/write", "Microsoft.Network/loadBalancers/delete", "Microsoft.Network/loadBalancers/backendAddressPools/read", "Microsoft.Network/loadBalancers/backendAddressPools/join/action", "Microsoft.Network/loadBalancers/frontendIPConfigurations/read", "Microsoft.Network/loadBalancers/loadBalancingRules/read", "Microsoft.Network/loadBalancers/probes/read", "Microsoft.Network/loadBalancers/probes/join/action",	Manages an Azure load balancer for HA pairs.
"Microsoft.Authorization/locks/*"	Enables management of locks on Azure disks.
"Microsoft.Authorization/roleDefinitions/write", "Microsoft.Authorization/roleAssignments/write", "Microsoft.Web/sites/*"	Manages failover for HA pairs.
"Microsoft.Network/privateEndpoints/write", "Microsoft.Storage/storageAccounts/PrivateEndpointConnectionsApproval/action", "Microsoft.Storage/storageAccounts/privateEndpointConnections/read", "Microsoft.Network/privateEndpoints/read", "Microsoft.Network/privateDnsZones/write", "Microsoft.Network/privateDnsZones/virtualNetworkLinks/write", "Microsoft.Network/virtualNetworks/join/action", "Microsoft.Network/privateDnsZones/A/write", "Microsoft.Network/privateDnsZones/read", "Microsoft.Network/privateDnsZones/virtualNetworkLinks/read",	Enables the management of private endpoints. Private endpoints are used when connectivity isn't provided to outside the subnet. Cloud Manager creates the storage account for HA with only internal connectivity within the subnet.
"Microsoft.NetApp/netAppAccounts/capacityPools/volumes/delete",	Enables Cloud Manager to delete volumes for Azure NetApp Files.

Actions	Purpose
"Microsoft.Resources/deployments/operationStatuses/read"	Azure requires this permission for some virtual machine deployments (it depends on the underlying physical hardware that's used during deployment).
"Microsoft.Resources/deployments/operationStatuses/read", "Microsoft.Insights/Metrics/Read", "Microsoft.Compute/virtualMachines/extensions/write", "Microsoft.Compute/virtualMachines/extensions/read", "Microsoft.Compute/virtualMachines/extensions/delete", "Microsoft.Compute/virtualMachines/delete", "Microsoft.Network/networkInterfaces/delete", "Microsoft.Network/networkSecurityGroups/delete", "Microsoft.Resources/deployments/delete",	Enables you to use Global File Cache.
"Microsoft.Compute/diskEncryptionSets/read"	Enables Cloud Manager to encrypt Azure managed disks on single node Cloud Volumes ONTAP systems using external keys from another account. This feature is supported using APIs.

What Cloud Manager does with GCP permissions

The Cloud Manager policy for GCP includes the permissions that Cloud Manager needs to deploy and manage Cloud Volumes ONTAP.

Actions	Purpose
- compute.disks.create - compute.disks.createSnapshot - compute.disks.delete - compute.disks.get - compute.disks.list - compute.disks.setLabels - compute.disks.use	To create and manage disks for Cloud Volumes ONTAP.
- compute.firewalls.create - compute.firewalls.delete - compute.firewalls.get - compute.firewalls.list	To create firewall rules for Cloud Volumes ONTAP.
- compute.globalOperations.get	To get the status of operations.

Actions	Purpose
<ul style="list-style-type: none"> - compute.images.get - compute.images.getFromFamily - compute.images.list - compute.images.useReadOnly 	To get images for VM instances.
<ul style="list-style-type: none"> - compute.instances.attachDisk - compute.instances.detachDisk 	To attach and detach disks to Cloud Volumes ONTAP.
<ul style="list-style-type: none"> - compute.instances.create - compute.instances.delete 	To create and delete Cloud Volumes ONTAP VM instances.
<ul style="list-style-type: none"> - compute.instances.get 	To list VM instances.
<ul style="list-style-type: none"> - compute.instances.getSerialPortOutput 	To get console logs.
<ul style="list-style-type: none"> - compute.instances.list 	To retrieve the list of instances in a zone.
<ul style="list-style-type: none"> - compute.instances.setDeletionProtection 	To set deletion protection on the instance.
<ul style="list-style-type: none"> - compute.instances.setLabels 	To add labels.
<ul style="list-style-type: none"> - compute.instances.setMachineType 	To change the machine type for Cloud Volumes ONTAP.
<ul style="list-style-type: none"> - compute.instances.setMetadata 	To add metadata.
<ul style="list-style-type: none"> - compute.instances.setTags 	To add tags for firewall rules.
<ul style="list-style-type: none"> - compute.instances.start - compute.instances.stop - compute.instances.updateDisplayDevice 	To start and stop Cloud Volumes ONTAP.
<ul style="list-style-type: none"> - compute.machineTypes.get 	To get the numbers of cores to check quotas.
<ul style="list-style-type: none"> - compute.projects.get 	To support multi-projects.
<ul style="list-style-type: none"> - compute.snapshots.create - compute.snapshots.delete - compute.snapshots.get - compute.snapshots.list - compute.snapshots.setLabels 	To create and manage persistent disk snapshots.
<ul style="list-style-type: none"> - compute.networks.get - compute.networks.list - compute.regions.get - compute.regions.list - compute.subnetworks.get - compute.subnetworks.list - compute.zoneOperations.get - compute.zones.get - compute.zones.list 	To get the networking information needed to create a new Cloud Volumes ONTAP virtual machine instance.

Actions	Purpose
<ul style="list-style-type: none"> - deploymentmanager.compositeTypes.get - deploymentmanager.compositeTypes.list - deploymentmanager.deployments.create - deploymentmanager.deployments.delete - deploymentmanager.deployments.get - deploymentmanager.deployments.list - deploymentmanager.manifests.get - deploymentmanager.manifests.list - deploymentmanager.operations.get - deploymentmanager.operations.list - deploymentmanager.resources.get - deploymentmanager.resources.list - deploymentmanager.typeProviders.get - deploymentmanager.typeProviders.list - deploymentmanager.types.get - deploymentmanager.types.list 	<p>To deploy the Cloud Volumes ONTAP virtual machine instance using Google Cloud Deployment Manager.</p>
<ul style="list-style-type: none"> - logging.logEntries.list - logging.privateLogEntries.list 	<p>To get stack log drives.</p>
<ul style="list-style-type: none"> - resourcemanager.projects.get 	<p>To support multi-projects.</p>
<ul style="list-style-type: none"> - storage.buckets.create - storage.buckets.delete - storage.buckets.get - storage.buckets.list - storage.buckets.update 	<p>To create and manage a Google Cloud Storage bucket for data tiering.</p>
<ul style="list-style-type: none"> - cloudkms.cryptoKeyVersions.useToEncrypt - cloudkms.cryptoKeys.get - cloudkms.cryptoKeys.list - cloudkms.keyRings.list 	<p>To use customer-managed encryption keys from the Cloud Key Management Service with Cloud Volumes ONTAP.</p>
<ul style="list-style-type: none"> - compute.instances.setServiceAccount - iam.serviceAccounts.getIamPolicy - iam.serviceAccounts.list 	<p>To set a service account on the Cloud Volumes ONTAP instance. This service account provides permissions for data tiering to a Google Cloud Storage bucket.</p>

Actions	Purpose
<ul style="list-style-type: none"> - compute.addresses.list - compute.backendServices.create - compute.networks.updatePolicy - compute.regionBackendServices.create - compute.regionBackendServices.get - compute.regionBackendServices.list - iam.serviceAccounts.actAs - storage.objects.get - storage.objects.list 	<p>To deploy HA pairs.</p>

AWS Marketplace pages for Cloud Manager and Cloud Volumes ONTAP

Several offerings are available in the AWS Marketplace for Cloud Manager and Cloud Volumes ONTAP. If need help understanding the purpose of each page, read the descriptions below.

In all cases, remember that you can't launch Cloud Volumes ONTAP in AWS from the AWS Marketplace. You need to launch it directly from Cloud Manager.

Goal	AWS Marketplace page to use	More information
<p>Enable the use of Cloud Volumes ONTAP PAYGO, Cloud Tiering, Cloud Compliance, and other add-on services</p>	<p>Cloud Manager - Deploy & Manage NetApp Cloud Data Services</p>	<p>This subscription enables charging for the PAYGO version of Cloud Volumes ONTAP 9.6 and later. It also enables charging for Cloud Tiering, Cloud Compliance, and other add-on services.</p> <p>You should subscribe to this offering when Cloud Manager prompts you and redirects you to the page. Cloud Manager prompts you in the Working Environment wizard or when you add new credentials in the Settings.</p> <p>This page doesn't enable you to launch Cloud Manager in AWS. That should be done from NetApp Cloud Central, or alternatively using the AMI listed in row 3 of this table.</p>
<p>Enable the use of Cloud Volumes ONTAP PAYGO, Cloud Tiering, Cloud Compliance, and other add-on services <i>using an annual contract</i></p>	<p>Cloud Manager (Contracts) - Deploy & Manage NetApp Cloud Data Services</p>	<p>This subscription is an alternative to the subscription in the first row. It enables you to get an annual upfront payment for the listings. It's mostly for NetApp partners.</p>
<p>Deploy Cloud Manager from the AWS Marketplace using an AMI</p>	<p>Cloud Manager - Manual installation without access keys</p>	<p>We recommend that you launch Cloud Manager in AWS from NetApp Cloud Central, but you can launch it from this AWS Marketplace page, if you prefer.</p>

Goal	AWS Marketplace page to use	More information
<p>Enable deployment of Cloud Volumes ONTAP PAYGO (9.5 or earlier)</p>	<ul style="list-style-type: none"> • Cloud Volumes ONTAP for AWS • Cloud Volumes ONTAP for AWS - High Availability 	<p>These AWS Marketplace pages enable you to subscribe to the single node or HA versions of Cloud Volumes ONTAP PAYGO for versions 9.5 and earlier.</p> <p>Starting with version 9.6, you need to subscribe through the AWS Marketplace page listed in row 1 of this table for PAYGO deployments.</p>

Copyright Information

Copyright © 2020 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system-without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at <http://www.netapp.com/TM> are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.