



Prepare for installing the SnapCenter Server

SnapCenter software

NetApp
February 20, 2026

Table of Contents

- Prepare for installing the SnapCenter Server 1
 - Requirements to install SnapCenter Server 1
 - Domain and workgroup requirements for Windows host 1
 - Space and sizing requirements 1
 - SAN host requirements 3
 - Browser requirements 3
 - Port requirements 3
- Register to access the SnapCenter software 7
- Multi-factor authentication (MFA) 7
 - Manage multi-factor authentication (MFA) 7
 - Manage multi-factor authentication (MFA) using Rest API, PowerShell, and SCCLI 10
 - Configure MFA in SnapCenter Server using PowerShell, SCCLI, and REST API 14

Prepare for installing the SnapCenter Server

Requirements to install SnapCenter Server

Before you install SnapCenter Server either on Windows or Linux host, you should review and ensure that all the requirements are met for your environment.

Domain and workgroup requirements for Windows host

The SnapCenter Server can be installed on a Windows host that is either in a domain or in a workgroup.

The user having admin privileges is allowed to install the SnapCenter server.

- Active Directory domain: You must use a Domain user with local administrator rights. The Domain user must be a member of the local Administrator group on the Windows host.
- Workgroups: You must use a local account that has local administrator rights.

While domain trusts, multi-domain forests, and cross-domain trusts are supported, cross-forest domains are not supported. The Microsoft documentation about Active Directory Domains and Trusts contains more information.



After installing the SnapCenter Server, you should not change the domain in which the SnapCenter host is located. If you remove the SnapCenter Server host from the domain it was in when the SnapCenter Server was installed and then try to uninstall SnapCenter Server, the uninstall operation fails.

Space and sizing requirements

You should be familiar with the space and sizing requirements.

Item	Windows host requirements	Linux host requirements
Operating Systems	Microsoft Windows Only English, German, Japanese, and simplified Chinese version of the operating systems are supported. For the latest information about supported versions, see NetApp Interoperability Matrix Tool .	<ul style="list-style-type: none">• Red Hat Enterprise Linux (RHEL) 8 and 9• SUSE Linux Enterprise Server (SLES) 15 For the latest information about supported versions, see NetApp Interoperability Matrix Tool .
Minimum CPU count	4 cores	4 cores

Item	Windows host requirements	Linux host requirements
Minimum RAM	8 GB  The MySQL Server buffer pool uses 20 percent of the total RAM.	8 GB
Minimum hard drive space for the SnapCenter Server software and logs	7 GB  If you have the SnapCenter repository in the same drive where SnapCenter Server is installed, then it is recommended to have 15 GB.	15 GB
Minimum hard drive space for the SnapCenter repository	8 GB  NOTE: If you have the SnapCenter Server in the same drive where SnapCenter repository is installed, then it is recommended to have 15 GB.	Not applicable
Required software packages	<ul style="list-style-type: none"> • ASP.NET Core Runtime 8.0.12 (and all subsequent 8.0.x patches) Hosting Bundle • PowerShell 7.4.2 or later <p>For .NET specific troubleshooting information, see SnapCenter upgrade or install fails for legacy systems that do not have internet connectivity.</p>	<ul style="list-style-type: none"> • .NET Framework 8.0.12 (and all subsequent 8.0.x patches) • PowerShell 7.4.2 or later • Nginx is a web server that can be used as a reverse proxy • Pam-devel <p>PAM (Pluggable Authentication Modules) is a system security tool which allows system administrators to set authentication policy without having to recompile programs which do authentication.</p>



ASP.NET core needs IIS_IUSRS to access the temp file system in SnapCenter Server on Windows.

SAN host requirements

SnapCenter does not include host utilities or a DSM. If the SnapCenter host is part of a SAN (FC/iSCSI) environment, you might need to install and configure additional software on the SnapCenter Server host.

- Host Utilities: The Host Utilities support FC and iSCSI, and it enables you to use MPIO on your Windows Servers. [Learn More](#).
- Microsoft DSM for Windows MPIO: This software works with Windows MPIO drivers to manage multiple paths between NetApp and Windows host computers. A DSM is required for high availability configurations.



If you were using ONTAP DSM, you should migrate to Microsoft DSM. For more information, see [How to migrate from ONTAP DSM to Microsoft DSM](#).

Browser requirements

SnapCenter software supports Chrome 125 and later and Microsoft Edge 110.0.1587.17 and later.

Port requirements

The SnapCenter software requires different ports for communication between different components.

- Applications cannot share a port.
- For customizable ports, you can select a custom port during installation if you do not want to use the default port.
- For fixed ports, you should accept the default port number.
- Firewalls
 - Firewalls, proxies, or other network devices should not interfere with connections.
 - If you specify a custom port when you install SnapCenter, you should add a firewall rule on the plug-in host for that port for the SnapCenter Plug-in Loader.

The following table lists the different ports and their default values.

Port Name	Port Numbers	Protocol	Direction	Description
SnapCenter web port	8146	HTTPS	Bidirectional	<p>This port is used for communication between the SnapCenter client (the SnapCenter user) and the SnapCenter Server and is also used for communication from the plug-in hosts to the SnapCenter Server.</p> <p>You can customize the port number.</p>
SnapCenter SMCORE communication port	8145	HTTPS	Bidirectional	<p>This port is used for communication between the SnapCenter Server and the hosts where the SnapCenter plug-ins are installed.</p> <p>You can customize the port number.</p>
Scheduler Service Port	8154	HTTPS		<p>This is port is used to orchestrate the SnapCenter scheduler workflows for all the managed plug-ins within the SnapCenter server host in centralized manner.</p> <p>You can customize the port number.</p>
RabbitMQ Port	5672	TCP		<p>This is the default port that RabbitMQ listens on and it is used for publisher-subscriber model communication between Scheduler service and SnapCenter.</p>

Port Name	Port Numbers	Protocol	Direction	Description
MySQL port	3306	HTTPS		The port is used for communicating with SnapCenter repository database. You can create secured connections from the SnapCenter Server to the MySQL server. Learn more
Windows plug-in hosts	135, 445	TCP		This port is used for communication between the SnapCenter Server and the host on which the plug-in is being installed. Additional dynamic port range specified by Microsoft should also be open.
Linux or AIX plug-in hosts	22	SSH	Unidirectional	This port is used for communication between the SnapCenter Server and the host, initiated from the server to client host.
SnapCenter Plug-ins Package for Windows, Linux or AIX	8145	HTTPS	Bidirectional	This port is used for communication between SMCORE and hosts where the plug-ins package is installed. Customizable. You can customize the port number.
SnapCenter Plug-in for Oracle Database	27216			The default JDBC port is used by the plug-in for Oracle for connecting to the Oracle database.

Port Name	Port Numbers	Protocol	Direction	Description
SnapCenter Plug-in for Exchange Database	909			The default NET.TCP port is used by the plug-in for Windows for connecting to the Exchange VSS call-backs.
NetApp supported plug-ins for SnapCenter	9090	HTTPS		<p>This is an internal port that is used only on the plug-in host; no firewall exception is required.</p> <p>Communication between the SnapCenter Server and plug-ins is routed through port 8145.</p>
ONTAP cluster or SVM communication port	<ul style="list-style-type: none"> • 443 (HTTPS) • 80 (HTTP) 	<ul style="list-style-type: none"> • HTTPS • HTTP 	Bidirectional	The port is used by the SAL (Storage Abstraction Layer) for communication between the host running SnapCenter Server and SVM. The port is currently also used by the SAL on SnapCenter for Windows Plug-in hosts for communication between the SnapCenter plug-in host and SVM.
SnapCenter Plug-in for SAP HANA Database	<ul style="list-style-type: none"> • 3instance_number13 • 3instance_number15 	<ul style="list-style-type: none"> • HTTPS • HTTP 	Bidirectional	<p>For a multitenant database container (MDC) single tenant, the port number ends with 13; for non MDC, the port number ends with 15.</p> <p>You can customize the port number.</p>

Port Name	Port Numbers	Protocol	Direction	Description
SnapCenter Plug-in for PostgreSQL	5432			<p>This port is the default PostgreSQL port used for communication by the plug-in for PostgreSQL to the PostgreSQL cluster.</p> <p>You can customize the port number.</p>

Register to access the SnapCenter software

You should register to access the SnapCenter software if you are new to Amazon FSx for NetApp ONTAP or Azure NetApp Files and do not have an existing NetApp account.

Before you begin

- You should have access to the corporate email ID.
- If you using Azure NetApp Files, you should have the Azure subscription ID.
- If you are using Amazon FSx for NetApp ONTAP, you should have the File System ID of your FSx for ONTAP file system.

About this task

Your registration is subject to information validations and may take up to a day to confirm and upgrade new NetApp Support Site (NSS) account to **full** access from **guest** access.

Steps

1. Click <https://mysupport.netapp.com/site/user/registration> for registration.
2. Enter your corporate email ID, complete the captcha, accept NetApp's privacy policy, and click **Submit**.
3. Authenticate the registration by entering the OTP sent to your email ID and click **Continue**.
4. On the registration completion page, enter the following details to complete the registration.
 - a. Select **NetApp Customer / End User**.
 - b. In the SERIAL NUMBER field, either enter the Azure subscription ID if you are using Azure NetApp Files or the File System ID if you are using Amazon FSx for NetApp ONTAP.



You can raise a ticket at <https://mysupport.netapp.com/site/help> if you face any issue during registration or to know the status.

Multi-factor authentication (MFA)

Manage multi-factor authentication (MFA)

You can manage Multi-factor authentication (MFA) functionality in the Active Directory Federation Service (AD FS) Server and SnapCenter Server.

Enable multi-factor authentication (MFA)

You can enable MFA functionality for SnapCenter Server using PowerShell commands.

About this task

- SnapCenter supports SSO based logins when other applications are configured in the same AD FS. In certain AD FS configurations, SnapCenter might require user authentication for security reasons depending on the AD FS session persistence.
- The information regarding the parameters that can be used with the cmdlet and their descriptions can be obtained by running `Get-Help command_name`. Alternatively, you can also see [SnapCenter Software Cmdlet Reference Guide](#).

Before you begin

- Windows Active Directory Federation Service (AD FS) should be up and running in the respective domain.
- You should have an AD FS supported Multi-factor authentication service such as Azure MFA, Cisco Duo, and so on.
- SnapCenter and AD FS server timestamp should be the same regardless of the timezone.
- Procure and configure the authorized CA certificate for SnapCenter Server.

CA Certificate is mandatory for the following reasons:

- Ensures that the ADFS-F5 communications do not break because the self-signed certificates are unique at the node level.
- Ensures that during upgrade, repair, or disaster recovery (DR) in a standalone or high availability configuration, the self-signed certificate does not get recreated thus avoiding MFA reconfiguration.
- Ensures IP-FQDN resolutions.

For information on CA certificate, see [Generate CA Certificate CSR file](#).

Steps

1. Connect to the Active Directory Federation Services (AD FS) host.
2. Download AD FS federation metadata file from "https://<host FQDN>/FederationMetadata/2007-06/FederationMetadata.xml".
3. Copy the downloaded file to SnapCenter Server to enable MFA feature.
4. Log in to SnapCenter Server as the SnapCenter Administrator user through PowerShell.
5. Using the PowerShell session, generate the SnapCenter MFA metadata file by using the `New-SmMultifactorAuthenticationMetadata -path` cmdlet.

The path parameter specifies the path to save the MFA metadata file in the SnapCenter Server host.

6. Copy the generated file to the AD FS host to configure SnapCenter as the client entity.
7. Enable MFA for SnapCenter Server using the `Set-SmMultiFactorAuthentication` cmdlet.
8. (Optional) Check the MFA configuration status and settings by using `Get-SmMultiFactorAuthentication` cmdlet.
9. Go to the Microsoft management console (MMC) and perform the following steps:
 - a. Click **File > Add/Remove Snapin**.

- b. In the Add or Remove Snap-ins window, select **Certificates** and then click **Add**.
- c. In the Certificates snap-in window, select the **Computer account** option, and then click **Finish**.
- d. Click **Console Root > Certificates – Local Computer > Personal > Certificates**.
- e. Right-click on the CA certificate bound to SnapCenter and then select **All Tasks > Manage Private Keys**.
- f. On the permissions wizard perform the following steps:
 - i. Click **Add**.
 - ii. Click **Locations** and select the concerned host (top of hierarchy).
 - iii. Click **OK** in the **Locations** pop-up window.
 - iv. In the object name field, enter 'IIS_IUSRS' and click **Check Names** and click **OK**.

If the check is successful, click **OK**.

10. In the AD FS host, open AD FS management wizard and perform the following steps:
 - a. Right click on **Relying Party Trusts > Add Relying Party Trust > Start**.
 - b. Select the second option and browse the SnapCenter MFA Metadata file and click **Next**.
 - c. Specify a display name and click **Next**.
 - d. Choose an access control policy as required and click **Next**.
 - e. Select the settings in the next tab to default.
 - f. Click **Finish**.

SnapCenter is now reflected as a relying party with the provided display name.

11. Select the name and perform the following steps:
 - a. Click **Edit Claim Issuance Policy**.
 - b. Click **Add Rule** and click **Next**.
 - c. Specify a name for the claim rule.
 - d. Select **Active Directory** as the attribute store.
 - e. Select the attribute as **User-Principal-Name** and the outgoing claim type as **Name-ID**.
 - f. Click **Finish**.

12. Run the following PowerShell commands on the ADFS server.

```
Set-AdfsRelyingPartyTrust -TargetName '<Display name of relying party >'
-SigningCertificateRevocationCheck None
```

```
Set-AdfsRelyingPartyTrust -TargetName '<Display name of relying party >'
-EncryptionCertificateRevocationCheck None
```

13. Perform the following steps to confirm that the metadata was imported successfully.
 - a. Right-click the relying party trust and select **Properties**.
 - b. Ensure that the Endpoints, Identifiers, and Signature fields are populated.
14. Close all the browser tabs and reopen a browser to clear the existing or active session cookies, and login again.

SnapCenter MFA functionality can also be enabled using REST APIs.

For troubleshooting information, see [Simultaneous login attempts in multiple tabs shows MFA error](#).

Update AD FS MFA Metadata

You should update the AD FS MFA metadata in SnapCenter whenever there is any modification in the AD FS Server, such as upgrade, CA certificate renewal, DR, and so on.

Steps

1. Download AD FS federation metadata file from "https://<host FQDN>/FederationMetadata/2007-06/FederationMetadata.xml"
2. Copy the downloaded file to SnapCenter Server to update the MFA configuration.
3. Update the AD FS metadata in SnapCenter by running the following cmdlet:

```
Set-SmMultiFactorAuthentication -Path <location of ADFS MFA metadata xml file>
```

4. Close all the browser tabs and reopen a browser to clear the existing or active session cookies, and login again.

Update SnapCenter MFA metadata

You should update the SnapCenter MFA metadata in AD FS whenever there is any modification in ADFS server such as repair, CA certificate renewal, DR, and so on.

Steps

1. In the AD FS host, open AD FS management wizard and perform the following steps:
 - a. Select **Relying Party Trusts**.
 - b. Right click on the relying party trust that was created for SnapCenter and select **Delete**.

The user defined name of the relying party trust will be displayed.

- c. Enable Multi-factor authentication (MFA).

See [Enable Multi-factor authentication](#).

2. Close all the browser tabs and reopen a browser to clear the existing or active session cookies, and login again.

Disable Multi-factor authentication (MFA)

Steps

1. Disable MFA and clean up the configuration files that were created when MFA was enabled by using the `Set-SmMultiFactorAuthentication` cmdlet.
2. Close all the browser tabs and reopen a browser to clear the existing or active session cookies, and login again.

Manage multi-factor authentication (MFA) using Rest API, PowerShell, and SCCLI

MFA login is supported from browser, REST API, PowerShell, and SCCLI. MFA is supported through an AD FS identity manager. You can enable MFA, disable MFA, and

configure MFA from GUI, REST API, PowerShell, and SCCLI.

Setup AD FS as OAuth/OIDC

Configure AD FS using Windows GUI wizard

1. Navigate to **Server Manager Dashboard > Tools > ADFS Management**.

2. Navigate to **ADFS > Application Groups**.

- a. Right-click on **Application Groups**.
- b. Select **Add Application group** and enter **Application Name**.
- c. Select **Server Application**.
- d. Click **Next**.

3. Copy **Client Identifier**.

This is the Client ID. ... Add Callback URL (SnapCenter Server URL) in Redirect URL. ... Click **Next**.

4. Select **Generate shared secret**.

Copy the secret value. This is the client's secret. .. Click **Next**.

5. On the **Summary** page, click **Next**.

- a. On the **Complete** page, click **Close**.

6. Right-click on the newly added **Application Group** and select **Properties**.

7. Select **Add application** from App Properties.

8. Click **Add application**.

Select Web API and click **Next**.

9. On the Configure Web API page, enter the SnapCenter Server URL and Client Identifier created in the previous step into the Identifier section.

- a. Click **Add**.
- b. Click **Next**.

10. On the **Choose Access Control Policy** page, select control policy based on your requirement (For example, Permit everyone and require MFA) and click **Next**.

11. On the **Configure Application Permission** page, by default openid is selected as a scope, click **Next**.

12. On the **Summary** page, click **Next**.

On the **Complete** page, click **Close**.

13. On the **Sample Application Properties** page, click **OK**.

14. JWT token issued by an authorization server (AD FS) and intended to be consumed by the resource.

The 'aud' or audience claim of this token must match the identifier of the resource or Web API.

15. Edit the selected WebAPI and check that Callback URL (SnapCenter Server URL) and the client identifier were added correctly.

Configure OpenID Connect to provide a username as claims.

16. Open the **AD FS Management** tool located under the **Tools** menu at the top right of the Server Manager.
 - a. Select the **Application Groups** folder from the left sidebar.
 - b. Select the Web API and click **EDIT**.
 - c. Go-to Issuance Transform Rules Tab
17. Click **Add Rule**.
 - a. Select the **Send LDAP Attributes as Claims** in the Claim rule template dropdown.
 - b. Click **Next**.
18. Enter the **Claim rule** name.
 - a. Select **Active Directory** in the Attribute store dropdown.
 - b. Select **User-Principal-Name** in the **LDAP Attribute** dropdown and **UPN** in the O*utgoing Claim Type* dropdown.
 - c. Click **Finish**.

Create Application Group using PowerShell commands

You can create the application group, web API, and add the scope and claims using PowerShell commands. These commands are available in automated script format. For more information see [<link to KB article>](#).

1. Create the new Application Group in AD FS by using the following comamnd.

```
New-AdfsApplicationGroup -Name $ClientRoleIdentifier
-ApplicationGroupIdentifier $ClientRoleIdentifier
```

ClientRoleIdentifier name of your application group

redirectURL valid URL for redirection after authorization

2. Create the AD FS Server Application and generate the client secret.

```
Add-AdfsServerApplication -Name "$ClientRoleIdentifier - Server app"
-ApplicationGroupIdentifier $ClientRoleIdentifier -RedirectUri $redirectURL
-Identifier $identifier -GenerateClientSecret
```

3. Create the ADFS Web API application and configure the policy name it should use.

```
$identifier = (New-Guid).Guid
```

```
Add-AdfsWebApiApplication -ApplicationGroupIdentifier $ClientRoleIdentifier
-Name "App Web API"
```

```
-Identifier $identifier -AccessControlPolicyName "Permit everyone"
```

4. Get the client ID and client secret from the output of the following commands because, it is shown only one time.

```
"client_id = $identifier"
```

```
"client_secret: "$($ADFSApp.ClientSecret)
```

5. Grant the AD FS Application the allatclaims and openid permissions.

```
Grant-AdfsApplicationPermission -ClientRoleIdentifier $identifier
-ServerRoleIdentifier $identifier -ScopeNames @('openid')

$transformrule = @"

@RuleTemplate = "LdapClaims"

@RuleName = "AD User properties and Groups"

c:[Type ==
"http://schemas.microsoft.com/ws/2008/06/identity/claims/windowsaccountname",
Issuer ==

"AD AUTHORITY"]

⇒ issue(store = "Active Directory", types =
("http://schemas.xmlsoap.org/ws/2005/05/identity/claims/upn"), query =
";userPrincipalName;{0}", param = c.Value);

"@
```

6. Write out the transform rules file.

```
$transformrule | Out-File -FilePath .\issueancetransformrules.tmp -force
-Encoding ascii $relativePath = Get-Item .\issueancetransformrules.tmp
```

7. Name the Web API Application and define its Issuance Transform Rules using an external file.

```
Set-AdfsWebApiApplication -Name "$ClientRoleIdentifier - Web API"
-TargetIdentifier

$identifier -Identifier $identifier,$redirectURL -IssuanceTransformRulesFile

$relativePath
```

Update access token expiry time

You can update the access token expiry time using the PowerShell command.

About this task

- An access token can be used only for a specific combination of user, client, and resource. Access tokens cannot be revoked and are valid until their expiry.
- By default, the expiry time of an access token is 60 minutes. This minimal expiry time is sufficient and scaled. You must provide sufficient value to avoid any ongoing business-critical jobs.

Step

To update the access token expiry time for an application group WebApi, use the following command in AD FS server.

```
+ Set-AdfsWebApiApplication -TokenLifetime 3600 -TargetName "<Web API>"
```

Get the bearer token from AD FS

You should fill the below-mentioned parameters in any REST client (like Postman) and it prompts you to fill in the user credentials. Additionally, you should enter the second-factor authentication (something you have & something you are) to get the bearer token.

+ The validity of the bearer token is configurable from the AD FS server per application and the default validity period is 60 minutes.

Field	Value
Grant type	Authorization Code
Callback URL	Enter your application's base URL if you do not have a callback URL.
Auth URL	[adfs-domain-name]/adfs/oauth2/authorize
Access token URL	[adfs-domain-name]/adfs/oauth2/token
Client ID	Enter the AD FS client ID
Client secret	Enter the AD FS client secret
Scope	OpenID
Client Authentication	Send as Basic AUTH Header
Resource	In the Advance Options tab, add the Resource field with the same value as the Callback URL, which comes as an "aud" value in the JWT token.

Configure MFA in SnapCenter Server using PowerShell, SCCLI, and REST API

You can configure MFA in SnapCenter Server using PowerShell, SCCLI, and REST API.

SnapCenter MFA CLI authentication

In PowerShell and SCCLI, the existing cmdlet (Open-SmConnection) is extended with one more field called "AccessToken" to use the bearer token to authenticate the user.

```
Open-SmConnection -Credential <PSCredential> [-SMSbaseUrl <String>] [-Port <String>] [-RoleName <String>] [-AccessToken <string>]
```

After the above cmdlet is executed, a session is created for the respective user to execute further SnapCenter cmdlets.

SnapCenter MFA Rest API Authentication

Use bearer token in the format *Authorization=Bearer <access token>* in REST API client (like Postman or swagger) and mention the user RoleName in the header to get a successful response from SnapCenter.

MFA Rest API Workflow

When MFA is configured with AD FS, you should authenticate using an access (bearer) token to access the SnapCenter application by any Rest API.

About this task

- You can use any REST client like Postman, Swagger UI or FireCamp.
- Get an access token and use it to authenticate subsequent requests (SnapCenter Rest API) to perform any operation.

Steps

To authenticate through AD FS MFA

1. Configure the REST client to call AD FS endpoint to get the access token.

When you hit the button to get an access token for an application, you will be redirected to the AD FS SSO page where you must provide your AD credentials and authenticate with MFA. 1. In the AD FS SSO page, type your username or email in the Username text box.

+ Usernames must be formatted as user@domain or domain\user.

2. In the Password text box, type your password.
3. Click **Log in**.
4. From the **Sign-in Options** section, select an authentication option and authenticate (depending on your configuration).
 - Push: Approve the push notification that is sent to your phone.
 - QR Code: Use the AUTH Point mobile app to scan the QR code, then type the verification code shown in the app
 - One-Time Password: Type the one-time password for your token.
5. After successful authentication, a popup will open that contains the Access, ID, and Refresh Token.

Copy the access token and use it in the SnapCenter Rest API to perform the operation.

6. In the Rest API, you should pass the access token and role name in the header section.
7. SnapCenter validates this access token from AD FS.

If it is a valid token, SnapCenter decodes it and gets the username.

8. Using the Username and Role Name, SnapCenter authenticates the user for an API execution.

If the authentication succeeds, SnapCenter returns the result else an error message is displayed.

Enable or disable SnapCenter MFA functionality for Rest API, CLI, and GUI

GUI

Steps

1. Log into the SnapCenter Server as the SnapCenter Administrator.
2. Click **Settings > Global Settings > MultiFactorAuthentication(MFA) Settings**
3. Select the interface (GUI/RST API/CLI) to enable or disable the MFA login.

PowerShell interface

Steps

1. Run the PowerShell or CLI commands for enabling MFA for GUI, Rest API, PowerShell, and SCCLI.

```
Set-SmMultiFactorAuthentication -IsGuiMFAEnabled -IsRestApiMFAEnabled  
-IsCliMFAEnabled -Path
```

The path parameter specifies the location of the AD FS MFA metadata xml file.

Enables MFA for SnapCenter GUI, Rest API, PowerShell, and SCCLI configured with specified AD FS metadata file path.

2. Check the MFA configuration status and settings by using the `Get-SmMultiFactorAuthentication` cmdlet.

SCCLI Interface

Steps

1. # `sccli Set-SmMultiFactorAuthentication -IsGuiMFAEnabled true -IsRESTAPIMFAEnabled true -IsCliMFAEnabled true -Path "C:\ADFS_metadata\abc.xml"`
2. # `sccli Get-SmMultiFactorAuthentication`

REST APIs

1. Run the following post API for enabling MFA for GUI, Rest API, PowerShell, and SCCLI.

Parameter	Value
Requested URL	/api/4.9/settings/multifactorauthentication
HTTP method	Post
Request Body	{ "IsGuiMFAEnabled": false, "IsRestApiMFAEnabled": true, "IsCliMFAEnabled": false, "ADFSConfigFilePath": "C:\ADFS_metadata\abc.xml" }

Response Body	<pre>{ "MFAConfiguration": { "IsGuiMFAEnabled": false, "ADFSSConfigFilePath": "C:\\ADFS_metadata\\abc.xml", "SCConfigFilePath": null, "IsRestApiMFAEnabled": true, "IsCliMFAEnabled": false, "ADFSHostName": "win-adfs-sc49.winscedom2.com" } }</pre>
---------------	-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------

2. Check the MFA configuration status and settings by using the following API.

Parameter	Value
Requested URL	/api/4.9/settings/multifactorauthentication
HTTP method	Get
Response Body	<pre>{ "MFAConfiguration": { "IsGuiMFAEnabled": false, "ADFSSConfigFilePath": "C:\\ADFS_metadata\\abc.xml", "SCConfigFilePath": null, "IsRestApiMFAEnabled": true, "IsCliMFAEnabled": false, "ADFSHostName": "win-adfs-sc49.winscedom2.com" } }</pre>

Copyright information

Copyright © 2026 NetApp, Inc. All Rights Reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means—graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system—without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

LIMITED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (b)(3) of the Rights in Technical Data -Noncommercial Items at DFARS 252.227-7013 (FEB 2014) and FAR 52.227-19 (DEC 2007).

Data contained herein pertains to a commercial product and/or commercial service (as defined in FAR 2.101) and is proprietary to NetApp, Inc. All NetApp technical data and computer software provided under this Agreement is commercial in nature and developed solely at private expense. The U.S. Government has a non-exclusive, non-transferrable, nonsublicensable, worldwide, limited irrevocable license to use the Data only in connection with and in support of the U.S. Government contract under which the Data was delivered. Except as provided herein, the Data may not be used, disclosed, reproduced, modified, performed, or displayed without the prior written approval of NetApp, Inc. United States Government license rights for the Department of Defense are limited to those rights identified in DFARS clause 252.227-7015(b) (FEB 2014).

Trademark information

NETAPP, the NETAPP logo, and the marks listed at <http://www.netapp.com/TM> are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.