



Recovering from a disaster at the 7-Mode site during transition

ONTAP 7-Mode Transition

NetApp
May 31, 2021

This PDF was generated from https://docs.netapp.com/us-en/ontap-7mode-transition/snapmirror/task_redirecting_clients_to_clustered_ontap_secondary_volume.html on May 31, 2021. Always check docs.netapp.com for the latest.

Table of Contents

- Recovering from a disaster at the 7-Mode site during transition 1
 - Redirecting clients to the clustered Data ONTAP secondary volume after a disaster 1
 - Transitioning the 7-Mode primary as a stand-alone volume 2
 - Redirecting clients to the clustered Data ONTAP primary volume 9

Recovering from a disaster at the 7-Mode site during transition

If you have established a SnapMirror disaster recovery (DR) relationship between the 7-Mode primary volume and the clustered Data ONTAP secondary volume and if a disaster occurs at the 7-Mode primary site, you can direct client access to the clustered Data ONTAP secondary volume. After the 7-Mode primary volume is brought back online, you have to perform additional steps to redirect the clients to the clustered Data ONTAP primary volume.

To retain any data written on the clustered Data ONTAP secondary volume after the disaster, you must transition the 7-Mode primary volume after the 7-Mode primary volume is back online and establish a SnapMirror relationship between the clustered Data ONTAP primary and secondary volumes. You can then redirect the clients to the clustered Data ONTAP primary volumes.

SnapMirror resynchronization from clustered Data ONTAP volumes to the 7-Mode volumes is not supported. Therefore, if you reestablish the DR relationship between the 7-Mode primary volume and the clustered Data ONTAP secondary volume after the disaster, any data written on the secondary clustered Data ONTAP will be lost.

Redirecting clients to the clustered Data ONTAP secondary volume after a disaster

If you have established a SnapMirror disaster recovery (DR) relationship between the 7-Mode primary volume and the clustered Data ONTAP secondary volume and if a disaster occurs at the 7-Mode primary site, you must redirect client access to the clustered Data ONTAP secondary volume.

Steps

1. From the secondary cluster, use the `snapmirror break` command to break the SnapMirror relationship between the 7-Mode primary volume and the clustered Data ONTAP secondary volume.

```
sec_cluster::> snapmirror break -destination-path dst_vserver:dst_c_vol
```

2. From the secondary cluster, use the `snapmirror delete` command to delete the SnapMirror relationship between the 7-Mode primary volume and the clustered Data ONTAP secondary volume.

```
sec_cluster::> snapmirror delete -destination-path dst_vserver:dst_c_vol
```

3. Redirect client access to the clustered Data ONTAP secondary volume.

For more information about setting up client access in clustered Data ONTAP, see the [Clustered Data ONTAP File Access and Protocols Management Guide](#).

Transitioning the 7-Mode primary as a stand-alone volume

After the 7-Mode primary volume is back online after a disaster, you must transition the 7-Mode primary volume. Because all SnapMirror relationships to the 7-Mode primary volume are broken and deleted at this stage, you can transition a stand-alone volume for this type of transition.

Steps

1. Copy data from the 7-Mode volume to the clustered Data ONTAP volume:

- a. If you want to configure the TCP window size for the SnapMirror relationship between the 7-Mode system and the SVM, create a SnapMirror policy of type `async-mirror` with the `window-size-for-tdp-mirror` option.

You must then apply this policy to the TDP SnapMirror relationship between the 7-Mode system and the SVM.

You can configure the TCP window size in the range of 256 KB to 7 MB for improving the SnapMirror transfer throughput so that the transition copy operations get completed faster. The default value of TCP window size is 2 MB.

```
cluster1::> snapmirror policy create -vserver vs1 -policy tdp_policy
-window-size-for-tdp-mirror 5MB -type async-mirror
```

- b. Use the `snapmirror create` command with the relationship type as TDP to create a SnapMirror relationship between the 7-Mode system and the SVM.

If you have created a SnapMirror policy to configure the TCP window size, you must apply the policy to this SnapMirror relationship.

```
cluster1::> snapmirror create -source-path system7mode:dataVol120
-destination-path vs1:dst_vol -type TDP -policy tdp_policy
Operation succeeded: snapmirror create the relationship with
destination vs1:dst_vol.
```

- c. Use the `snapmirror initialize` command to start the baseline transfer.

```
cluster1::> snapmirror initialize -destination-path vs1:dst_vol
Operation is queued: snapmirror initialize of destination
vs1:dst_vol.
```

- d. Use the `snapmirror show` command to monitor the status.

```
cluster1::> snapmirror show -destination-path vs1:dst_vol
-----
Source Path: system7mode:dataVol120
```

```
Destination Path: vs1:dst_vol
Relationship Type: TDP
Relationship Group Type: none
SnapMirror Schedule: -
SnapMirror Policy Type: async-mirror
SnapMirror Policy: DPDefault
Tries Limit: -
Throttle (KB/sec): unlimited
**Mirror State: Snapmirrored**
Relationship Status: Idle
File Restore File Count: -
File Restore File List: -
Transfer Snapshot: -
Snapshot Progress: -
Total Progress: -
Network Compression Ratio: -
Snapshot Checkpoint: -
Newest Snapshot: vs1(4080431166)_dst_vol.1
Newest Snapshot Timestamp: 10/16 02:49:03
Exported Snapshot: vs1(4080431166)_dst_vol.1
Exported Snapshot Timestamp: 10/16 02:49:03
Healthy: true
Unhealthy Reason: -
Constituent Relationship: false
Destination Volume Node: cluster1-01
Relationship ID: 97b205a1-54ff-11e4-9f30-
005056a68289
Current Operation ID: -
Transfer Type: -
Transfer Error: -
Current Throttle: -
Current Transfer Priority: -
Last Transfer Type: initialize
Last Transfer Error: -
Last Transfer Size: 152KB
Last Transfer Network Compression Ratio: 1:1
Last Transfer Duration: 0:0:6
Last Transfer From: system7mode:dataVol20
Last Transfer End Timestamp: 10/16 02:43:53
Progress Last Updated: -
Relationship Capability: 8.2 and above
Lag Time: -
Number of Successful Updates: 0
Number of Failed Updates: 0
Number of Successful Resyncs: 0
Number of Failed Resyncs: 0
```

```
Number of Successful Breaks: 0
Number of Failed Breaks: 0
Total Transfer Bytes: 155648
Total Transfer Time in Seconds: 6
```

- e. Depending on whether you want to update the clustered Data ONTAP volume manually or by setting up a SnapMirror schedule, perform the appropriate action:

If you want to...	Then...
Update transfers manually	<p data-bbox="886 159 1442 193">i. Use the <code>snapmirror update</code> command.</p> <pre data-bbox="915 226 1484 365">cluster1::> snapmirror update -destination-path vs1:dst_vol</pre> <p data-bbox="886 403 1490 470">ii. Use the <code>snapmirror show</code> command to monitor the data copy status.</p> <pre data-bbox="915 504 1484 2066">cluster1::> snapmirror show -destination-path vs1:dst_vol Source Path: system7mode:dataVol20 Destination Path: vs1:dst_vol Relationship Type: TDP Relationship Group Type: none SnapMirror Schedule: - SnapMirror Policy Type: async-mirror SnapMirror Policy: DPDefault Tries Limit: - Throttle (KB/sec): unlimited Mirror State: Snapmirrored ... Number of Failed Updates: 0 Number of Successful Resyncs: 0 Number of Failed Resyncs: 0 Number of Successful Breaks: 0 Number of Failed Breaks: 0 Total Transfer Bytes: 278528 Total Transfer Time in Seconds: 11</pre>

If you want to...	Then...
Perform scheduled update transfers	<p data-bbox="883 159 1487 260">i. Use the <code>job schedule cron create</code> command to create a schedule for update transfers.</p> <pre data-bbox="915 296 1487 474">cluster1::> job schedule cron create -name 15_minute_sched -minute 15</pre> <p data-bbox="883 510 1487 611">ii. Use the <code>snapmirror modify</code> command to apply the schedule to the SnapMirror relationship.</p> <pre data-bbox="915 646 1487 825">cluster1::> snapmirror modify -destination-path vs1:dst_vol -schedule 15_minute_sched</pre> <p data-bbox="883 861 1487 921">iii. Use the <code>snapmirror show</code> command to monitor the data copy status.</p>

2. If you have a schedule for incremental transfers, perform the following steps when you are ready to perform cutover:

a. Use the `snapmirror quiesce` command to disable all future update transfers.

```
cluster1::> snapmirror show
-destination-path vs1:dst_vol
```

```
cluster1::> snapmirror quiesce -destination-path vs1:dst_vol
```

b. Use the `snapmirror modify` command to delete the SnapMirror schedule.

```
cluster1::> snapmirror modify -destination-path vs1:dst_vol -schedule
""
```

c. If you quiesced the SnapMirror transfers earlier, use the `snapmirror resume` command to enable SnapMirror transfers.

```
cluster1::> snapmirror resume -destination-path vs1:dst_vol
```

3. Wait for any ongoing transfers between the 7-Mode volumes and the clustered Data ONTAP volumes to finish, and then disconnect client access from the 7-Mode volumes to start cutover.

4. Use the `snapmirror update` command to perform a final data update to the clustered Data ONTAP volume.

```
cluster1::> snapmirror update -destination-path vs1:dst_vol
Operation is queued: snapmirror update of destination vs1:dst_vol.
```

5. Use the `snapmirror show` command to verify that the last transfer was successful.

6. Use the `snapmirror break` command to break the SnapMirror relationship between the 7-Mode volume and the clustered Data ONTAP volume.

```
cluster1::> snapmirror break -destination-path vs1:dst_vol
[Job 60] Job succeeded: SnapMirror Break Succeeded
```

7. If your volumes have LUNs configured, at the advanced privilege level, use the `lun transition 7-mode show` command to verify that the LUNs were transitioned.

You can also use the `lun show` command on the clustered Data ONTAP volume to view all of the LUNs that were successfully transitioned.

8. Use the `snapmirror delete` command to delete the SnapMirror relationship between the 7-Mode volume and the clustered Data ONTAP volume.

```
cluster1::> snapmirror delete -destination-path vs1:dst_vol
```

9. Use the `snapmirror release` command to remove the SnapMirror relationship information from the 7-Mode system.

```
system7mode> snapmirror release dataVol20 vs1:dst_vol
```

Redirecting clients to the clustered Data ONTAP primary volume

After the 7-Mode primary volume comes back online, you can transition the 7-Mode primary volume, establish a SnapMirror relationship with the clustered Data ONTAP secondary volume, and redirect client access to the clustered Data ONTAP primary volume.

Steps

1. Create the SVM peer relationship between the primary and secondary SVMs.
 - a. Use the `cluster peer create` command to create the cluster peer relationship.

```
pri_cluster::> cluster peer create -peer-addr cluster2-d2,
10.98.234.246 -timeout 60
```

Notice: Choose a passphrase of 8 or more characters. To ensure the authenticity of the peering relationship, use a phrase or sequence of characters that would be hard to guess.

```
Enter the passphrase: *****
Confirm the passphrase: *****
```

- b. From the source cluster, use the `vserver peer create` command to create an SVM peer relationship between the clustered Data ONTAP primary volume and clustered Data ONTAP secondary volume.

```
pri_cluster::> vserver peer create -vserver src_vserver -peervserver
src_c_vserver -applications snapmirror -peer-cluster sec_cluster
```

- c. From the destination cluster, use the `vserver peer accept` command to accept the SVM peer request and establish the SVM peer relationship.

```
sec_cluster::> vserver peer accept -vserver dst_vserver -peervserver
src_vserver
```

2. Use the `snapmirror create` command to create a SnapMirror relationship with the clustered Data ONTAP secondary volume as the source and the clustered Data ONTAP primary volume as destination.

```
pri_cluster::> snapmirror create -source-path dst_vserver:dst_c_vol  
-destination-path src_vserver:src_c_vol
```

3. From the primary cluster, use the `snapmirror resync` command to resynchronize the clustered Data ONTAP secondary volume.

```
pri_cluster::> snapmirror resync -source-path dst_vserver:dst_c_vol  
-destination-path src_vserver:src_c_vol
```

You must wait till the resynchronization finishes. The SnapMirror state changes to `SnapMirrored` when resynchronization is complete.

4. When you are ready to switch over to the clustered Data ONTAP primary volume, disconnect client access from the clustered Data ONTAP secondary volume.
5. From the primary cluster, use the `snapmirror update` command to update the primary volume.

```
pri_cluster::> snapmirror update -destination-path src_vserver:src_c_vol
```

6. From the primary cluster, use the `snapmirror break`` command to break the SnapMirror relationship between the clustered Data ONTAP primary and secondary volumes.

```
pri_cluster::> snapmirror break -destination-path src_vserver:src_c_vol
```

7. Enable client access to the clustered Data ONTAP primary volume.
8. From the primary cluster, use the `snapmirror delete` command to delete the SnapMirror relationship between the clustered Data ONTAP primary and secondary volumes.

```
pri_cluster::> snapmirror delete -destination-path src_vserver:src_c_vol
```

9. From the secondary cluster, use the `snapmirror create` command to create a SnapMirror relationship with the clustered Data ONTAP primary volume as the source and the clustered Data ONTAP secondary volume as destination, with a schedule similar to the previous schedule between the 7-Mode primary volume and clustered Data ONTAP secondary volume.

```
sec_cluster::> snapmirror create -source-path src_vserver:src_c_vol  
-destination-path dst_vserver:dst_c_vol -schedule 15_minute_sched
```

10. From the secondary cluster, use the `snapmirror resync` command to resynchronize the clustered Data ONTAP primary volume.

```
sec_cluster::> snapmirror resync -source-path src_vserver:src_c_vol  
-destination-path dst_vserver:dst_c_vol
```

Copyright Information

Copyright © 2021 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system- without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP "AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at <http://www.netapp.com/TM> are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.