



## **vserver nfs commands**

### **ONTAP 9.5 commands**

NetApp  
November 11, 2022

# Table of Contents

- vserver nfs commands . . . . . 1
  - vserver nfs create . . . . . 1
  - vserver nfs delete . . . . . 9
  - vserver nfs modify . . . . . 10
  - vserver nfs off . . . . . 18
  - vserver nfs on . . . . . 19
  - vserver nfs prepare-for-hadoop-non-root-mount-downgrade . . . . . 19
  - vserver nfs prepare-for-v3-ms-dos-client-downgrade . . . . . 20
  - vserver nfs prepare-to-downgrade . . . . . 20
  - vserver nfs show . . . . . 21
  - vserver nfs start . . . . . 29
  - vserver nfs status . . . . . 30
  - vserver nfs stop . . . . . 30
  - vserver nfs credentials count . . . . . 31
  - vserver nfs credentials flush . . . . . 31
  - vserver nfs credentials show . . . . . 32
  - vserver nfs kerberos interface disable . . . . . 35
  - vserver nfs kerberos interface enable . . . . . 36
  - vserver nfs kerberos interface modify . . . . . 37
  - vserver nfs kerberos interface show . . . . . 38
  - vserver nfs kerberos realm create . . . . . 40
  - vserver nfs kerberos realm delete . . . . . 41
  - vserver nfs kerberos realm modify . . . . . 42
  - vserver nfs kerberos realm show . . . . . 44
  - vserver nfs pnfs devices create . . . . . 46
  - vserver nfs pnfs devices delete . . . . . 47
  - vserver nfs pnfs devices show . . . . . 47
  - vserver nfs pnfs devices cache show . . . . . 49
  - vserver nfs pnfs devices mappings show . . . . . 50

# vserver nfs commands

## vserver nfs create

Create an NFS configuration for a Vserver

**Availability:** This command is available to *cluster* and *Vserver* administrators at the *admin* privilege level.

### Description

The `vserver nfs create` command enables and configures a Vserver to serve NFS clients. The Vserver must already exist. An NFS-enabled Vserver is associated with an NIS domain.

### Parameters

**-vserver <vserver name> - Vserver**

This parameter specifies the Vserver on which you want to create the NFS configuration.

**[-access {true|false}] - General NFS Access**

This optional parameter specifies whether to enable NFS access on the Vserver. The default setting is `true`.

**[-rpcsec-ctx-high <integer>] - RPC GSS Context Cache High Water Mark**

This optional parameter specifies the maximum number of `RPCSEC_GSS` authentication contexts, which are used by Kerberos. The default setting is zero. See RFC 2203 for information about `RPCSEC_GSS` contexts.

**[-rpcsec-ctx-idle <integer>] - RPC GSS Context Idle**

This optional parameter specifies, in seconds, the amount of time a `RPCSEC_GSS` context is permitted to remain unused before it is deleted. The default setting is zero seconds. See RFC 2203 for information about `RPCSEC_GSS` contexts.

**[-v3 {enabled|disabled}] - NFS v3**

This optional parameter specifies whether to enable access for NFSv3 clients. The default setting is `enabled`.

**[-v4.0 {enabled|disabled}] - NFS v4.0**

This optional parameter specifies whether to enable access for NFSv4.0 clients. The default setting is `disabled`.

**[-udp {enabled|disabled}] - UDP Protocol**

This optional parameter specifies whether to enable NFS access over UDP. The default setting is `enabled`.



Even if UDP is disabled, if TCP is enabled, the Vserver does not block NFSv3 traffic over UDP. By allowing this traffic, the storage system can process NFS\_NULL ops that the Solaris automounter sends to determine if the storage system is alive. (Solaris sends these ops over UDP even if configured to use TCP.) To disallow access for certain clients, including over UDP, you can use export-policy rules. For more information, see the [vserver export-policy rule create](#) command.

#### **[`-tcp {enabled|disabled}`] - TCP Protocol**

This optional parameter specifies whether to enable NFS access over TCP. The default setting is `enabled`.

#### **[`-default-win-user <text>`] - Default Windows User**

This optional parameter specifies a list of default Windows users for the NFS server.

#### **[`-enable-ejukebox {true|false}`] - Enable NFSv3 EJUKEBOX error**

This optional parameter specifies whether EJUKEBOX errors are enabled for NFSv3. The default setting is `true`.

#### **[`-v3-require-read-attributes {true|false}`] - Require All NFSv3 Reads to Return Read Attributes**

This optional parameter specifies whether NFSv3 read operations are required to return read attributes. The default setting is `false`.

#### **[`-v3-fsid-change {enabled|disabled}`] - Show Change in FSID as NFSv3 Clients Traverse Filesystems**

This optional parameter specifies whether Data ONTAP shows changes in file system identifiers (FSIDs) as NFSv3 clients traverse file systems. The default setting is `enabled`.

#### **[`-v3-connection-drop {enabled|disabled}`] - Enable the Dropping of a Connection When an NFSv3 Request is Dropped**

This optional parameter specifies whether Data ONTAP allows to drop the connection when a NFSv3 request is dropped. The default setting is `enabled`.

#### **[`-ntfs-unix-security-ops {fail|ignore|use-export-policy}`] - Vserver NTFS Unix Security Options**

This optional parameter specifies how NFSv3 security changes affect NTFS volumes. If you set this parameter to `ignore`, Data ONTAP ignores NFSv3 security changes. If you set this parameter to `fail`, this overrides the unix security options set in the relevant export rules. If you set this parameter to `use_export_policy`, Data ONTAP processes NFSv3 security changes in accordance with the relevant export rules. The default setting is `use_export_policy` at the time of creation.

#### **[`-chown-mode {restricted|unrestricted|use-export-policy}`] - Vserver Change Ownership Mode**

This optional parameter specifies whether ownership of a file can be changed by superusers or by non-root users who currently own the file. If you set this parameter to `restricted`, the ownership of a file can be changed by superusers only. If you set this parameter to `unrestricted`, the ownership of a file can be changed by superusers and the current owner of the file. If you set this parameter to `use-export-policy`, the ownership of a file can be changed in accordance with the relevant export rules. The default setting is `use-export-policy`.

### **[`-trace-enabled {true|false}`] - NFS Response Trace Enabled**

This optional parameter specifies whether Data ONTAP logs NFS requests when they exceed the NFS response trigger time (see the `trigger` parameter). The default setting is `false`.

### **[`-trigger <integer>`] - NFS Response Trigger (in secs)**

This optional parameter specifies the amount of time, in seconds, after which Data ONTAP must log an NFS request if it has not completed (assuming the `-trace-enabled` option is `true`). The default setting is 60.

### **[`-udp-max-xfer-size <integer>`] - UDP Maximum Transfer Size (bytes)**

This optional parameter specifies the maximum transfer size (in bytes) that the NFS mount protocol will negotiate with the client for UDP transport. The range is 8192 to 57344. The default setting is 32768.

### **[`-tcp-max-xfer-size <integer>`] - TCP Maximum Transfer Size (bytes)**

This optional parameter specifies the maximum transfer size (in bytes) that the storage system negotiates with the client for TCP transport of data for NFSv3, and NFSv4.x protocols. The range is 8192 to 1048576. The default setting is 65536.



Setting the parameter value greater than 65536 may cause performance degradation for existing connections using smaller values. Contact technical support for guidance.

### **[`-v3-tcp-max-read-size <integer>`] - NFSv3 TCP Maximum Read Size (bytes)**

This optional parameter specifies the maximum transfer size (in bytes) that the storage system negotiates with the client for TCP transport of data for NFSv3 read requests. The range is 8192 to 1048576. The default setting is 65536 when created.



This parameter is deprecated and may be removed in a future release of Data ONTAP. Use the `-tcp-max-xfer-size` parameter instead.

### **[`-v3-tcp-max-write-size <integer>`] - NFSv3 TCP Maximum Write Size (bytes)**

This optional parameter specifies the maximum transfer size (in bytes) that the storage system negotiates with the client for TCP transport of data for NFSv3 write requests. The range is 8192 to 65536. The default setting is 65536 when created.



This parameter is deprecated and may be removed in a future release of Data ONTAP. Use the `-tcp-max-xfer-size` parameter instead.

### **[`-v4.0-acl {enabled|disabled}`] - NFSv4.0 ACL Support**

This optional parameter specifies whether Data ONTAP supports NFSv4.0 access control lists (ACLs). The default setting is `disabled`.

### **[`-v4.0-read-delegation {enabled|disabled}`] - NFSv4.0 Read Delegation Support**

This optional parameter specifies whether Data ONTAP supports NFSv4.0 read delegations. The default setting is `disabled`.

### **[`-v4.0-write-delegation {enabled|disabled}`] - NFSv4.0 Write Delegation Support**

This optional parameter specifies whether Data ONTAP supports NFSv4.0 write delegations. The default setting is `disabled`.

### **[`-v4-fsid-change` {`enabled`|`disabled`}] - Show Change in FSID as NFSv4 Clients Traverse Filesystems**

This optional parameter specifies whether Data ONTAP shows changes in file system identifiers (FSIDs) as NFSv4 clients traverse file systems. The default setting is `enabled`.



If users access the storage system using NFSv4 from Solaris 10 clients, you must set this option to `disabled`.

### **[`-v4.0-referrals` {`enabled`|`disabled`}] - NFSv4.0 Referral Support**

This optional parameter specifies whether Data ONTAP supports NFSv4.0 referrals. The default setting is `disabled`. You can set this parameter to `enabled` only if you also set the `-v4-fsid-change` to `enabled`. If clients accessing the node do not support NFSv4.0 referrals, set this option to `disabled`; otherwise, those clients will not be able to access the file system.

### **[`-v4-id-domain` <`nfs domain`>] - NFSv4 ID Mapping Domain**

This optional parameter specifies the domain portion of the string form of user and group names as defined by the NFSv4 protocol. By default, the domain name is normally taken from the NIS domain or the DNS domain in use. However, the value of this parameter overrides the default. The domain name must be agreed upon by both the NFS client and the storage controller before NFSv4 operations can be executed. It is recommended that the domain be specified in the fully qualified domain name format.

### **[`-v4-validate-symlinkdata` {`enabled`|`disabled`}] - NFSv4 Validate UTF-8 Encoding of Symbolic Link Data**

This optional parameter specifies whether Data ONTAP validates the UTF-8 encoding of symbolic link data. The default setting is `disabled`.

### **[`-v4-lease-seconds` <`integer`>] - NFSv4 Lease Timeout Value (in secs)**

This optional parameter specifies the time period in which Data ONTAP irrevocably grants a lock to a client. By default, the lease period is 30 seconds. The minimum value is 10. The maximum value is one less than the value of the `-v4-grace-seconds` parameter.

### **[`-v4-grace-seconds` <`integer`>] - NFSv4 Grace Timeout Value (in secs)**

This optional parameter specifies the time period in which clients attempt to reclaim their locking state from Data ONTAP during server recovery. By default, the grace period is 45 seconds. The minimum value is 1 more than the value of the `-v4-lease-seconds` parameter. The maximum value is 90.

### **[`-v4-acl-preserve` {`enabled`|`disabled`}] - Preserves and Modifies NFSv4 ACL (and NTFS File Permissions in Unified Security Style)**

This optional parameter specifies if the NFSv4 ACL is preserved or dropped when `chmod` is performed. In unified security style, this parameter also specifies if NTFS file permissions are preserved or dropped when `chmod`, `chgrp`, or `chown` are performed. The default is `enabled`.

### **[`-v4.1` {`enabled`|`disabled`}] - NFSv4.1 Minor Version Support**

This optional parameter specifies whether to enable access for NFSv4.1 clients. The default setting is `disabled`.

### **[`-rquota` {`enabled`|`disabled`}] - Rquota Enable**

This optional parameter specifies whether to enable rquota over NFS. The default setting is `disabled`.

**[-v4.1-implementation-domain <nfs domain>] - NFSv4.1 Implementation ID Domain**

This optional parameter specifies the NFSv4.1 implementation domain.

**[-v4.1-implementation-name <text>] - NFSv4.1 Implementation ID Name**

This optional parameter specifies the NFSv4.1 implementation name.

**[-v4.1-implementation-date <Date>] - NFSv4.1 Implementation ID Date**

This optional parameter specifies the NFSv4.1 implementation date.

**[-v4.1-pnfs {enabled|disabled}] - NFSv4.1 Parallel NFS Support**

This optional parameter specifies whether Data ONTAP supports parallel NFS over NFSv4.1. The default setting is `enabled`.

**[-v4.1-referrals {enabled|disabled}] - NFSv4.1 Referral Support**

This optional parameter specifies whether Data ONTAP supports NFSv4.1 referrals. The default setting is `disabled`. You can set this parameter to `enabled` only if you also set the `-v4-fsid-change` to `enabled`. If clients accessing the node do not support NFSv4.1 referrals, set this option to `disabled`; otherwise, those clients will not be able to access the file system.

**[-v4.1-acl {enabled|disabled}] - NFSv4.1 ACL Support**

This optional parameter specifies whether Data ONTAP supports NFSv4.1 access control lists (ACLs). The default setting is `disabled`.

**[-vstorage {enabled|disabled}] - NFS vStorage Support**

This optional parameter specifies whether to enable vstorage over NFS. The default setting is `disabled`.

**[-v4-numeric-ids {enabled|disabled}] - NFSv4 Support for Numeric Owner IDs**

This optional parameter specifies whether the support for numeric string identifiers in NFSv4 owner attributes is enabled. The default setting is `enabled`.

**[-default-win-group <text>] - Default Windows Group**

This optional parameter specifies a list of default Windows groups for the NFS server.

**[-v4.1-read-delegation {enabled|disabled}] - NFSv4.1 Read Delegation Support**

This optional parameter specifies whether Data ONTAP supports NFSv4.1 read delegations. The default setting is `disabled`.

**[-v4.1-write-delegation {enabled|disabled}] - NFSv4.1 Write Delegation Support**

This optional parameter specifies whether Data ONTAP supports NFSv4.1 write delegations. The default setting is `disabled`.

**[-v4.x-session-num-slots <integer>] - Number of Slots in the NFSv4.x Session slot tables**

This optional parameter specifies the number of entries in the NFSv4.x session slot table. By default, the number of slots is 180. The maximum value is 2000.

**[-v4.x-session-slot-reply-cache-size <integer>] - Size of the Reply that will be Cached in Each NFSv4.x Session Slot (in bytes)**

This optional parameter specifies the number of bytes of the reply that will be cached in each NFSv4.x session slot. By default, the size of the cached reply is 640 bytes. The maximum value is 4096.

**[-v4-acl-max-aces <integer>] - Maximum Number of ACEs per ACL**

This optional parameter specifies the maximum number of ACEs in an NFSv4 ACL. The range is 192 to 1024. The default value is 400. Setting it to a value more than the default could cause performance problems for clients accessing files with NFSv4 ACLs.

**[-mount-rootonly {enabled|disabled}] - NFS Mount Root Only**

This optional parameter specifies whether the Vserver allows MOUNT protocol calls only from privileged ports (port numbers less than 1024). The default setting is `enabled`.

**[-nfs-rootonly {enabled|disabled}] - NFS Root Only**

This optional parameter specifies whether the Vserver allows NFS protocol calls only from privileged ports (port numbers less than 1024). The default setting is `disabled`.

**[-auth-sys-extended-groups {enabled|disabled}] - AUTH\_SYS Extended Groups Enabled**

This optional parameter specifies whether Data ONTAP supports fetching auxiliary groups from a name service rather than from the RPC header. The default setting is `disabled`.

**[-extended-groups-limit <integer>] - AUTH\_SYS and RPCSEC\_GSS Auxiliary Groups Limit**

This optional parameter specifies the maximum number of auxiliary groups supported over RPC security flavors AUTH\_SYS and RPCSEC\_GSS in Data ONTAP. The range is 32 to 1024. The default value is 32.

**[-validate-qtrees-export {enabled|disabled}] - Validation of Qtree IDs for Qtree File Operations**

This optional parameter specifies whether clustered Data ONTAP performs an additional validation on qtree IDs. The default setting is `enabled`. This parameter is ignored unless a non-inherited policy has been or is assigned to a qtree.

**[-mountd-port <integer>] - NFS Mount Daemon Port**

This optional parameter specifies which port the NFS mount daemon (`mountd`) uses. The port numbers allowed are 635 (the default) and 1024 through 9999.

**[-nlm-port <integer>] - Network Lock Manager Port**

This optional parameter specifies which port the network lock manager (NLM) uses. The port numbers allowed are 1024 through 9999. The default setting is 4045.

**[-nsm-port <integer>] - Network Status Monitor Port**

This optional parameter specifies which port the network status monitor (NSM) uses. The port numbers allowed are 1024 through 9999. The default setting is 4046.

**[-rquotad-port <integer>] - NFS Quota Daemon Port**

This optional parameter specifies which port the NFS quota daemon (`rquotad`) uses. The port numbers allowed are 1024 through 9999. The default setting is 4049.

**[-permitted-enc-types <NFS Kerberos Encryption Type>, ...] - Permitted Kerberos Encryption Types**

This optional parameter specifies the permitted encryption types for Kerberos over NFS. The default setting is `des ,des3 ,aes-128 ,aes-256`.



### **[`-showmount {enabled|disabled}`] - Showmount Enabled**

This optional parameter specifies whether to allow or disallow clients to see the Vserver's NFS exports list. The default setting is *enabled*.



Showmount leverages the MOUNT protocol in NFSv3 to issue an EXPORT query to the NFS server. If the mount port is not listening or blocked by a firewall, or if NFSv3 is disabled on the NFS server, showmount queries fail.

### **[`-name-service-lookup-protocol {TCP|UDP}`] - Set the Protocol Used for Name Services Lookups for Exports**

This optional parameter specifies the protocol to use for doing name service lookups. The allowed values are `TCP` and `UDP`. The default setting is `UDP`.

### **[`-map-unknown-uid-to-default-windows-user {enable|disable}`] - Map Unknown UID to Default Windows User**

If you enable this optional parameter, unknown UNIX users that do not have a name mapping to a Windows user are mapped to the configured default Windows user. This allows all unknown UNIX users access with the credentials of the default Windows user. If you disable it, all unknown UNIX users without name mapping are always denied access. By default, this parameter is enabled.

### **[`-netgroup-dns-domain-search {enabled|disabled}`] - DNS Domain Search Enabled During Netgroup Lookup**

If you enable this optional parameter, during client access check evaluation in a netgroup, Data ONTAP performs an additional verification to ensure that the domain returned from DNS for that client is listed in the DNS configuration of the Vserver. This enables you to validate the domain when clients have the same short name in multiple domains. The default setting is *enabled*.

### **[`-netgroup-trust-any-ns-switch-no-match {enabled|disabled}`] - Trust No-Match Result from Any Name Service Switch Source During Netgroup Lookup**

This optional parameter specifies if you can consider a no-match result from any netgroup ns-switch source to be authoritative. If this option is enabled, then a no-match response from any one of the netgroup ns-switch sources is deemed conclusive even if other sources could not be searched. The default setting is 'disabled', which causes all netgroup ns-switch sources to be consulted before a no-match result is deemed conclusive.

### **[`-ntacl-display-permissive-perms {enabled|disabled}`] - Display maximum NT ACL Permissions to NFS Client**

This optional parameter controls the permissions that are displayed to NFSv3 and NFSv4 clients on a file or directory that has an NT ACL set. When true, the displayed permissions are based on the maximum access granted by the NT ACL to any user. When false, the displayed permissions are based on the minimum access granted by the NT ACL to any user. The default setting is *false*.

### **[`-v3-ms-dos-client {enabled|disabled}`] - NFSv3 MS-DOS Client Support**

This optional parameter specifies whether to enable access for NFSv3 MS-DOS clients. The default setting is *disabled*.

### **[`-ignore-nt-acl-for-root {enabled|disabled}`] - Ignore the NT ACL Check for NFS User 'root'**

This optional parameter specifies whether Windows ACLs affect root access from NFS. If this option is enabled, root access from NFS ignores the NT ACL set on the file or directory. If auditing is enabled for the Vserver and there is no name-mapping present, then a default SMB credential (`Builtin\administrator`) is used for auditing, and an EMS warning is generated. The default setting is 'disabled', which causes NFS

'root' to be mapped to a Windows account, like any other NFS user.

**[-cached-cred-positive-ttl <integer>] - Time To Live Value (in msec) of a Positive Cached Credential**

This optional parameter specifies the age of the positive cached credentials after which they will be cleared from the cache. The value specified must be between 60000 and 604800000. The default setting is 86400000.

**[-cached-cred-negative-ttl <integer>] - Time To Live Value (in msec) of a Negative Cached Credential**

This optional parameter specifies the age of the negative cached credentials after which they will be cleared from the cache. The value specified must be between 60000 and 604800000. The default setting is 7200000.

**[-skip-root-owner-write-perm-check {enabled|disabled}] - Skip Permission Check for NFS Write Calls from Root/Owner**

This optional parameter specifies if permission checks are to be skipped for NFS WRITE calls from root/owner. For copying read-only files to a destination folder which has inheritable ACLs, this option must be *enabled*. Warning: When *enabled*, if an NFS client does not make use of an NFS ACCESS call to check for user-level permissions and then tries to write onto read-only files, the operation will succeed. The default setting is *disabled*.

**[-v3-64bit-identifiers {enabled|disabled}] - Use 64 Bits for NFSv3 FSIDs and File IDs**

This optional parameter specifies whether Data ONTAP uses 64 bits (instead of 32 bits) for file system identifiers (FSIDs) and file identifiers (file IDs) that are returned to NFSv3 clients. The default setting is *disabled*. When *-v3-fsid-change* is disabled, enable this parameter to avoid file ID collisions.

**[-v4-inherited-acl-preserve {enabled|disabled}] - Ignore Client Specified Mode Bits and Preserve Inherited NFSv4 ACL When Creating New Files or Directories**

This optional parameter specifies whether the client-specified mode bits should be ignored and the inherited NFSv4 ACL should be preserved when creating new files or directories. The default setting is *disabled*.

**[-v3-search-unconverted-filename {enabled|disabled}] - Fallback to Unconverted Filename Search**

This optional parameter specifies whether to continue search without converting the filename to the Unicode character set while doing lookup in a directory.

**[-file-session-io-grouping-count <integer>] - I/O Count to Be Grouped as a Session**

This optional parameter specifies the number of read or write operations on a file from a single client that are grouped and considered as one session for event generation applications, such as FPolicy. The event is generated on the first read or write of a file, and subsequently the event is generated only after the specified *-file-session-io-grouping-count*. The default value is 5000.

**[-file-session-io-grouping-duration <integer>] - Duration for I/O to Be Grouped as a Session (Secs)**

This optional parameter specifies the duration for which the read or write operations on a file from a single client are grouped and considered as one session for event generation applications, such as FPolicy. The default value is 120 seconds.

**[-checksum-for-replay-cache {enabled|disabled}] - Enable or disable Checksum for Replay-Cache**

This optional parameter specifies whether to enable replay cache checksum for NFS requests . The default value is *enabled* .

#### **`[-cached-cred-harvest-timeout <integer>]` - Harvest timeout (in msec) for a Cached Credential**

This optional parameter specifies the harvest timeout for cached credentials. The value specified must be between 60000 and 604800000. The default setting is 86400000 .

#### **`[-idle-connection-timeout <integer>]` - Idle Connection Timeout Value (in seconds)**

This optional parameter specifies the idle connection timeout value for NFS connections in seconds. The value specified must be between 120 and 86400.

#### **`[-allow-idle-connection {enabled|disabled}]` - Are Idle NFS Connections Supported**

This optional parameter specifies whether to enable idle NFS connections. The default setting is *disabled* .

#### **`[-v3-hide-snapshot {enabled|disabled}]` - Hide Snapshot Directory under NFSv3 Mount Point**

This optional parameter specifies whether to hide the `.snapshot` directory while listing under NFSv3 mount points. However an explicit access to the `.snapshot` directory will still be allowed even though the option is enabled. The default setting is *disabled* .

## Examples

The following example enables and configures NFS access on a Vserver named `vs0`. NFS access is enabled. The maximum number of RPCSEC\_GSS authentication contexts is set to 5. The RPCSEC\_GSS idle time is set to 360 seconds. Access is enabled for NFS v3 clients over both UDP and TCP.

```
cluster1::> vsserver nfs create -vserver vs0 -access true -rpcsec-ctx-high
5 -rpcsec-ctx-idle 360 -v3 enabled -udp enabled -tcp enabled
```

## Related Links

- [vsserver export-policy rule create](#)

## vsserver nfs delete

Delete the NFS configuration of a Vserver

**Availability:** This command is available to *cluster* and *Vserver* administrators at the *admin* privilege level.

## Description

The `vsserver nfs delete` command deletes the NFS configuration of a specified Vserver. This command does not delete the Vserver itself, just its ability to serve NFS clients.



If you delete a Vserver, the Vserver's NFS configuration is automatically deleted. Any Windows-to-UNIX or UNIX-to-Windows name mappings defined for the Vserver are also deleted because they require both the CIFS and NFS servers.

## Parameters

### **-vserver <vserver name> - Vserver**

This specifies the Vserver whose NFS configuration you want to delete.

## Examples

The following example deletes the NFS configuration of a Vserver named vs2:

```
cluster1::> vserver nfs delete -vserver vs2
```

## vserver nfs modify

Modify the NFS configuration of a Vserver

**Availability:** This command is available to *cluster* and *Vserver* administrators at the *admin* privilege level.

## Description

The `vserver nfs modify` command modifies the configuration of an NFS-enabled Vserver.

## Parameters

### **-vserver <vserver name> - Vserver**

This specifies the Vserver whose NFS configuration you want to modify.

### **[-access {true|false}] - General NFS Access**

This optional parameter specifies whether NFS access is enabled on the Vserver.

### **[-rpcsec-ctx-high <integer>] - RPC GSS Context Cache High Water Mark**

This optional parameter specifies the maximum number of RPCSEC\_GSS authentication contexts, which are used by Kerberos. The default setting is zero at the time of creation. See RFC 2203 for information about RPCSEC\_GSS contexts.

### **[-rpcsec-ctx-idle <integer>] - RPC GSS Context Idle**

This optional parameter specifies, in seconds, the amount of time a RPCSEC\_GSS context is permitted to remain unused before it is deleted. The default setting is zero seconds at the time of creation. See RFC 2203 for information about RPCSEC\_GSS contexts.

### **[-v3 {enabled|disabled}] - NFS v3**

This optional parameter specifies whether to enable access for NFS v3 clients.

### **[-v4.0 {enabled|disabled}] - NFS v4.0**

This optional parameter specifies whether to enable access for NFSv4.0 clients. The default setting is enabled at the time of creation.

### **[-udp {enabled|disabled}] - UDP Protocol**

This optional parameter specifies whether to enable NFS access over UDP.



Even if UDP is disabled, if TCP is enabled, the Vserver does not block NFSv3 traffic over UDP. By allowing this traffic, the storage system can process NFS\_NULL ops that the Solaris automounter sends to determine if the storage system is alive. (Solaris sends these ops over UDP even if configured to use TCP.) To disallow access for certain clients, including over UDP, you can use export-policy rules. For more information, see the [vserver export-policy rule create](#) command.

#### **[-tcp {enabled|disabled}] - TCP Protocol**

This optional parameter specifies whether to enable NFS access over TCP.

#### **[-default-win-user <text>] - Default Windows User**

This optional parameter specifies a list of default Windows users for the NFS server.

#### **[-enable-ejukebox {true|false}] - Enable NFSv3 EJUKEBOX error**

This optional parameter specifies whether EJUKEBOX errors are enabled for NFSv3. The default setting is `true` at the time of creation.

#### **[-v3-require-read-attributes {true|false}] - Require All NFSv3 Reads to Return Read Attributes**

This optional parameter specifies whether NFSv3 read operations are required to return read attributes. The default setting is `false` at the time of creation.

#### **[-v3-fsid-change {enabled|disabled}] - Show Change in FSID as NFSv3 Clients Traverse Filesystems**

This optional parameter specifies whether Data ONTAP shows changes in file system identifiers (FSIDs) as NFSv3 clients traverse file systems. If you change the value of this parameter, clients must remount any paths over which they are using NFSv3.

#### **[-v3-connection-drop {enabled|disabled}] - Enable the Dropping of a Connection When an NFSv3 Request is Dropped**

This optional parameter specifies whether NFS v3 connection drop is enabled. The default setting is `enabled` at the time of creation.

#### **[-ntfs-unix-security-ops {fail|ignore|use-export-policy}] - Vserver NTFS Unix Security Options**

This optional parameter specifies how NFSv3 security changes affect NTFS volumes. If you set this parameter to `ignore`, Data ONTAP ignores NFSv3 security changes. If you set this parameter to `fail`, this overrides the unix security options set in the relevant export rules. If you set this parameter to `use_export_policy`, Data ONTAP processes NFSv3 security changes in accordance with the relevant export rules. The default setting is `use_export_policy` at the time of creation.

#### **[-chown-mode {restricted|unrestricted|use-export-policy}] - Vserver Change Ownership Mode**

This optional parameter specifies whether ownership of a file can be changed by superusers or by non-root users who currently own the file. If you set this parameter to `restricted`, the ownership of a file can be changed by superusers only. If you set this parameter to `unrestricted`, the ownership of a file can be changed by superusers and the current owner of the file. If you set this parameter to `use-export-policy`, the ownership of a file can be changed in accordance with the relevant export rules.

### **[`-trace-enabled {true|false}`] - NFS Response Trace Enabled**

This optional parameter specifies whether Data ONTAP logs NFS requests when they exceed the NFS response trigger time (see the `trigger` parameter). The default setting is `false` at the time of creation.

### **[`-trigger <integer>`] - NFS Response Trigger (in secs)**

This optional parameter specifies the amount of time, in seconds, after which Data ONTAP must log an NFS request if it has not completed (assuming the `-trace-enabled` option is set to `true`). The default setting is 60 at the time of creation.

### **[`-udp-max-xfer-size <integer>`] - UDP Maximum Transfer Size (bytes)**

This optional parameter specifies the maximum transfer size (in bytes) that the NFS mount protocol negotiates with the client for UDP transport. The range is 8192 to 57344. The default setting is 32768 at the time of creation.

### **[`-tcp-max-xfer-size <integer>`] - TCP Maximum Transfer Size (bytes)**

This optional parameter specifies the maximum transfer size (in bytes) that the storage system negotiates with the client for TCP transport of data for NFSv3 and NFSv4.x protocols. The range is 8192 to 1048576. The default setting is 65536 when created.

### **[`-v3-tcp-max-read-size <integer>`] - NFSv3 TCP Maximum Read Size (bytes)**

This optional parameter specifies the maximum transfer size (in bytes) that the storage system negotiates with the client for TCP transport of data for NFSv3 read requests. The range is 8192 to 1048576. The default setting is 65536 when created.



This parameter is deprecated and may be removed in a future release of Data ONTAP. Use the `-tcp-max-xfer-size` parameter instead.

### **[`-v3-tcp-max-write-size <integer>`] - NFSv3 TCP Maximum Write Size (bytes)**

This optional parameter specifies the maximum transfer size (in bytes) that the storage system negotiates with the client for TCP transport of data for NFSv3 write requests. The range is 8192 to 65536. The default setting is 65536 when created.



This parameter is deprecated and may be removed in a future release of Data ONTAP. Use the `-tcp-max-xfer-size` parameter instead.

### **[`-v4.0-acl {enabled|disabled}`] - NFSv4.0 ACL Support**

This optional parameter specifies whether Data ONTAP supports NFSv4.0 access control lists (ACLs). The default setting is `disabled` when created.

### **[`-v4.0-read-delegation {enabled|disabled}`] - NFSv4.0 Read Delegation Support**

This optional parameter specifies whether Data ONTAP supports NFSv4 read delegations. The default setting is `disabled` when created.

### **[`-v4.0-write-delegation {enabled|disabled}`] - NFSv4.0 Write Delegation Support**

This optional parameter specifies whether Data ONTAP supports NFSv4 write delegations. The default setting is `disabled` when created.

### **[`-v4-fsid-change {enabled|disabled}`] - Show Change in FSID as NFSv4 Clients Traverse Filesystems**

This optional parameter specifies whether Data ONTAP shows changes in file system identifiers (FSIDs) as NFSv4 clients traverse file systems. The default setting is `enabled` when created. If you change the value of this parameter, clients must remount any paths over which they are using NFSv4.



If users access the storage system using NFSv4 from Solaris 10 clients, you must set this option to `disabled`.

#### **`[-v4.0-referrals {enabled|disabled}] - NFSv4.0 Referral Support`**

This optional parameter specifies whether Data ONTAP supports NFSv4.0 referrals. The default setting is `disabled` when created. You can set this parameter to `enabled` only if the `-v4-fsid-change` option is also set to `enabled`. If clients accessing the node do not support NFSv4.0 referrals, set this option to `disabled`; otherwise, those clients will not be able to access the file system.

#### **`[-v4-id-domain <nfs domain>] - NFSv4 ID Mapping Domain`**

This optional parameter specifies the domain portion of the string form of user and group names as defined by the NFSv4 protocol. By default, the domain name is normally taken from the NIS domain or the DNS domain in use. However, the value of this parameter overrides the default. The domain name must be agreed upon by both the NFS client and the storage controller before NFSv4 operations can be executed. It is recommended that the domain be specified in the fully qualified domain name format.

#### **`[-v4-validate-symlinkdata {enabled|disabled}] - NFSv4 Validate UTF-8 Encoding of Symbolic Link Data`**

This optional parameter specifies whether Data ONTAP validates the UTF-8 encoding of symbolic link data. The default setting is `disabled` when created.

#### **`[-v4-lease-seconds <integer>] - NFSv4 Lease Timeout Value (in secs)`**

This optional parameters specifies the time period in which Data ONTAP irrevocably grants a lock to a client. By default, the lease period is 30 seconds. The minimum value is 10. The maximum value is one less than the value of the `-v4-grace-seconds` parameter.

#### **`[-v4-grace-seconds <integer>] - NFSv4 Grace Timeout Value (in secs)`**

This optional parameter specifies the time period in which clients attempt to reclaim their locking state from Data ONTAP during server recovery. By default, the grace period is 45 seconds. The minimum value is 1 more than the value of the `-v4-lease-seconds` parameter. The maximum value is 90.

#### **`[-v4-acl-preserve {enabled|disabled}] - Preserves and Modifies NFSv4 ACL (and NTFS File Permissions in Unified Security Style)`**

This optional parameter specifies if the NFSv4 ACL is preserved or dropped when `chmod` is performed. In unified security style, this parameter also specifies if NTFS file permissions are preserved or dropped when `chmod`, `chgrp`, or `chown` are performed. The default is `enabled`.

#### **`[-v4.1 {enabled|disabled}] - NFSv4.1 Minor Version Support`**

This optional parameter specifies whether to enable access for NFSv4.1 clients. The default setting is `enabled` at the time of creation.

#### **`[-rquota {enabled|disabled}] - Rquota Enable`**

This optional parameter specifies whether to enable rquota over NFS. The default setting is `disabled` at the time of creation.

**[-v4.1-implementation-domain <nfs domain>] - NFSv4.1 Implementation ID Domain**

This optional parameter specifies the NFSv4.1 implementation domain.

**[-v4.1-implementation-name <text>] - NFSv4.1 Implementation ID Name**

This optional parameter specifies the NFSv4.1 implementation name.

**[-v4.1-implementation-date <Date>] - NFSv4.1 Implementation ID Date**

This optional parameter specifies the NFSv4.1 implementation date.

**[-v4.1-pnfs {enabled|disabled}] - NFSv4.1 Parallel NFS Support**

This optional parameter specifies whether to enable access for pNFS for NFSv4.1. The default setting is `enabled` at the time of creation.

**[-v4.1-referrals {enabled|disabled}] - NFSv4.1 Referral Support**

This optional parameter specifies whether Data ONTAP supports NFSv4.1 referrals. The default setting is `disabled` when created. You can set this parameter to `enabled` only if the `-v4-fsid-change` option is also set to `enabled`. If clients accessing the node do not support NFSv4.1 referrals, set this option to `disabled`; otherwise, those clients will not be able to access the file system.

**[-v4.1-acl {enabled|disabled}] - NFSv4.1 ACL Support**

This optional parameter specifies whether Data ONTAP supports NFSv4.1 access control lists (ACLs). The default setting is `disabled` when created.

**[-vstorage {enabled|disabled}] - NFS vStorage Support**

This optional parameter specifies whether to enable vstorage over NFS. The default setting is `disabled` at the time of creation.

**[-v4-numeric-ids {enabled|disabled}] - NFSv4 Support for Numeric Owner IDs**

This optional parameter specifies whether to enable the support for numeric string identifiers in NFSv4 owner attributes. The default setting is `enabled` at the time of creation.

**[-default-win-group <text>] - Default Windows Group**

This optional parameter specifies a list of default Windows groups for the NFS server.

**[-v4.1-read-delegation {enabled|disabled}] - NFSv4.1 Read Delegation Support**

This optional parameter specifies whether Data ONTAP supports NFSv4.1 read delegations. The default setting is `disabled` when created.

**[-v4.1-write-delegation {enabled|disabled}] - NFSv4.1 Write Delegation Support**

This optional parameter specifies whether Data ONTAP supports NFSv4.1 write delegations. The default setting is `disabled` when created.

**[-v4.x-session-num-slots <integer>] - Number of Slots in the NFSv4.x Session slot tables**

This optional parameter specifies the number of entries in the NFSv4.x session slot table. By default, the number of slots is 180. The maximum value is 2000.

**[-v4.x-session-slot-reply-cache-size <integer>] - Size of the Reply that will be Cached in Each NFSv4.x Session Slot (in bytes)**

This optional parameter specifies the number of bytes of the reply that will be cached in each NFSv4.x



session slot. By default, the size of the cached reply is 640 bytes. The maximum value is 4096.

**[-v4-acl-max-aces <integer>] - Maximum Number of ACEs per ACL**

This optional parameter specifies the maximum number of ACEs in a NFSv4 ACL. The range is 192 to 1024. The default value is 400. Setting it to a value more than the default could cause performance problems for clients accessing files with NFSv4 ACLs.

**[-mount-rootonly {enabled|disabled}] - NFS Mount Root Only**

This optional parameter specifies whether the Vserver allows MOUNT protocol calls only from privileged ports (port numbers less than 1024). The default setting is `enabled`.

**[-nfs-rootonly {enabled|disabled}] - NFS Root Only**

This optional parameter specifies whether the Vserver allows NFS protocol calls only from privileged ports (port numbers less than 1024). The default setting is `disabled`.

**[-auth-sys-extended-groups {enabled|disabled}] - AUTH\_SYS Extended Groups Enabled**

This optional parameter specifies whether Data ONTAP supports fetching auxillary groups from a name service rather than from the RPC header. The default setting is `disabled`.

**[-extended-groups-limit <integer>] - AUTH\_SYS and RPCSEC\_GSS Auxillary Groups Limit**

This optional parameter specifies the maximum number of auxillary groups supported over RPC security flavors AUTH\_SYS and RPCSEC\_GSS in Data ONTAP. The range is 32 to 1024. The default value is 32.

**[-validate-qtrees-export {enabled|disabled}] - Validation of Qtree IDs for Qtree File Operations**

This optional parameter specifies whether clustered Data ONTAP performs an additional validation on qtree IDs. The default setting is `enabled`. This parameter is ignored unless a non-inherited policy has been or is assigned to a qtree.

**[-mountd-port <integer>] - NFS Mount Daemon Port**

This optional parameter specifies which port the NFS mount daemon (`mountd`) uses. The port numbers allowed are 635 (the default) and 1024 through 9999.

**[-nlm-port <integer>] - Network Lock Manager Port**

This optional parameter specifies which port the network lock manager (NLM) uses. The port numbers allowed are 1024 through 9999. The default setting is 4045.

**[-nsm-port <integer>] - Network Status Monitor Port**

This optional parameter specifies which port the network status monitor (NSM) uses. The port numbers allowed are 1024 through 9999. The default setting is 4046.

**[-rquotad-port <integer>] - NFS Quota Daemon Port**

This optional parameter specifies which port the NFS quota daemon (`rquotad`) uses. The port numbers allowed are 1024 through 9999. The default setting is 4049.

**[-permitted-enc-types <NFS Kerberos Encryption Type>,...] - Permitted Kerberos Encryption Types**

This optional parameter specifies the permitted encryption types for Kerberos over NFS. The default setting is `des ,des3 ,aes-128 ,aes-256`.

### **[`-showmount {enabled|disabled}`] - Showmount Enabled**

This optional parameter specifies whether to allow or disallow clients to see the Vserver's NFS exports list. The default setting is *enabled*.



Showmount leverages the MOUNT protocol in NFSv3 to issue an EXPORT query to the NFS server. If the mount port is not listening or blocked by a firewall, or if NFSv3 is disabled on the NFS server, showmount queries fail.

### **[`-name-service-lookup-protocol {TCP|UDP}`] - Set the Protocol Used for Name Services Lookups for Exports**

This optional parameter specifies the protocol to use for doing name service lookups. The allowed values are `TCP` and `UDP`. The default setting is `UDP`.

### **[`-map-unknown-uid-to-default-windows-user {enable|disable}`] - Map Unknown UID to Default Windows User**

If you enable this optional parameter, unknown UNIX users that do not have a name mapping to a Windows user are mapped to the configured default Windows user. This allows all unknown UNIX users access with the credentials of the default Windows user. If you disable it, all unknown UNIX users without name mapping are always denied access. By default, this parameter is enabled.

### **[`-netgroup-dns-domain-search {enabled|disabled}`] - DNS Domain Search Enabled During Netgroup Lookup**

If you enable this optional parameter, during client access check evaluation in a netgroup, Data ONTAP performs an additional verification to ensure that the domain returned from DNS for that client is listed in the DNS configuration of the Vserver. This enables you to validate the domain when clients have the same short name in multiple domains. The default setting is *enabled*.

### **[`-netgroup-trust-any-ns-switch-no-match {enabled|disabled}`] - Trust No-Match Result from Any Name Service Switch Source During Netgroup Lookup**

This optional parameter specifies if you can consider a no-match result from any of the netgroup ns-switch sources to be authoritative. If this option is enabled, then a no-match response from any of the netgroup ns-switch sources is deemed conclusive even if other sources could not be searched. The default setting is 'disabled', which causes all netgroup ns-switch sources to be consulted before a no-match result is deemed conclusive.

### **[`-ntacl-display-permissive-perms {enabled|disabled}`] - Display maximum NT ACL Permissions to NFS Client**

This optional parameter controls the permissions that are displayed to NFSv3 and NFSv4 clients on a file or directory that has an NT ACL set. When true, the displayed permissions are based on the maximum access granted by the NT ACL to any user. When false, the displayed permissions are based on the minimum access granted by the NT ACL to any user. The default setting is *false*.

### **[`-v3-ms-dos-client {enabled|disabled}`] - NFSv3 MS-DOS Client Support**

This optional parameter specifies whether to enable access for NFSv3 MS-DOS clients. The default setting is *disabled* at the time of creation.

### **[`-ignore-nt-acl-for-root {enabled|disabled}`] - Ignore the NT ACL Check for NFS User 'root'**

This optional parameter specifies whether Windows ACLs affect root access from NFS. If this option is enabled, root access from NFS ignores the NT ACL set on the file or directory. If auditing is enabled for the Vserver and there is no name-mapping present, then a default SMB credential (`Builtin\administrator`) is used for auditing, and an EMS warning is generated. The default setting is 'disabled', which causes NFS

'root' to be mapped to a Windows account, like any other NFS user.

**[-cached-cred-positive-ttl <integer>] - Time To Live Value (in msec) of a Positive Cached Credential**

This optional parameter specifies the age of the positive cached credentials after which they will be cleared from the cache. The value specified must be between 60000 and 604800000. The default setting is 86400000.

**[-cached-cred-negative-ttl <integer>] - Time To Live Value (in msec) of a Negative Cached Credential**

This optional parameter specifies the age of the negative cached credentials after which they will be cleared from the cache. The value specified must be between 60000 and 604800000. The default setting is 7200000.

**[-skip-root-owner-write-perm-check {enabled|disabled}] - Skip Permission Check for NFS Write Calls from Root/Owner**

This optional parameter specifies if permission checks are to be skipped for NFS WRITE calls from root/owner. For copying read-only files to a destination folder which has inheritable ACLs, this option must be *enabled*. Warning: When *enabled*, if an NFS client does not make use of an NFS ACCESS call to check for user-level permissions and then tries to write onto read-only files, the operation will succeed. The default setting is *disabled*.

**[-v3-64bit-identifiers {enabled|disabled}] - Use 64 Bits for NFSv3 FSIDs and File IDs**

This optional parameter specifies whether Data ONTAP uses 64 bits (instead of 32 bits) for file system identifiers (FSIDs) and file identifiers (file IDs) that are returned to NFSv3 clients. If you change the value of this parameter, clients must remount any paths over which they are using NFSv3. When `-v3-fsid-change` is disabled, enable this parameter to avoid file ID collisions.

**[-v4-inherited-acl-preserve {enabled|disabled}] - Ignore Client Specified Mode Bits and Preserve Inherited NFSv4 ACL When Creating New Files or Directories**

This optional parameter specifies whether the client-specified mode bits should be ignored and the inherited NFSv4 ACL should be preserved when creating new files or directories. The default setting is *disabled*.

**[-v3-search-unconverted-filename {enabled|disabled}] - Fallback to Unconverted Filename Search**

This optional parameter specifies whether to continue search without converting the filename to the Unicode character set while doing lookup in a directory.

**[-file-session-io-grouping-count <integer>] - I/O Count to Be Grouped as a Session**

This optional parameter specifies the number of read or write operations on a file from a single client that are grouped and considered as one session for event generation applications, such as FPolicy. The event is generated on the first read or write of a file, and subsequently the event is generated only after the specified `-file-session-io-grouping-count`. The default value is 5000.

**[-file-session-io-grouping-duration <integer>] - Duration for I/O to Be Grouped as a Session (Secs)**

This optional parameter specifies the duration for which the read or write operations on a file from a single client are grouped and considered as one session for event generation applications, such as FPolicy. The default value is 120 seconds.

**`[-checksum-for-replay-cache {enabled|disabled}]` - Enable or disable Checksum for Replay-Cache**

This optional parameter specifies whether to enable replay cache checksum for NFS requests. The default value is *enabled*.

**`[-cached-cred-harvest-timeout <integer>]` - Harvest timeout (in msec) for a Cached Credential**

This optional parameter specifies the harvest timeout for cached credentials. The value specified must be between 60000 and 604800000. The default setting is 86400000.

**`[-idle-connection-timeout <integer>]` - Idle Connection Timeout Value (in seconds)**

This optional parameter specifies the idle connection timeout for NFS connections. The value specified must be between 120 and 86400.

**`[-allow-idle-connection {enabled|disabled}]` - Are Idle NFS Connections Supported**

This optional parameter specifies whether to enable idle NFS connections. The default setting is *disabled*.

**`[-v3-hide-snapshot {enabled|disabled}]` - Hide Snapshot Directory under NFSv3 Mount Point**

This optional parameter specifies whether to hide the `.snapshot` directory while listing under NFSv3 mount points. However an explicit access to the `.snapshot` directory will still be allowed even though the option is enabled. The default setting is *disabled* at the time of creation.

## Examples

The following example enables NFS access on a Vserver named `vs0` for NFS clients that use NFS v3 over TCP:

```
cluster1::> vservers nfs modify -vserver vs0 -access true -v3 enabled -udp disabled -tcp enabled
```

## Related Links

- [vserver export-policy rule create](#)

## vserver nfs off

Disable the NFS service of a Vserver

**Availability:** This command is available to *cluster* and *Vserver* administrators at the *admin* privilege level.

## Description

The `vserver nfs off` command disables NFS access on a Vserver. The Vserver must already exist.

## Parameters

### **-vserver <vserver name> - Vserver**

This parameter specifies the Vserver on which you want to disable NFS access.

## **Examples**

The following example disables NFS access on a Vserver named vs0.

```
cluster1::> vserver nfs off -vserver vs0
```

## **vserver nfs on**

Enable the NFS service of a Vserver

**Availability:** This command is available to *cluster* and *Vserver* administrators at the *admin* privilege level.

### **Description**

The `vserver nfs on` command enables NFS access on a Vserver. The Vserver must already exist.

### **Parameters**

#### **-vserver <vserver name> - Vserver**

This parameter specifies the Vserver on which you want to enable NFS access.

## **Examples**

The following example enables NFS access on a Vserver named vs0.

```
cluster1::> vserver nfs on -vserver vs0
```

## **vserver nfs prepare-for-hadoop-non-root-mount-downgrade**

Remove -hadoop-allow-non-root-mount field on all Vservers

**Availability:** This command is available to *cluster* administrators at the *advanced* privilege level.

### **Description**

The `vserver nfs prepare-for-hadoop-non-root-mount-downgrade` command removes -hadoop-allow-non-root-mount field on all the Vservers and disables the `hadoop.non_root.mount` capability on the cluster when downgrading Data ONTAP to a version that does not support Hadoop Non-Root Mount feature.

## **Examples**

The following example removes -hadoop-allow-non-root-mount field on the Vservers and disables the `hadoop.non_root.mount` capability.

```
cluster::1> vservers nfs prepare-for-hadoop-non-root-mount-downgrade
```

## vserver nfs prepare-for-v3-ms-dos-client-downgrade

Disable NFSv3 MS-DOS Client Support

**Availability:** This command is available to *cluster* administrators at the *advanced* privilege level.

### Description

The `vserver nfs prepare-for-v3-ms-dos-client-downgrade` command verifies that the NFSv3 MS-DOS client setting is disabled on all Vservers and disables the NFSv3 MS-DOS client support capability on the cluster when downgrading Data ONTAP to a version that does not support NFSv3 MS-DOS clients.

### Examples

The following example disables NFSv3 MS-DOS client support on the Vservers.

```
cluster::1> vservers nfs prepare-for-v3-ms-dos-client-downgrade
```

## vserver nfs prepare-to-downgrade

Remove NFS configurations that are not compatible with earlier versions of Data ONTAP

**Availability:** This command is available to *cluster* administrators at the *advanced* privilege level.

### Description

The `vserver nfs prepare-to-downgrade` command removes NFS configurations incompatible with the earlier release of Data ONTAP.

### Parameters

#### **-disable-feature-set <downgrade version> - Data ONTAP Version**

This parameter specifies the Data ONTAP version that introduced the new NFS configurations and needs to be removed before downgrade. The value can be one of the following:

- 9.2.0 - Remove the NFS configurations introduced in Data ONTAP release 9.2.0. The configurations include the following:
  - `-file-session-io-grouping-count` .
  - `-file-session-io-grouping duration` .

### Examples

```
cluster1::*> vserver nfs prepare-to-downgrade -disable-feature-set 9.2.0
```

## vserver nfs show

Display the NFS configurations of Vservers

**Availability:** This command is available to *cluster* and *Vserver* administrators at the *admin* privilege level.

### Description

The `vserver nfs show` command displays information about NFS-enabled Vservers. The command output depends on the parameter or parameters specified with the command. If no parameters are specified, the command displays the following information about all NFS-enabled Vservers:

- Vserver name
- Whether general NFS access is enabled
- Whether access to NFSv3 clients is enabled
- Whether access to NFSv4 clients is enabled
- Whether NFS access over UDP is enabled
- Whether NFS access over TCP is enabled
- List of default Windows users (detailed view only)

You can specify additional parameters to display only information that matches those parameters. For instance, to display information only about Vservers that enable access over TCP, enter the command with the `-tcp -enable true` parameter.

### Parameters

**{ [-fields <fieldname>,...]**

If you specify the `-fields` parameter, the command only displays the fields that you specify.

**| [-krb-opts ]**

If you specify the parameter for `-instance`, the command shows detailed information about all NFS-enabled Vservers. Otherwise, if the `-krb-opts` parameter is specified, the command shows the following Kerberos-related information:

- Vserver name
- Maximum number of RPCSEC\_GSS authentication contexts
- Time, in seconds, an RPCSEC\_GSS context can remain idle before being deleted

Otherwise, if the `-fields` parameter is specified, the command shows information about all of the NFS-enabled Vservers that you specify as a comma-delimited list.

**| [-instance ] }**

If you specify the `-instance` parameter, the command displays detailed information about all entries.

**[-vserver <vserver name>] - Vserver**

If you specify this parameter, the command displays information only about the specified NFS-enabled Vserver.

**[-access {true|false}] - General NFS Access**

If you specify this parameter, the command displays information only about the NFS-enabled Vservers that have the specified general-access setting.

**[-rpcsec-ctx-high <integer>] - RPC GSS Context Cache High Water Mark**

If you specify this parameter, the command displays information only about NFS-enabled Vservers that have the specified maximum number of RPCSEC\_GSS authentication contexts.

**[-rpcsec-ctx-idle <integer>] - RPC GSS Context Idle**

If you specify this parameter, the command displays information only about the NFS-enabled Vservers that have the specified timeout value for idle RPCSEC\_GSS contexts.

**[-v3 {enabled|disabled}] - NFS v3**

If you specify this parameter, the command displays information only about the NFS-enabled Vservers for which the v3 option matches the specified input.

**[-v4.0 {enabled|disabled}] - NFS v4.0**

If you specify this parameter, the command displays information only about NFS-enabled Vservers for which the v4.0 option matches the specified input.

**[-udp {enabled|disabled}] - UDP Protocol**

If you specify this parameter, the command displays information only about the NFS-enabled Vservers that have the specified NFS-over-UDP access setting.

**[-tcp {enabled|disabled}] - TCP Protocol**

If you specify this parameter, the command displays information only about the NFS-enabled Vservers that have the specified NFS-over-TCP setting.

**[-default-win-user <text>] - Default Windows User**

If you specify this parameter, the command displays information only about the NFS-enabled Vservers that have the specified list of default Windows users.

**[-enable-ejukebox {true|false}] - Enable NFSv3 EJUKEBOX error**

If you specify this parameter, the command displays information only about the NFS-enabled Vservers for which the enable-ejukebox option matches the specified input.

**[-v3-require-read-attributes {true|false}] - Require All NFSv3 Reads to Return Read Attributes**

If you specify this parameter, the command displays information only about the NFS-enabled Vservers for which NFSv3 read operations are required or not required to return read attributes.

**[-v3-fsid-change {enabled|disabled}] - Show Change in FSID as NFSv3 Clients Traverse Filesystems**

If you specify this parameter, the command displays information about changes in file system identifiers (FSIDs) as NFSv3 clients traverse file systems.



**[`-v3-connection-drop {enabled|disabled}`] - Enable the Dropping of a Connection When an NFSv3 Request is Dropped**

If you specify this parameter, the command displays information only about the NFS-enabled Vservers for which the `v3-connection-drop` option matches the specified input.

**[`-ntfs-unix-security-ops {fail|ignore|use-export-policy}`] - Vserver NTFS Unix Security Options**

If you specify this parameter, the command displays information only about the NFS-enabled Vservers for which the NTFS-UNIX security setting matches the specified input.

**[`-chown-mode {restricted|unrestricted|use-export-policy}`] - Vserver Change Ownership Mode**

If you specify this parameter, the command displays information only about the NFS-enabled Vservers for which the `chown-mode` setting matches the specified input.

**[`-trace-enabled {true|false}`] - NFS Response Trace Enabled**

If you specify this parameter, the command displays information only about the NFS-enabled Vservers for which the `trace-enabled` option matches the specified input.

**[`-trigger <integer>`] - NFS Response Trigger (in secs)**

If you specify this parameter, the command displays information only about the NFS-enabled Vservers with the specified NFS response trigger time.

**[`-udp-max-xfer-size <integer>`] - UDP Maximum Transfer Size (bytes)**

If you specify this parameter, the command displays information only about the NFS-enabled Vservers with the specified UDP maximum transfer size. The range is 8192 to 57344.

**[`-tcp-max-xfer-size <integer>`] - TCP Maximum Transfer Size (bytes)**

If you specify this parameter, the command displays information only about the NFS-enabled Vservers with the specified TCP maximum transfer size. The range is 8192 to 1048576.

**[`-v3-tcp-max-read-size <integer>`] - NFSv3 TCP Maximum Read Size (bytes)**

If you specify this parameter, the command displays information only about the NFS-enabled Vservers with the specified TCP maximum transfer size for NFSv3 read requests. The range is 8192 to 1048576.



This parameter is deprecated and may be removed in a future release of Data ONTAP. Use the `-tcp-max-xfer-size` parameter instead.

**[`-v3-tcp-max-write-size <integer>`] - NFSv3 TCP Maximum Write Size (bytes)**

If you specify this parameter, the command displays information only about the NFS-enabled Vservers with the specified TCP maximum transfer size for NFSv3 write requests. The range is 8192 to 65536.



This parameter is deprecated and may be removed in a future release of Data ONTAP. Use the `-tcp-max-xfer-size` parameter instead.

**[`-v4.0-acl {enabled|disabled}`] - NFSv4.0 ACL Support**

If you specify this parameter, the command displays information only about the NFS-enabled Vservers for which the `v4.0-acl` option matches the specified input.

**[-v4.0-read-delegation {enabled|disabled}] - NFSv4.0 Read Delegation Support**

If you specify this parameter, the command displays information only about the NFS-enabled Vservers for which the `v4.0-read-delegation` option matches the specified input.

**[-v4.0-write-delegation {enabled|disabled}] - NFSv4.0 Write Delegation Support**

If you specify this parameter, the command displays information only about the NFS-enabled Vservers for which the `v4.0-write-delegation` option matches the specified input.

**[-v4-fsid-change {enabled|disabled}] - Show Change in FSID as NFSv4 Clients Traverse Filesystems**

If you specify this parameter, the command displays information only about the NFS-enabled Vservers for which the showing of NFSv4 file system identifier (FSID) changes has been enabled or disabled.

**[-v4.0-referrals {enabled|disabled}] - NFSv4.0 Referral Support**

If you specify this parameter, the command displays information only about the NFS-enabled Vservers for which the `v4.0-referrals` option matches the specified input.

**[-v4-id-domain <nfs domain>] - NFSv4 ID Mapping Domain**

If you specify this parameter, the command displays information only about the NFS-enabled Vservers having the specified domain name.

**[-v4-validate-symlinkdata {enabled|disabled}] - NFSv4 Validate UTF-8 Encoding of Symbolic Link Data**

If you specify this parameter, the command displays information only about the NFS-enabled Vservers for which validation of UTF-8 encoding of symbolic link data has been enabled or disabled.

**[-v4-lease-seconds <integer>] - NFSv4 Lease Timeout Value (in secs)**

If you specify this parameter, it displays the locking lease period. It is expressed in seconds. Clients that have been inactive for a period equal or longer to the lease period may lose all their locking state on a node.

**[-v4-grace-seconds <integer>] - NFSv4 Grace Timeout Value (in secs)**

If you specify this parameter, it displays the grace period for clients to reclaim file locks after a server failure. The grace period is expressed in seconds.

**[-v4-acl-preserve {enabled|disabled}] - Preserves and Modifies NFSv4 ACL (and NTFS File Permissions in Unified Security Style)**

If you specify this parameter, the command displays information only about the NFS-enabled Vservers for which the `v4-acl-preserve` option matches the specified input.

**[-v4.1 {enabled|disabled}] - NFSv4.1 Minor Version Support**

If you specify this parameter, the command displays information only about NFS-enabled Vservers for which the `v4.1` option matches the specified input.

**[-rquota {enabled|disabled}] - Rquota Enable**

If you specify this parameter, the command displays information only about the NFS-enabled Vservers for which the `rquota` option matches the specified input.

**[-v4.1-implementation-domain <nfs domain>] - NFSv4.1 Implementation ID Domain**

If you specify this parameter, the command displays information only about the NFS-enabled Vservers for which the `v4.1-implementation-domain` option matches the specified input.

**[-v4.1-implementation-name <text>] - NFSv4.1 Implementation ID Name**

If you specify this parameter, the command displays information only about the NFS-enabled Vservers for which the `v4.1-implementation-name` option matches the specified input.

**[-v4.1-implementation-date <Date>] - NFSv4.1 Implementation ID Date**

If you specify this parameter, the command displays information only about the NFS-enabled Vservers for which the `v4.1-implementation-date` option matches the specified input.

**[-v4.1-pnfs {enabled|disabled}] - NFSv4.1 Parallel NFS Support**

If you specify this parameter, the command displays information only about the NFS-enabled Vservers for which the `v4.1-pnfs` option matches the specified input.

**[-v4.1-referrals {enabled|disabled}] - NFSv4.1 Referral Support**

If you specify this parameter, the command displays information only about the NFS-enabled Vservers for which the `v4.1-referrals` option matches the specified input.

**[-v4.1-acl {enabled|disabled}] - NFSv4.1 ACL Support**

If you specify this parameter, the command displays information only about the NFS-enabled Vservers for which the `v4.1-acl` option matches the specified input.

**[-vstorage {enabled|disabled}] - NFS vStorage Support**

If you specify this parameter, the command displays information only about the NFS-enabled Vservers for which the `vstorage` option matches the specified input.

**[-v4-numeric-ids {enabled|disabled}] - NFSv4 Support for Numeric Owner IDs**

If you specify this parameter, the command displays information only about the NFS-enabled Vservers for which the `v4-numeric-ids` option matches the specified input.

**[-default-win-group <text>] - Default Windows Group**

If you specify this parameter, the command displays information only about the NFS-enabled Vservers that have the specified list of default Windows groups.

**[-v4.1-read-delegation {enabled|disabled}] - NFSv4.1 Read Delegation Support**

If you specify this parameter, the command displays information only about the NFS-enabled Vservers for which the `v4.1-read-delegation` option matches the specified input.

**[-v4.1-write-delegation {enabled|disabled}] - NFSv4.1 Write Delegation Support**

If you specify this parameter, the command displays information only about the NFS-enabled Vservers for which the `v4.1-write-delegation` option matches the specified input.

**[-v4.x-session-num-slots <integer>] - Number of Slots in the NFSv4.x Session slot tables**

If you specify this parameter, this command displays information only about the NFS-enabled Vservers for which the `v4.x-session-num-slots` option matches the specified input. The range is 1 to 2000.

**[-v4.x-session-slot-reply-cache-size <integer>] - Size of the Reply that will be Cached in Each NFSv4.x Session Slot (in bytes)**

If you specify this parameter, this command displays information only about the NFS-enabled Vservers for which the `v4.x-session-slot-reply-cache-size` option matches the specified input. The cache size is expressed in bytes. The range is 512 to 4096.

**[-v4-acl-max-aces <integer>] - Maximum Number of ACEs per ACL**

If you specify this parameter, the command displays information only about the NFS-enabled Vservers for which the `v4-acl-max-aces` option matches the specified input.

**[-mount-rootonly {enabled|disabled}] - NFS Mount Root Only**

If you specify this parameter, the command displays information only about the NFS-enabled Vservers for which the `mount-rootonly` option matches the specified input.

**[-nfs-rootonly {enabled|disabled}] - NFS Root Only**

If you specify this parameter, the command displays information only about the NFS-enabled Vservers for which the `nfs-rootonly` option matches the specified input.

**[-auth-sys-extended-groups {enabled|disabled}] - AUTH\_SYS Extended Groups Enabled**

If you specify this parameter, the command displays information only about the NFS-enabled Vservers for which the `auth-sys-extended-groups` option matches the specified input.

**[-extended-groups-limit <integer>] - AUTH\_SYS and RPCSEC\_GSS Auxillary Groups Limit**

If you specify this parameter, the command displays information about the NFS-enabled Vservers for which the `extended-groups-limit` option matches the specified input. The range is 32 to 1024.

**[-validate-qtree-export {enabled|disabled}] - Validation of Qtree IDs for Qtree File Operations**

If you specify this parameter, the command displays information only about the NFS-enabled Vservers for which `validate-qtree-export` option matches the specified input.

**[-mountd-port <integer>] - NFS Mount Daemon Port**

If you specify this parameter, the command displays information only about the NFS-enabled Vservers for which the `mountd-port` option matches the specified input.

**[-nlm-port <integer>] - Network Lock Manager Port**

If you specify this parameter, the command displays information only about the NFS-enabled Vservers for which the `nlm-port` option matches the specified input.

**[-nsm-port <integer>] - Network Status Monitor Port**

If you specify this parameter, the command displays information only about the NFS-enabled Vservers for which the `nsm-port` option matches the specified input.

**[-rquotad-port <integer>] - NFS Quota Daemon Port**

If you specify this parameter, the command displays information only about the NFS-enabled Vservers for which the `rquotad-port` option matches the specified input.

**[-permitted-enc-types <NFS Kerberos Encryption Type>, ...] - Permitted Kerberos Encryption Types**

If you specify this parameter, the command displays information only about the NFS-enabled Vservers for

which `permitted-enc-types` option matches any of the following : `des`, `des3`, `aes-128`, `aes-256`.

**`[-showmount {enabled|disabled}] - Showmount Enabled`**

If you specify this parameter, the command displays information only about the NFS-enabled Vserver's for which the `showmount` option matches the specified input.

**`[-name-service-lookup-protocol {TCP|UDP}] - Set the Protocol Used for Name Services Lookups for Exports`**

If you specify this parameter, the command displays information only about the NFS-enabled Vservers for which `-name-service-lookup-protocol` matches the parameter.

**`[-map-unknown-uid-to-default-windows-user {enable|disable}] - Map Unknown UID to Default Windows User`**

If you specify this parameter, the command displays information only about the NFS-enabled Vservers for which `-map-unknown-uid-to-default-windows-user` is enabled or disabled.

**`[-netgroup-dns-domain-search {enabled|disabled}] - DNS Domain Search Enabled During Netgroup Lookup`**

If you specify this parameter, the command displays information only about the NFS-enabled Vservers for which `-netgroup-dns-domain-search` is enabled or disabled.

**`[-netgroup-trust-any-ns-switch-no-match {enabled|disabled}] - Trust No-Match Result from Any Name Service Switch Source During Netgroup Lookup`**

If you specify this parameter, the command displays information only about the NFS-enabled Vservers for which `-netgroup-trust-any-ns-switch-no-match` is enabled or disabled.

**`[-ntacl-display-permissive-perms {enabled|disabled}] - Display maximum NT ACL Permissions to NFS Client`**

If you specify this parameter, the command displays information only about the NFS-enabled Vservers for which `-ntacl-display-permissive-perms` matches the parameter.

**`[-v3-ms-dos-client {enabled|disabled}] - NFSv3 MS-DOS Client Support`**

If you specify this parameter, the command displays information only about NFS-enabled Vservers for which NFSv3 MS-DOS client support is enabled or disabled.

**`[-ignore-nt-acl-for-root {enabled|disabled}] - Ignore the NT ACL Check for NFS User 'root'`**

If you specify this parameter, the command displays information only about the NFS-enabled Vservers for which `-ignore-nt-acl-for-root` is enabled or disabled.

**`[-cached-cred-positive-ttl <integer>] - Time To Live Value (in msec) of a Positive Cached Credential`**

If you specify this parameter, the command displays information about the NFS-enabled Vservers time to live value of the positive cached credentials.

**`[-cached-cred-negative-ttl <integer>] - Time To Live Value (in msec) of a Negative Cached Credential`**

If you specify this parameter, the command displays information about the NFS-enabled Vservers time to live value of the negative cached credentials.

**[`-skip-root-owner-write-perm-check` {`enabled`|`disabled`}] - Skip Permission Check for NFS Write Calls from Root/Owner**

If you specify this parameter, the command displays information only about the NFS-enabled Vservers for which `-skip-root-owner-write-perm-check` is enabled or disabled.

**[`-v3-64bit-identifiers` {`enabled`|`disabled`}] - Use 64 Bits for NFSv3 FSIDs and File IDs**

If you specify this parameter, the command displays information only about the NFS-enabled Vservers for which `-v3-64bit-identifiers` is enabled or disabled.

**[`-v4-inherited-acl-preserve` {`enabled`|`disabled`}] - Ignore Client Specified Mode Bits and Preserve Inherited NFSv4 ACL When Creating New Files or Directories**

If you specify this parameter, the command displays information about the NFS-enabled Vservers for which `-v4-inherited-acl-preserve` matches the specified input.

**[`-v3-search-unconverted-filename` {`enabled`|`disabled`}] - Fallback to Unconverted Filename Search**

If you specify this parameter, the command displays information about the NFS-enabled Vservers for which `-v3-search-unconverted-filename` matches the specified input.

**[`-file-session-io-grouping-count` <`integer`>] - I/O Count to Be Grouped as a Session**

If you specify this parameter, the command displays information about the NFS-enabled SVMs for which the `-file-session-io-grouping-count` matches the specified input.

**[`-file-session-io-grouping-duration` <`integer`>] - Duration for I/O to Be Grouped as a Session (Secs)**

If you specify this parameter, the command displays information about the NFS-enabled SVMs for which the `-file-session-io-grouping-duration` matches the specified input.

**[`-checksum-for-replay-cache` {`enabled`|`disabled`}] - Enable or disable Checksum for Replay-Cache**

If you specify this parameter, the command displays information about the NFS-enabled SVMs for which the `-checksum-for-replay-cache` matches the specified input.

**[`-cached-cred-harvest-timeout` <`integer`>] - Harvest timeout (in msec) for a Cached Credential**

If you specify this parameter, the command displays information about the NFS-enabled Vservers harvest timeout for cached credentials.

**[`-idle-connection-timeout` <`integer`>] - Idle Connection Timeout Value (in seconds)**

If you specify this parameter, the command displays information about the NFS-enabled Vservers idle connections timeout

**[`-allow-idle-connection` {`enabled`|`disabled`}] - Are Idle NFS Connections Supported**

If you specify this parameter, the command displays information only about NFS-enabled Vservers for which the `-allow-idle-connection` option matches the specified input.

**[`-v3-hide-snapshot` {`enabled`|`disabled`}] - Hide Snapshot Directory under NFSv3 Mount Point**

If you specify this parameter, the command displays information about the NFS-enabled Vservers for which `-v3-hide-snapshot` matches the specified input.

## Examples

The following example displays information about all NFS-enabled Vservers:

```
cluster1::> vserver nfs show
      General
Vserver  Access  v3      v4      v4.1    UDP      TCP      Default
User
-----
vs0      true     enabled disabled disabled enabled   enabled -
vs1      true     enabled disabled disabled enabled   enabled -
2 entries were displayed.
```

The following example displays Kerberos-related information about all NFS-enabled Vservers:

```
cluster1::*> vserver nfs show -krb-opts
Vserver Context High Context Idle
-----
vs0      30      30
vs1      30      30
2 entries were displayed.
```

## vserver nfs start

Start the NFS service of a Vserver

**Availability:** This command is available to *cluster* and *Vserver* administrators at the *admin* privilege level.

### Description

The `vserver nfs start` command starts the NFS service on a Vserver to serve NFS clients. The Vserver must already exist.

### Parameters

**-vserver <vserver name> - Vserver**

This parameter specifies the Vserver on which you want to start the NFS service.

## Examples

The following example starts the NFS service on a Vserver named vs0.

```
cluster1::> vserver nfs start -vserver vs0
```

# vserver nfs status

Display the status of the NFS service of a Vserver

**Availability:** This command is available to *cluster* and *Vserver* administrators at the *admin* privilege level.

## Description

The `vserver nfs status` command shows the status of NFS on a Vserver. The Vserver must already exist.

## Parameters

**-vserver <vserver name> - Vserver**

This parameter specifies the Vserver for which you want to see the NFS status.

**[-is-enabled {true|false}] - NFS Service Enabled**

If you specify this optional parameter, the command displays whether NFS is enabled or not. This parameter is true if the NFS server is running.

## Examples

The following example shows the status of NFS on a Vserver named vs0 for which NFS is enabled.

```
cluster1::> vserver nfs status -vserver vs0.  
The NFS server is running.
```

# vserver nfs stop

Stop the NFS service of a Vserver

**Availability:** This command is available to *cluster* and *Vserver* administrators at the *admin* privilege level.

## Description

The `vserver nfs stop` command stops the NFS service on a Vserver to serve NFS clients. The Vserver must already exist.

## Parameters

**-vserver <vserver name> - Vserver**

This parameter specifies the Vserver on which you want to stop the NFS service.

## Examples

The following example stops the NFS service on a Vserver named vs0.



```
cluster1::> vserver nfs stop -vserver vs0
```

## vserver nfs credentials count

Count credentials cached by NFS

**Availability:** This command is available to *cluster* administrators at the *advanced* privilege level.

### Description

The `vserver nfs credentials count` command displays the number of credentials stored in NFS credentials cache on a specific node. This command has no effect if the specified node has no active data.

### Parameters

**-node <nodename> - Node**

The name of the node on which the command is executed.

### Examples

Lists the number of credentials stored by NFS on node node1

```
cluster1::*> vserver nfs credentials count -node node1
```

```
Number of credentials cached by NFS on node "node1": "2"
```

## vserver nfs credentials flush

Flush credentials cached by NFS

**Availability:** This command is available to *cluster* administrators at the *advanced* privilege level.

### Description

The `vserver nfs credentials flush` command deletes credentials from the NFS credentials cache on a specific node for a given Vserver or a given UNIX user. This command has no effect if the vserver that is specified has no active data interfaces on the node where the command is run.

### Parameters

**-node <nodename> - Node**

The name of the node on which the command is executed.

**-vserver <vserver name> - Vserver**

Use this parameter to clear the credential cache for the Vserver you specify.

**{ [-unix-user-id <integer>] - UNIX User ID**

Use this parameter to clear the credential cache for the UNIX user id you specify.

**[-client-ip <IP Address>] - Client IP Address**

Use this parameter to clear the credential cache for the client IP address you specify.

**| [-unix-user-name <text>] - UNIX User Name**

Use this parameter to clear the credential cache for the UNIX user name you specify.

**| [-unix-group-id <integer>] - UNIX Group ID**

Use this parameter to clear the credential cache for the UNIX group id you specify.

**| [-unix-group-name <text>] - UNIX Group Name }**

Use this parameter to clear the credential cache for the UNIX group name you specify.

## Examples

Clear the credential cache for user user1 on node node1 in Vserver vs1.

```
cluster1::*> vserver nfs credentials flush -node node1 -vserver vs1 -unix
-user-name user1
```

```
Number of matching credentials flushed: 1
```

## vserver nfs credentials show

Show credentials cached by NFS

**Availability:** This command is available to *cluster* and *Vserver* administrators at the *advanced* privilege level.

### Description

The `vserver nfs credentials show` command displays the user account credentials stored on a specific node for a given UNIX user. This command has no effect if the vserver specified has no active data interfaces on the node where the command is run.

### Parameters

**{ [-fields <fieldname>,...]**

If you specify the `-fields <fieldname>, ...` parameter, the command output also includes the specified field or fields. You can use `'-fields ?'` to display the fields to specify.

**| [-instance ] }**

If you specify the `-instance` parameter, the command displays detailed information about all fields.

**-node <nodename> - Node**

The name of the node on which the command is executed.

**-vserver <vserver name> - Vserver**

Use this parameter to search for user credentials in the Vserver you specify.

**{ -unix-user-id <integer> - UNIX User ID**

Use this parameter to search for user credentials for the UNIX user id you specify.

**[-client-ip <IP Address>] - Client IP Address**

Use this parameter to search for user credentials for the client ip you specify.

**| -unix-user-name <text> - UNIX User Name**

Use this parameter to search for user credentials for the UNIX user name you specify.

**| -unix-group-id <integer> - UNIX Group ID**

Use this parameter to search for user credentials for the UNIX group id you specify.

**| -unix-group-name <text> - UNIX Group Name }**

Use this parameter to search for user credentials for the UNIX group name you specify.

**[-flags {ip-qualifier-configured|ip-qualifier-not-configured|unix-extended-creds-present|no-unix-extended-creds|unix-extended-creds-requested|unix-creds-transient-failure|cifs-creds-present|no-cifs-creds|cifs-creds-requested|cifs-cifs-transient-failure|place-holder|transient-failure|transient-error-on-last-refresh|id-name-mapping-present|no-id-name-mapping|id-name-mapping-requested|id-name-mapping-transient-failure|unix-cred-is-partial}] - Credential Entry Flags**

The credential entry flags.

**[-last-refresh-time <[<integer>h] [<integer>m] [<integer>s]>] - Time since Last Refresh**

Time since last refreshed.

**[-last-access-time <[<integer>h] [<integer>m] [<integer>s]>] - Time since Last Access**

Time since last access.

**[-hit-count <integer>] - Number of Hits**

Number of times the cached credential is fetched successfully.

**[-unix-cred-flags <integer>] - UNIX Credential Flags**

UNIX credentials flags.

**[-unix-cred-domain-id <integer>] - UNIX Credential Domain ID**

UNIX credentials domain ID.

**[-unix-cred-uid <integer>] - UNIX Credential UID**

User ID of the UNIX user.

**[-unix-cred-primary-gid <integer>] - UNIX Credential Primary GID**

Primary GID of the UNIX user.

**[-unix-cred-additional-gids <integer>,...] - UNIX Credential Additional GIDs**

Additional GIDs of the UNIX user.

**[-win-cred-flags <integer>] - Windows Credential Flags**

Windows credentials flags.

**[-win-cred-user-sid <text>] - Windows Credential User SID**

SID of the windows user.

**[-win-cred-primary-group-sid <text>] - Windows Credential Primary Group SID**

SID of the windows user's primary group.

**[-win-cred-domain-sids <text>, ...] - Windows Credential Domain SIDs**

Domain SIDs of the windows user.

## Examples

Show the credentials cached by NFS Cred Store for the UNIX user node1 on node node1.

```
gnklcluster1::*> vserver nfs credentials show -node gnklcluster1-01
-vserver coke -unix-user-name root
```

#### Credentials

-----

```
                Node: gnklcluster1-01
                Vserver: coke
                Client IP: -
                Flags: ip-qualifier-not-configured, unix-extended-
                creds-present, cifs-creds-present, id-name-mapping-present
                Time since Last Refresh: 10s
                Time since Last Access: 5s
                Hit Count: 24
```

#### Unix Credentials:

```
                Flags: 0
                Domain ID: 0
                UID: 0
                Primary GID: 1
                Additional GIDs: 1
```

#### Windows Credentials:

```
                Flags: 8759
                User SID: S-1-5-21-2552784647-1202982559-4146209732-500
                Primary Group SID: S-1-5-21-2552784647-1202982559-4146209732-513
                Domain SIDs: S-1-5-21-2552784647-1202982559-4146209732
                S-1-1
                S-1-5
                S-1-5-32
```

#### ID-Name Information:

```
                Type: user
                ID: 0
                Name: root
```

## vserver nfs kerberos interface disable

Disable NFS Kerberos on a LIF

**Availability:** This command is available to *cluster* and *Vserver* administrators at the *admin* privilege level.

### Description

The `vserver nfs kerberos interface disable` command disables NFS Kerberos on a logical interface.

## Parameters

### **-vserver <vserver name> - Vserver**

This parameter specifies the Vserver in which the logical interface exists.

### **-lif <lif-name> - Logical Interface**

This parameter specifies the name of the logical interface on which you want to disable NFS Kerberos.

### **[-admin-username <text>] - Account Creation Username**

This optional parameter specifies the administrator user name.

### **[-admin-password <text>] - Account Creation Password**

This optional parameter specifies the administrator password.

## Examples

The following example disables NFS Kerberos on a Vserver named vs0 and a logical interface named datalif1.

```
vs1::> vserver nfs kerberos interface disable -vserver vs0 -lif datalif1
```

## vserver nfs kerberos interface enable

Enable NFS Kerberos on a LIF

**Availability:** This command is available to *cluster* and *Vserver* administrators at the *admin* privilege level.

## Description

The `vserver nfs kerberos interface enable` command enables NFS Kerberos on a logical interface.

## Parameters

### **-vserver <vserver name> - Vserver**

This parameter specifies the Vserver in which the logical interface exists.

### **-lif <lif-name> - Logical Interface**

This parameter specifies the name of the logical interface on which you want to enable NFS Kerberos.

### **[-spn <text>] - Service Principal Name**

This optional parameter specifies the service principal name (SPN) for the logical interface you want to enable. This value must be in the form `nfs/host_name@REALM`, where `host_name` is the fully qualified host name of the Kerberos server, `nfs` is the service, and `REALM` is the name of the Kerberos realm (for instance, `EXAMPLE.COM`). Specify Kerberos realm name in uppercase.

### **[-admin-username <text>] - Account Creation Username**

This optional parameter specifies the administrator user name.

### **[-admin-password <text>] - Account Creation Password**

This optional parameter specifies the administrator password.

### **[-keytab-uri {(ftp|http)://(hostname|IPv4 Address|['IPv6 Address'])...}] - Load Keytab from URI**

This optional parameter specifies loading a keytab file from the specified URI.

### **[-ou <text>] - Organizational Unit**

This optional parameter specifies the organizational unit (OU) under which the Microsoft Active Directory server account will be created when you enable Kerberos using a realm for Microsoft KDC. If this parameter is not specified, the default OU is "CN=Computers".

### **[-machine-account <text>] - Machine Account Name**

This optional parameter specifies the machine account to create in Active Directory

## **Examples**

The following example enables NFS Kerberos on a Vserver named vs0 and a logical interface named datalif1. The SPN is nfs/sec.example.com@AUTH.SEC.EXAMPLE.COM and the keytab file is loaded from <ftp://ftp.example.com/keytab>.

```
vs1::> vsriver nfs kerberos interface enable -vserver vs0 -lif datalif1
-spn nfs/sec.example.com@AUTH.SEC.EXAMPLE.COM -keytab-uri
ftp://ftp.example.com/keytab
```

## **vserver nfs kerberos interface modify**

Modify the Kerberos configuration of an NFS server

**Availability:** This command is available to *cluster* and *Vserver* administrators at the *admin* privilege level.

### **Description**

The `vserver nfs kerberos interface modify` command modifies a Kerberos configuration for NFS. An NFS Kerberos configuration is associated with both a Vserver and a logical interface.

### **Parameters**

#### **-vserver <vserver name> - Vserver**

This parameter specifies the Vserver associated with the NFS Kerberos configuration you want to modify.

#### **-lif <lif-name> - Logical Interface**

This parameter specifies the name of the logical interface associated with the NFS Kerberos configuration you want to modify.

#### **[-kerberos {enabled|disabled}] - Kerberos Enabled**

This optional parameter specifies whether to enable or disable Kerberos for NFS on the specified Vserver and logical interface. If you specify a value of `enable`, you must also specify the `-spn` parameter. The

command prompts you for a user name and password for a Kerberos principal in the same realm as the principal specified by the `-spn` parameter; this principal must have permission to create or modify the principal specified by the `-spn` parameter.

#### **[`-spn <text>`] - Service Principal Name**

This optional parameter specifies the service principal name (SPN) of the Kerberos configuration you want to modify. If you specify a value of `enable` for the `-kerberos` parameter, you must also specify this parameter. This value must be in the form `nfs/host_name@REALM`, where `host_name` is the fully qualified host name of the Kerberos server, `nfs` is the service, and `REALM` is the name of the Kerberos realm (for instance, `EXAMPLE.COM`). Specify Kerberos realm names in uppercase.

#### **[`-admin-username <text>`] - Account Creation Username**

This optional parameter specifies the administrator user name.

#### **[`-keytab-uri {(ftp|http)://(hostname|IPv4 Address|['IPv6 Address'])...}`] - Load Keytab from URI**

This optional parameter specifies loading a keytab file from the specified URI.

#### **[`-ou <text>`] - Organizational Unit**

This optional parameter specifies the organizational unit (OU) under which the Microsoft Active Directory server account will be created when you enable Kerberos using a realm for Microsoft KDC. If this parameter is not specified, the default OU is "CN=Computers".

#### **[`-machine-account <text>`] - Machine Account Name**

This optional parameter specifies the machine account to create in Active Directory

## Examples

The following example enables an NFS Kerberos configuration on a Vserver named `vs0` and a logical interface named `datalif1`. The SPN is `nfs/sec.example.com@AUTH.SEC.EXAMPLE.COM` and the keytab file is loaded from <ftp://ftp.example.com/keytab>.

```
vs1::> vsserver nfs kerberos interface modify -vserver vs0 -lif datalif1
-k Kerberos enabled -spn nfs/sec.example.com@AUTH.SEC.EXAMPLE.COM -keytab
-Uri
ftp://ftp.example.com/keytab
```

## vserver nfs kerberos interface show

Display the Kerberos configurations of NFS servers

**Availability:** This command is available to *cluster* and *Vserver* administrators at the *admin* privilege level.

### Description

The `vserver nfs kerberos interface show` command displays information about Kerberos configurations for NFS. The command output depends on the parameters specified with the command. If you do not specify any parameters, the command displays the following information about all Kerberos configurations for NFS:



- Vserver name
- Logical interface name
- Logical interface IP address
- Whether Kerberos is enabled or disabled
- The Kerberos service principal name (SPN)
- The permitted encryption types

You can specify additional parameters to display only information that matches those parameters. For instance, to display information only about Kerberos configurations for NFS that are enabled, run the command with the `-kerberos enabled` parameter.

## Parameters

**{ [-fields <fieldname>,...]**

If you specify the `-fields <fieldname>, ...` parameter, the command output also includes the specified field or fields. You can use `'-fields ?'` to display the fields to specify.

**| [-instance ] }**

If you specify the `-instance` parameter, the command displays detailed information about all fields.

**[-vserver <vserver name>] - Vserver**

If you specify this parameter and the `-lif` parameter, the command displays information only about the Kerberos configuration or configurations for NFS that are associated with the specified Vserver and logical interface.

**[-lif <lif-name>] - Logical Interface**

If you specify this parameter and the `-vserver` parameter, the command displays information only about the Kerberos configuration or configurations for NFS that are associated with the specified logical interface and Vserver.

**[-address <IP Address>] - IP Address**

If you specify this parameter, the command displays information only about the Kerberos configurations for NFS that are associated with the specified logical-interface IP address.

**[-kerberos {enabled|disabled}] - Kerberos Enabled**

If you specify this parameter, the command displays information only about the Kerberos configurations for NFS that match the specified value.

**[-spn <text>] - Service Principal Name**

If you specify this parameter, the command displays information only about the Kerberos configuration or configurations for NFS that match the specified SPN.

**[-permitted-enc-types <NFS Kerberos Encryption Type>,...] - Permitted Encryption Types**

If you specify this parameter, the command displays information only about the Kerberos configuration for NFS that matches the specified encryption types.

**[-machine-account <text>] - Machine Account Name**

If you specify this parameter, the command displays information only about the Kerberos configuration for

NFS that matches the specified machine account.

## Examples

The following example displays information about the Kerberos configuration for NFS associated with the Vserver vs0 and the logical interface datalif1:

```
vs1::> vserver nfs kerberos interface show -vserver vs0 -lif datalif1
      Vserver: vs1
      Logical Interface: datalif1
      IP Address: 192.0.2.130
      Kerberos Enabled: enabled
      Service Principal Name: nfs/sec.example.com@AUTH.SEC.EXAMPLE.COM
      Permitted Encryption Types: des,des3,aes-128,aes-256
```

## vserver nfs kerberos realm create

Create a Kerberos realm configuration

**Availability:** This command is available to *cluster* and *Vserver* administrators at the *admin* privilege level.

### Description

The `vserver nfs kerberos realm create` command creates a Kerberos realm configuration.

### Parameters

**-vserver <vserver name> - Vserver**

This parameter specifies the Vserver associated with the Kerberos realm configuration that you want to create.

**-realm <text> - Kerberos Realm**

This parameter specifies the name of the Kerberos realm for the configuration.

**-kdc-vendor <Kerberos Key Distribution Center (KDC) Vendor> - KDC Vendor**

This optional parameter specifies the KDC vendor. Specify Microsoft if you are using a Microsoft Active Directory server; specify Other if you are using a UNIX server.

**-kdc-ip <IP Address> - KDC IP Address**

This optional parameter specifies the IP address of the Kerberos Distribution Center (KDC) server.

**[-kdc-port <integer>] - KDC Port**

This optional parameter specifies the port number of the KDC server. The default setting is 88.

**[-clock-skew <integer>] - Clock Skew**

This optional parameter specifies how many seconds of clock skew between the clients and the server are permitted. The default setting is 300 seconds.

**[`-adserver-name <text>`] - Active Directory Server Name**

This optional parameter specifies the name of an Active Directory server for the configuration. Use this parameter only if you specified the value of `-kdc-vendor` parameter as Microsoft.

**[`-adserver-ip <IP Address>`] - Active Directory Server IP Address**

This optional parameter specifies the IP address of an Active Directory server for the configuration. Use this parameter only if you specified the value of the `-kdc-vendor` parameter as Microsoft.

**[`-comment <text>`] - Comment**

This optional parameter specifies a comment for the Kerberos realm configuration.

**[`-adminserver-ip <IP Address>`] - Admin Server IP Address**

This optional parameter specifies the IP address of the administrative server. Use this parameter only if you specified the value of `-kdc-vendor` parameter as Other. The default setting for this parameter is the KDC server's IP address as specified by the `-kdc-ip` parameter.

**[`-adminserver-port <integer>`] - Admin Server Port**

This optional parameter specifies the port number of the administrative server. The default setting is 749. Use this parameter only if you specified the value of `-kdc-vendor` parameter as Other.

**[`-passwordserver-ip <IP Address>`] - Password Server IP Address**

This optional parameter specifies the IP address of the password server. Use this parameter only if you specified the value of `-kdc-vendor` parameter as Other. The default setting for this parameter is the KDC server's IP address as specified by the `-kdc-ip` parameter.

**[`-passwordserver-port <integer>`] - Password Server Port**

This optional parameter specifies the port number of the password server. The default setting is 464. Use this parameter only if you specified the value of `-kdc-vendor` parameter as Other.

## Examples

The following example creates a Kerberos realm named SEC.EXAMPLE.COM for the Vserver named AUTH. The permitted clock skew is 15 seconds. The KDC's IP address is 192.0.2.170 and its port is 88. The KDC vendor is Other (for a UNIX KDC). The administrative server's IP address is 192.0.2.170 and its port is 749. The password server's IP address is 192.0.2.170 and its port is 464.

```
cluster1::> vserver nfs kerberos realm create -vserver AUTH -realm
SEC.EXAMPLE.COM -clock-skew 15 -kdc-ip 192.0.2.170 -kdc-port 88 -kdc
-vendor Other -adminserver-ip 192.0.2.170 -adminserver-port 749
-passwordserver-ip 192.0.2.170 -passwordserver-port 464
```

## vserver nfs kerberos realm delete

Delete a Kerberos realm configuration

**Availability:** This command is available to *cluster* and *Vserver* administrators at the *admin* privilege level.

## Description

The `vserver nfs kerberos realm delete` command deletes a Kerberos realm configuration from the system.

## Parameters

### **-vserver <vserver name> - Vserver**

This parameter specifies the name of the Vserver for the Kerberos realm configuration that you want to delete.

### **-realm <text> - Kerberos Realm**

This parameter specifies the name of the Kerberos realm for the configuration.

## Examples

The following example deletes the Kerberos realm SEC.EXAMPLE.COM from the Vserver named AUTH:

```
cluster1::> vserver nfs kerberos realm delete -vserver AUTH -realm
SEC.EXAMPLE.COM
```

## vserver nfs kerberos realm modify

Modify a Kerberos realm configuration

**Availability:** This command is available to *cluster* and *Vserver* administrators at the *admin* privilege level.

## Description

The `vserver nfs kerberos realm modify` command modifies one or more attributes of a Kerberos realm configuration.

## Parameters

### **-vserver <vserver name> - Vserver**

This parameter specifies the name of the Vserver for the Kerberos realm configuration that you want to modify.

### **-realm <text> - Kerberos Realm**

This optional parameter specifies the name of a Kerberos realm for the configuration.

### **[-kdc-vendor <Kerberos Key Distribution Center (KDC) Vendor>] - KDC Vendor**

This optional parameter specifies the KDC vendor. Specify Microsoft if you are using a Microsoft Active Directory server; specify Other if you are using a UNIX server.

### **[-kdc-ip <IP Address>] - KDC IP Address**

This optional parameter specifies the IP address of the Kerberos Distribution Center (KDC) server.

**[-kdc-port <integer>] - KDC Port**

This optional parameter specifies the port number of the KDC server. The default setting at the time of creation is 88.

**[-clock-skew <integer>] - Clock Skew**

This optional parameter specifies how many seconds of clock-skew between server and the clients are permitted. The default setting at the time of creation is 300 seconds.

**[-adserver-name <text>] - Active Directory Server Name**

This optional parameter specifies the name of an Active Directory server for the configuration. Use this parameter if you specified the value of `-kdc-vendor` parameter as Microsoft.

**[-adserver-ip <IP Address>] - Active Directory Server IP Address**

This optional parameter specifies the IP address of an Active Directory server for the configuration. Use this parameter if you specified the value of the `-kdc-vendor` parameter as Microsoft.

**[-comment <text>] - Comment**

This optional parameter specifies a comment for the Kerberos realm configuration.

**[-adminserver-ip <IP Address>] - Admin Server IP Address**

This optional parameter specifies the IP address of the administrative server. Use this parameter if you specified the value of `-kdc-vendor` parameter as Other.

**[-adminserver-port <integer>] - Admin Server Port**

This optional parameter specifies the port number of the administrative server. The default setting at the time of creation is 749. Use this parameter if you specified the value of the `-kdc-vendor` parameter as Other.

**[-passwordserver-ip <IP Address>] - Password Server IP Address**

This optional parameter specifies the IP address of the password server. Use this parameter if you specified the value of `-kdc-vendor` parameter as Other.

**[-passwordserver-port <integer>] - Password Server Port**

This optional parameter specifies the port number of the password server. The default setting at the time of creation is 464. Use this parameter only if you specified the value of `-kdc-vendor` parameter as Other.

## Examples

The following example modifies the Kerberos realm SEC.EXAMPLE.COM for the Vserver named AUTH to use a Microsoft KDC server with the IP address 192.0.2.170 and an Active Directory server named AUTH.SEC.EXAMPLE.COM with the IP address 192.0.2.170:

```
cluster1:~> vserver nfs kerberos realm modify -vserver AUTH -realm
SEC.EXAMPLE.COM -adserver-name AUTH.SEC.EXAMPLE.COM -adserver-ip
192.0.2.170 -kdc-ip 192.0.2.170 -kdc-vendor Microsoft
```

# vserver nfs kerberos realm show

Display Kerberos realm configurations

**Availability:** This command is available to *cluster* and *Vserver* administrators at the *admin* privilege level.

## Description

The `vserver nfs kerberos realm show` command displays information about Kerberos realm configurations. The command output depends on the parameters specified with the command. If you do not specify any parameters, the command displays the following information about all Kerberos realm configurations:

- Vserver
- Kerberos realm name
- Active Directory server name
- Kerberos Distribution Center (KDC) vendor
- KDC IP address
- The permitted encryption types

## Parameters

**{ [-fields <fieldname>,...]**

If you specify the `-fields <fieldname>, ...` parameter, the command output also includes the specified field or fields. You can use `'-fields ?'` to display the fields to specify.

**| [-instance ] }**

If you specify the `-instance` parameter, the command displays detailed information about all fields.

**[-vserver <vserver name>] - Vserver**

If you specify this parameter, the command displays information only about the Kerberos realm configurations for the specified Vserver.

**[-realm <text>] - Kerberos Realm**

If you specify this parameter, the command displays information only about the Kerberos realm configurations that use the specified Kerberos realm.

**[-kdc-vendor <Kerberos Key Distribution Center (KDC) Vendor>] - KDC Vendor**

If you specify this parameter, the command displays information only about the Kerberos realm configurations that use the specified KDC vendor.

**[-kdc-ip <IP Address>] - KDC IP Address**

If you specify this parameter, the command displays information only about the Kerberos realm configurations that use the specified KDC IP address.

**[-kdc-port <integer>] - KDC Port**

If you specify this parameter, the command displays information only about the Kerberos realm configurations that use the specified KDC port number.

**[-clock-skew <integer>] - Clock Skew**

If you specify this parameter, the command displays information only about the Kerberos realm configurations that use the specified clock skew.

**[-adserver-name <text>] - Active Directory Server Name**

If you specify this parameter, the command displays information only about the Kerberos realm configurations that use the Active Directory server that has the specified name.

**[-adserver-ip <IP Address>] - Active Directory Server IP Address**

If you specify this parameter, the command displays information only about the Kerberos realm configurations that use the Active Directory server that has the specified IP address.

**[-comment <text>] - Comment**

If you specify this parameter, the command displays information only about the Kerberos realm configurations that match the specified comment text.

**[-adminserver-ip <IP Address>] - Admin Server IP Address**

If you specify this parameter, the command displays information only about the Kerberos realm configurations that use the specified administrative-server IP address.

**[-adminserver-port <integer>] - Admin Server Port**

If you specify this parameter, the command displays information only about the Kerberos realm configurations that use the specified administrative-server port number.

**[-passwordserver-ip <IP Address>] - Password Server IP Address**

If you specify this parameter, the command displays information only about the Kerberos realm configurations that use the specified password-server IP address.

**[-passwordserver-port <integer>] - Password Server Port**

If you specify this parameter, the command displays information only about the Kerberos realm configurations that use the specified password-server port number.

**[-permitted-enc-types <NFS Kerberos Encryption Type>,...] - Permitted Encryption Types**

If you specify this parameter, the command displays information only about the Kerberos realm configuration that match the specified encryption types.

## Examples

The following example displays information about all Kerberos realm configurations:

```
cluster1::> vserver nfs kerberos realm show
Kerberos          Active Directory KDC          KDC
Vserver  Realm          Server          Vendor          IP Address
-----  -----
AUTH     SEC.EXAMPLE.COM    AUTH.SEC.EXAMPLE.COM
                                         Microsoft  192.0.2.170
```

# vserver nfs pnfs devices create

Create a new pNFS device and its mapping

**Availability:** This command is available to *cluster* and *Vserver* administrators at the *advanced* privilege level.

## Description

The ``vserver nfs pnfs devices create`` command creates a pNFS device for a given instance of a volume. The actual creation of pNFS devices is automatically done by the pNFS implementation in Data ONTAP kernel. The usage of this command might interfere with the functionality of the pNFS server. Thus, it is advised that this command not be used without supervision by technical support.

## Parameters

### **[`-global-device-table-id <integer>`] - Global Device Mapping Table ID**

This optional parameter specifies the unique identifier that the pNFS devices subsystem assigns to the device that corresponds to the MSID described below. The pNFS devices implementations keeps track of the global unique identifier that needs to be assigned to this device. It is expected that users need not specifically input the device identifier while creation.

### **`-vserver <vserver name>` - Vserver Name**

This parameter specifies the Vserver to which the volumes belong.

### **`-msid <integer>` - Volume MSID**

This parameter uniquely identifies the volume for which you are creating a pNFS device.

### **`-striping-epoch <integer>` - Striping Epoch**

This optional parameter specifies the striping epoch identifier for a volume for which you are creating a pNFS device. For flexible volumes, the value is always 1.

### **`-device-access <integer>` - Device Access Flags**

This optional parameter specifies the type of access that is given to the pNFS device that you are creating. If the value is 1, it means write access. If the value is 0, it means read access. By default, the device is created with write access.

### **`-version <integer>` - Device Version**

This optional parameter specifies the version associated with the pNFS device identifier. By default, the version is set to 1.

### **[`-generation-count <integer>`] - Device Generation**

This optional parameter specifies the generation count associated with the pNFS device identifier. If a device already exists, the existing device is invalidated and the generation number for the device is bumped. If a device does not already exist, a new device is created with generation number 1.



### **[`-create-time` <MM/DD/YYYY HH:MM:SS>] - Device Creation Time**

This optional parameter specifies the time at which the device is created. If the parameter is not specified, the time at which the device is created is stored along with the device.

### **[`-mapping-status` {`available`|`notavailable`}] - Device Mapping Status**

This optional parameter specifies if the mapping exists for a device. If the value is set to "available", the mappings will be created in the device mappings table. If the value is set to "notavailable", the mappings will not be created in the device mappings table.

## Examples

# vserver nfs pnfs devices delete

Delete a pNFS device

**Availability:** This command is available to *cluster* and *Vserver* administrators at the *advanced* privilege level.

## Description

The `vserver nfs pnfs devices delete` command deletes a unique pNFS device. The pNFS device to be deleted is identified by the unique device mapping identifier (`mid`) parameter passed to this operation. When this operation is successful, the device mappings corresponding to the device and the information corresponding to the device itself are removed. You can obtain the global mapping identifier from the list of devices using the command [vserver nfs pnfs devices show](#) .

## Parameters

### **`-global-device-table-id` <integer> - Global Device Mapping Table ID**

This parameter specifies the pNFS global device mapping identifier that uniquely identifies a pNFS device

## Examples

The following example deletes the device information of a device with global mapping identifier value 2.

```
cluster1::> vserver nfs pnfs delete -mid 2
```

## Related Links

- [vserver nfs pnfs devices show](#)

# vserver nfs pnfs devices show

Display pNFS device information

**Availability:** This command is available to *cluster* and *Vserver* administrators at the *advanced* privilege level.

## Description

The `\vserver nfs pnfs devices show`` command displays a pNFS device for a given instance of a volume. The command output depends on the parameter or parameters specified with the command. If you do not specify any parameters, the command displays the following information about all pNFS devices:

- Vserver name
- The global device mapping identifier of the device
- The master data set ID (MSID) of the volume that leads to this device
- The mapping status of the device
- The generation number of the device

You can specify additional parameters to display only information that matches those parameters. For instance, to display information only about devices that are exported as write-only devices, enter the command with the `-access-flags 1` parameter.

## Parameters

**{ [-fields <fieldname>,...]**

If you specify the `-fields` parameter, the command only displays the fields that you specify.

**| [-instance ] }**

If you specify the `-instance` parameter, the command displays detailed information about all entries.

**[-global-device-table-id <integer>] - Global Device Mapping Table ID**

If you specify this parameter, the command displays information only about the unique identifier that the pNFS devices subsystem assigns to the device that is being output.

**[-vserver <vserver name>] - Vserver Name**

If you specify this parameter, the command displays information only about the Vserver that owns the volume represented by MSID.

**[-msid <integer>] - Volume MSID**

If you specify this parameter, the command displays information only about the volume or volumes that match the specified MSID.

**[-striping-epoch <integer>] - Striping Epoch**

If you specify this parameter, the command displays information only about the striping epoch identifier for a volume that serves as the basis for the pNFS device.

**[-device-access <integer>] - Device Access Flags**

If you specify this parameter, the command displays information only about access flags which specify the type of access that is given to the pNFS device. If the value is 1, it means write access. If the value is 0, it means read access.

### **[`-version <integer>`] - Device Version**

If you specify this parameter, the command displays information only about pNFS devices that match the specified version number.

### **[`-generation-count <integer>`] - Device Generation**

If you specify this parameter, the command displays information only about generation count associated with the pNFS device identifier.

### **[`-create-time <MM/DD/YYYY HH:MM:SS>`] - Device Creation Time**

If you specify this parameter, the command displays information only about pNFS devices that were created at the specified time.

### **[`-mapping-status {available|notavailable}`] - Device Mapping Status**

If you specify this parameter, the command displays information only about if the mapping exists for a device. If the value is set to "available", the mappings can be seen in the device mappings table. If the value is set to "notavailable", the mappings will not be seen in the device mappings table.

## **Examples**

The following example displays the information of a device with global mapping identifier 6. The device corresponds to a volume with MSID 2147484673 on Vserver vs1. The device mappings corresponding to this device follow in the mappings table.

```
cluster1::*> vserver nfs pnfs devices show
Vserver Name      Mapping ID      Msid            Mapping Status
Generation
-----
vs1                1                2147484673      available       6

cluster1::*> vserver nfs pnfs devices mappings show
Vserver Name      Mapping ID      Dsid            LIF IP
-----
vs1                1                1025            10.53.4.14
```

## **vserver nfs pnfs devices cache show**

Display the device cache

**Availability:** This command is available to *cluster* administrators at the *advanced* privilege level.

### **Description**

The ``vserver nfs pnfs devices cache show`` command displays the device cache.

## Parameters

**{ [-fields <fieldname>,...]**

If you specify the `-fields` parameter, the command only displays the fields that you specify.

**| [-instance ] }**

If you specify the `-instance` parameter, the command displays detailed information about all entries.

**[-node {<nodename>|local}] - Node**

If you specify this parameter, the command displays information only about the pNFS devices cache present on the node.

**[-vserver <vserver name>] - Vserver Name**

If you specify this parameter, the command displays information only about the Vserver that has the pNFS devices cache.

## Examples

### vserver nfs pnfs devices mappings show

Display the list of pNFS device mappings

**Availability:** This command is available to *cluster* and *Vserver* administrators at the *advanced* privilege level.

## Description

The `xref:{relative_path}vserver-nfs-pnfs-devices-show.html[vserver nfs pnfs devices show]` command displays a pNFS device for a given instance of a volume. The command output depends on the parameter or parameters specified with the command. If you do not specify parameters, the command displays the following information about all pNFS devices:

- Vserver name
- The global device mapping identifier of the device
- The Data Set ID (DSID) of the constituent volume
- The LIF IP address that serves the constituent on the same controller.

You can specify additional parameters to display only information that matches those parameters. For instance, to display information only about devices that are exported as write-only devices, enter the command with the `-access-flags 1` parameter.

## Parameters

**{ [-fields <fieldname>,...]**

If you specify the `-fields` parameter, the command only displays the fields that you specify.

**[ `-instance` ] }**

If you specify the `-instance` parameter, the command displays detailed information about all entries.

**[ `-global-device-table-id <integer>` ] - Global Device Mapping Table ID**

This specifies the unique identifier that the pNFS devices subsystem assigns to the device whose mappings are being output.

**[ `-vserver <vserver name>` ] - Vserver Name**

If you specify this parameter, the command displays information only about the Vserver that the mapping identifier and DSID belong to.

**[ `-dsid <integer>` ] - Constituent Volume DSID**

If you specify this parameter, the command displays information only about the volume or volumes that match the specified DSID.

**[ `-lifip <IP Address>` ] - LIF IP Address**

If you specify this parameter, the command displays information only about the pNFS devices that match the specified LIF IP address.

## Examples

The following example displays the device information of a device with global mapping identifier 6. The device corresponds to a volume with MSID 2147484673 on Vserver vs1. The device has one constituent with DSID 1025 and is served by the LIF with the IP address 10.53.4.14.

```
cluster1::*> vserver nfs pnfs devices* show
Vserver Name      Mapping ID      Msid            Mapping Status
Generation
-----
vs1                1                2147484673      available       6

cluster1::*> vserver nfs pnfs devices mappings show
Vserver Name      Mapping ID      Dsid            Lif IP
-----
vs1                1                1025            10.53.4.14
```

## Related Links

- [vserver nfs pnfs devices show](#)

## Copyright information

Copyright © 2022 NetApp, Inc. All Rights Reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means—graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system—without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

LIMITED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (b)(3) of the Rights in Technical Data -Noncommercial Items at DFARS 252.227-7013 (FEB 2014) and FAR 52.227-19 (DEC 2007).

Data contained herein pertains to a commercial product and/or commercial service (as defined in FAR 2.101) and is proprietary to NetApp, Inc. All NetApp technical data and computer software provided under this Agreement is commercial in nature and developed solely at private expense. The U.S. Government has a non-exclusive, non-transferrable, nonsublicensable, worldwide, limited irrevocable license to use the Data only in connection with and in support of the U.S. Government contract under which the Data was delivered. Except as provided herein, the Data may not be used, disclosed, reproduced, modified, performed, or displayed without the prior written approval of NetApp, Inc. United States Government license rights for the Department of Defense are limited to those rights identified in DFARS clause 252.227-7015(b) (FEB 2014).

## Trademark information

NETAPP, the NETAPP logo, and the marks listed at <http://www.netapp.com/TM> are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.