



network trace commands

ONTAP 9.9.1 commands

NetApp
February 12, 2024

Table of Contents

- network trace commands 1
 - network trace show 1
 - network trace start 1
 - network trace stop 2
 - network trace file delete 3
 - network trace file show 4

network trace commands

network trace show

Show running network trace instances

Availability: This command is available to *cluster* administrators at the *admin* privilege level.

Description

The `network trace show` command shows currently running packet traces on a matching node.

Parameters

{ [-fields <fieldname>,...]

If you specify the `-fields <fieldname>, ...` parameter, the command output also includes the specified field or fields. You can use `'-fields ?'` to display the fields to specify.

| [-instance] }

If you specify the `-instance` parameter, the command displays detailed information about all fields.

[-node {<nodename>|local}] - Node Name

Use this parameter optionally to show the details of running packet traces on a matching node.

[-port {<netport>|<ifgrp>}] - Port

Use this parameter optionally to show the details of running packet trace on a matching network interface.

Examples

The following example shows the details of running packet traces on nodes "node1" and "node2":

```
cluster1::> network trace show
Node      Port
-----
node1
          e0a
node2
          e0c
```

network trace start

trace start

Availability: This command is available to *cluster* and *Vserver* administrators at the *admin* privilege level.

Description

The `network trace start` command starts packet tracing with the given parameters. The best practice is to temporarily disable Snapshots on the root volume while the network trace is running.

Parameters

-node {<nodename>|local} - Node Name

Use this parameter to specify the node on which the packet trace should run.

-port {<netport>|<ifgrp>} - Port

Use this parameter to specify the network interface for packet tracing.

[-address <IP Address>] - IP Address

Use this parameter to optionally specify the address for packet tracing.

[-protocol-port <integer>] - Protocol Port Number

Use this parameter to optionally specify the protocol port number for packet tracing.

[-buffer-size <integer>] - Buffer Size in KB

Use this parameter to optionally specify the buffer size for packet tracing. The default buffer size is 4 KB.

[-file-size <integer>] - Trace File Size in MB

Use this parameter to optionally specify the trace file size for packet tracing. The default trace file size is 1 GB.

[-rolling-traces <integer>] - Number of Rolling Trace Files

Use this parameter to optionally specify the number of rolling trace files for packet tracing. The default number of rolling trace files is 2.

Examples

The following example starts packet tracing on node "node1" with address "10.98.16.164", network port "e0c", buffer size "10 KB", and protocol port number "10000":

```
cluster1::> network trace start -node node1
          -address 10.98.16.164 -port e0c -buffer-size 10 -protocol-port 10000
```

The following example disables Snapshots on the root volume. Snapshots should be re-enabled after the trace is stopped.

```
cluster1::> node run -node node1 vol options vol0 nosnap on
```

network trace stop

Stop an active network trace

Availability: This command is available to *cluster* administrators at the *admin* privilege level.

Description

The `network trace stop` command stops a running packet trace on a given network interface. The trace files could be located in `/mroot/etc/log/packet_traces/`.

Parameters

-node {<nodename>|local} - Node Name

Use this parameter to specify the node on which the packet tracing must be stopped.

-port {<netport>|<ifgrp>} - Port

Use this parameter to specify the network interface on which the packet tracing must be stopped.

Examples

The following example stops a packet trace on network interface "e0a" from node "node1":

```
cluster1::> network trace stop -node node1 -port e0a
```

network trace file delete

Delete a network trace file

Availability: This command is available to *cluster* administrators at the *admin* privilege level.

Description

The `network trace file delete` command deletes the network trace file from a matching node.

Parameters

-node {<nodename>|local} - Node Name

Use this parameter to delete the network trace file from a matching node.

-trace-file <text> - Trace File

Use this parameter to specify the network trace file to be deleted.

Examples

The following example deletes the list of network trace files from node "node1" using wildcard pattern:

```
cluster1::> network trace file delete -node node1 -trace-file *
```

network trace file show

Show list of network trace files

Availability: This command is available to *cluster* administrators at the *admin* privilege level.

Description

The `network trace file show` command shows the list of network trace files located in the `/mroot/etc/log/packet_traces/` directory.

Parameters

{ [-fields <fieldname>,...]

If you specify the `-fields <fieldname>, ...` parameter, the command output also includes the specified field or fields. You can use `-fields ?` to display the fields to specify.

| [-instance] }

If you specify the `-instance` parameter, the command displays detailed information about all fields.

[-node {<nodename>|local}] - Node Name

Use this parameter to show the list of traces files of a matching node.

[-trace-file <text>] - Trace File

Use this parameter optionally to show the list of trace files with a matching trace-file name.

Examples

The following example shows the list of trace files on nodes "node1" and "node2":

```
cluster1::> network trace file show
Node          Trace File
-----
node1
              e0a_20170314_115624.trc0
node2
              e0c_20170314_115624.trc0
```

Copyright information

Copyright © 2024 NetApp, Inc. All Rights Reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means—graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system—without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

LIMITED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (b)(3) of the Rights in Technical Data -Noncommercial Items at DFARS 252.227-7013 (FEB 2014) and FAR 52.227-19 (DEC 2007).

Data contained herein pertains to a commercial product and/or commercial service (as defined in FAR 2.101) and is proprietary to NetApp, Inc. All NetApp technical data and computer software provided under this Agreement is commercial in nature and developed solely at private expense. The U.S. Government has a non-exclusive, non-transferrable, nonsublicensable, worldwide, limited irrevocable license to use the Data only in connection with and in support of the U.S. Government contract under which the Data was delivered. Except as provided herein, the Data may not be used, disclosed, reproduced, modified, performed, or displayed without the prior written approval of NetApp, Inc. United States Government license rights for the Department of Defense are limited to those rights identified in DFARS clause 252.227-7015(b) (FEB 2014).

Trademark information

NETAPP, the NETAPP logo, and the marks listed at <http://www.netapp.com/TM> are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.