

# master events

ONTAP 9.11.1 EMS reference

NetApp August 29, 2024

This PDF was generated from https://docs.netapp.com/us-en/ontap-ems-9111/master-cast-events.html on August 29, 2024. Always check docs.netapp.com for the latest.

# **Table of Contents**

naster events	. 1
master.cast events	. 1
master.demote events	2
master.new events	3
master.promoting events	3
master.releasing events	. 4
master.try events	. 4

# master events

# master.cast events

# master.cast.cm.vote.against

#### Severity

NOTICE

#### Description

This message occurs when the master service of the associated node can not connect to current cluster master and try to cast a vote against current cluster master in the global database. The current cluster master will be demoted if more than half of the cluster nodes vote against it, and a new cluster master will be promoted.

#### **Corrective Action**

(None).

### Syslog Message

Service ID "%u" on node ID "%u" has voted against current cluster master with sequence number "%u" based on "%s", the current MVIP connection state is %s with duration %s, and the best connection state is %s.

#### Parameters

serviceID (INT): Service ID that identifies the associated master service.
nodeID (INT): Node ID number of the associated node.
sequenceNumber (INT): The sequence number of the cluster master.
reason (STRING): The reason for casting the vote against current cluster master.
currentState (STRING): The current MVIP connection state.
currentStateDuration (STRING): The duration of current MVIP connection state.
highestState (STRING): The best MVIP connection state since the node connects to current cluster master.

# master.cast.cm.vote.ex

#### Severity

NOTICE

#### Description

This message occurs when the master service on the associated node is unable to cast a vote to update the connection status with current cluster master in global database since it has lost connection to the database server.

# **Corrective Action**

(None).

# Syslog Message

Service ID "%u" on node ID "%u" failed to cast a vote to cluster master with sequence number is "%u" due to exception (%s). The connection state is %s with duration %s, and the best connection state is %s.

#### Parameters

serviceID (INT): Service ID that identifies the associated master service.
nodeID (INT): Node ID number of the associated node.
sequenceNumber (INT): The sequence number of current cluster master.
exceptionCode (STRING): The exception code.
currentState (STRING): The current MVIP connection state.
currentStateDuration (STRING): The duration of current MVIP connection state.
highestState (STRING): The best MVIP connection state since the node connects to current cluster master.

# master.demote events

# master.demote.cm.committed

#### Severity

NOTICE

#### Description

This message occurs when the associated node successfully updated the global database to demote current cluster master. As a result, a new cluster will be promoted.

#### **Corrective Action**

(None).

#### Syslog Message

Service ID "%u" on node ID "%u" successfully updated database to demote cluster master with serviceID "%u" and sequenceNumber "%u".

#### **Parameters**

serviceID (INT): Service ID that identifies the associated master service.
 nodeID (INT): Node ID number of the associated node.
 lastKnownLeaderID (INT): Service ID number of the cluster master last known by this node.
 sequenceNumber (INT): The sequence number of the cluster master last known by this node.

#### master.demote.cm.ex

#### Severity

NOTICE

#### Description

This message occurs when the associated node tries to update the global database to demote current cluster master but the operation failed due to an exception. This could happen if another cluster node already made the same database change, or the connection to global database has lost.

#### **Corrective Action**

(None).

#### Syslog Message

Service ID "%u" on node ID "%u" failed to update database to demote cluster master with serviceID "%u" with exception (%s).

#### Parameters

serviceID (INT): Service ID that identifies the associated master service. nodeID (INT): Node ID number of the associated node. lastKnownLeaderID (INT): Service ID number of the cluster master last known by this node. exceptionCode (STRING): The exception code.

# master.new events

### master.new.connection.state

#### Severity

NOTICE

#### Description

This message occurs when the connection state from the associated node to current cluster master has changed.

#### **Corrective Action**

(None).

#### Syslog Message

Service ID "%u" on node ID "%u" has a new MVIP connection state "%s" and the best connection state is "%s".

#### **Parameters**

serviceID (INT): Service ID that identifies the associated master service.
nodeID (INT): Node ID number of the associated node.
currentState (STRING): The current MVIP connection state.
highestState (STRING): The best MVIP connection state since the node connects to current cluster master.

# master.promoting events

# master.promoting.cm

#### Severity

NOTICE

#### Description

This message occurs when the node is promoted to the cluster master and takes constrol as the master.

#### **Corrective Action**

(None).

#### Syslog Message

Service ID "%u" on node ID "%u" is taking over as the cluster master.

#### **Parameters**

**serviceID** (INT): Service ID that identifies the associated master service. **nodeID** (INT): Node ID number of the associated node.

# master.releasing events

# master.releasing.cm

#### Severity

NOTICE

### Description

This message occurs when the node is demoted from being the cluster master, and it releases control as the master.

# **Corrective Action**

(None).

### Syslog Message

Service ID "%u" on node ID "%u" is releasing control as the cluster master.

### Parameters

**serviceID** (INT): Service ID that identifies the associated master service. **nodeID** (INT): Node ID number of the associated node.

# master.try events

# master.try.demote.cm

#### Severity

NOTICE

#### Description

This message occurs when the associated node cannot not connect to current cluster master and tries to demote it by making associated gloabal database change. The database change may fail if multiple cluster nodes try to do the same thing, and one of them has updated global database successfully.

#### **Corrective Action**

(None).

# Syslog Message

Service ID "%u" on node ID "%u" tries to demote the cluster master with serviceID "%u" and sequenceNumber "%u" from the global database based on the votes (forVotes=%u, againstVotes=%u, staleVotes=%u).

#### Parameters

serviceID (INT): Service ID that identifies the associated master service.

nodeID (INT): Node ID number of the associated node.

**lastKnownLeaderID** (INT): Service ID number of the cluster master last known by this node. **sequenceNumber** (INT): The sequence number of the cluster master last known by this node. **forVotes** (INT): The number of votes to keep current cluster master in the poll. **againstVotes** (INT): The number of votes to demote current cluster master in the poll. **staleVotes** (INT): The number of stale votes to update current cluster master in the poll.

### **Copyright information**

Copyright © 2024 NetApp, Inc. All Rights Reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means—graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system—without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP "AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

LIMITED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (b)(3) of the Rights in Technical Data -Noncommercial Items at DFARS 252.227-7013 (FEB 2014) and FAR 52.227-19 (DEC 2007).

Data contained herein pertains to a commercial product and/or commercial service (as defined in FAR 2.101) and is proprietary to NetApp, Inc. All NetApp technical data and computer software provided under this Agreement is commercial in nature and developed solely at private expense. The U.S. Government has a non-exclusive, non-transferrable, nonsublicensable, worldwide, limited irrevocable license to use the Data only in connection with and in support of the U.S. Government contract under which the Data was delivered. Except as provided herein, the Data may not be used, disclosed, reproduced, modified, performed, or displayed without the prior written approval of NetApp, Inc. United States Government license rights for the Department of Defense are limited to those rights identified in DFARS clause 252.227-7015(b) (FEB 2014).

#### **Trademark information**

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.