



Removing a Disaster Recovery group

ONTAP MetroCluster

Ivana Devine, Martin Houser, Thom Illingworth
August 27, 2021

Table of Contents

- Removing a Disaster Recovery group 1
 - Removing the DR group nodes from each cluster 2


Removing a Disaster Recovery group

Starting with ONTAP 9.8, you can remove a DR group from an eight-node MetroCluster configuration to create a four-node MetroCluster configuration.


This procedure is supported on ONTAP 9.8 and later. On earlier versions of ONTAP, please contact technical support to remove a DR group.

[NetApp Support](#)

An eight-node configuration includes eight-nodes organized as two four-node DR groups.



By removing a DR Group, four nodes remain in the configuration.



Removing the DR group nodes from each cluster

- You must perform this step on both clusters.
- The `metrocluster remove-dr-group` command is supported only on ONTAP 9.8 and later.
 1. Prepare for the removal of the DR group, if you haven't already.
 - a. Move all data volumes to another DR group.
 - b. Move all MDV_CRS metadata volumes to another DR group. Follow the steps in the following procedure: [Moving a metadata volume in MetroCluster configurations](#)
 - c. Delete all MDV_aud metadata volumes that might exist in the DR group to be removed.
 - d. Delete all data aggregates in the DR group to be removed as shown in the following example:

```
ClusterA::> storage aggregate show -node ClusterA-01, ClusterA-02
-fields aggregate ,node
ClusterA::> aggr delete -aggregate aggregate_name
ClusterB::> storage aggregate show -node ClusterB-01, ClusterB-02
-fields aggregate ,node
ClusterB::> aggr delete -aggregate aggregate_name
```



Root aggregates are not deleted.

- e. Migrate all data LIFs to home nodes in another DR group.


```
network interface show -home-node old_node

network interface modify -vserver svm-name -lif data-lif -home-port port-id
```
- f. Migrate the cluster management LIF to a home node in another DR group.


```
network interface show -role cluster-mgmt

network interface modify -vserver svm-name -lif data-lif -home-port port-
```

id

Node management and inter-cluster LIFs are not migrated.

- g. Transfer epsilon to a node in another DR group if required.

```
ClusterA::> set advanced
ClusterA::*> cluster show
Move epsilon if needed
ClusterA::*> cluster modify -node nodename -epsilon false
ClusterA::*> cluster modify -node nodename -epsilon true

ClusterB::> set advanced
ClusterB::*> cluster show
ClusterB::*> cluster modify -node nodename -epsilon false
ClusterB::*> cluster modify -node nodename -epsilon true
ClusterB::*> set admin
```

2. Identify and remove the DR group.

- a. Identify the correct DR group for removal:

```
metrocluster node show
```

- b. Remove the DR group nodes:

```
metrocluster remove-dr-group -dr-group-id 1
```

The following example shows the removal of the DR group configuration on cluster_A.

```

cluster_A::*>

Warning: Nodes in the DR group that are removed from the
MetroCluster
        configuration will lose their disaster recovery
protection.

        Local nodes "node_A_1-FC, node_A_2-FC" will be removed
from the
        MetroCluster configuration. You must repeat the operation
on the
        partner cluster "cluster_B" to remove the remote nodes in
the DR group.
Do you want to continue? {y|n}: y

Info: The following preparation steps must be completed on the
local and partner
        clusters before removing a DR group.

        1. Move all data volumes to another DR group.
        2. Move all MDV_CRS metadata volumes to another DR group.
        3. Delete all MDV_aud metadata volumes that may exist in the
DR group to
        be removed.
        4. Delete all data aggregates in the DR group to be removed.
Root
        aggregates are not deleted.
        5. Migrate all data LIFs to home nodes in another DR group.
        6. Migrate the cluster management LIF to a home node in
another DR group.
        Node management and inter-cluster LIFs are not migrated.
        7. Transfer epsilon to a node in another DR group.

        The command is vetoed if the preparation steps are not
completed on the
        local and partner clusters.
Do you want to continue? {y|n}: y
[Job 513] Job succeeded: Remove DR Group is successful.

cluster_A::*>

```

3. Repeat the previous step on the partner cluster.
4. If in a MetroCluster IP configuration, remove the MetroCluster connections on the nodes of the old DR group.

These commands can be issued from either cluster and apply to the entire DR group spanning both the clusters.

- a. Disconnect the connections:

```
metrocluster configuration-settings connection disconnect dr-group-id
```

- b. Delete the MetroCluster interfaces on the nodes of the old DR group:

```
metrocluster configuration-settings interface delete
```

- c. Delete the old DR group's configuration.

```
metrocluster configuration-settings dr-group delete
```

5. Unjoin the nodes in the old DR group.

You must perform this step on each cluster.

- a. Set the advanced privilege level:

```
set -privilege advanced
```

- b. Unjoin the node:

```
cluster unjoin -node node-name
```

Repeat this step for the other local node in the old DR group.

- c. Set the admin privilege level:

```
set -privilege admin
```

6. Re-enable cluster HA in the new DR group:

```
cluster ha modify -configured true
```

You must perform this step on each cluster.

7. Halt, power down, and remove the old controller modules and storage shelves.

Copyright Information

Copyright © 2021 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system- without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP "AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at <http://www.netapp.com/TM> are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.