



Manage Duo profiles for an SVM or cluster

ONTAP 9.15.1 REST API reference

NetApp
September 11, 2024

Table of Contents

- Manage Duo profiles for an SVM or cluster 1
 - Security authentication duo profiles owner.uuid endpoint overview 1
 - Delete a Duo profile for an SVM or cluster 2
 - Retrieve a Duo profile configured for an SVM or cluster 4
 - Update a Duo profile configured for an SVM or cluster 10

Manage Duo profiles for an SVM or cluster

Security authentication duo profiles owner.uuid endpoint overview

Overview

This API configures the Duo profile for an SVM. Specify the owner UUID. The owner UUID corresponds to the UUID of the SVM containing the Duo profile and can be obtained from the response body of the GET request performed on the API `"/api/svm/svms"`.

Examples

Retrieving the specific configured Duo profile of the cluster or SVM

```
# The API:
GET "/api/security/authentication/duo/profiles/{owner.uuid}"

# The call:
curl -k https://<mgmt-
ip>/api/security/authentication/duo/profiles/f810005a-d908-11ed-a6e6-
0050568e8ef2

# the response:
{
  "owner": {
    "uuid": "f810005a-d908-11ed-a6e6-0050568e8ef2",
    "name": "cluster-1"
  },
  "integration_key": "AAAA1A11A1AAA1AAA111",
  "fingerprint":
  "xxxxxxxxxc8f58b1d52317e1212e9f067a958c387e5e2axxxxxxxxxxxxxxxxxxxxx",
  "api_host": "api-*****.duosecurity.com",
  "status": "Ok",
  "is_enabled": true,
  "auto_push": true,
  "push_info": true,
  "fail_mode": "safe",
  "max_prompts": 1,
  "comment": "Duo profile for Cserver",
}
```

Modifying the Duo profile

```
# The API:
PATCH "/api/security/authentication/duo/profiles/{owner.uuid}"

# The call:
curl -k "https://<mgmt-
ip>/api/security/authentication/duo/profiles/f810005a-d908-11ed-a6e6-
0050568e8ef2" --request PATCH --data "{ \"comment\": \"Testing\",
\"auto_push\": false}"

# the response:
{}
```

Deleting the Duo profile

```
# The API:
DELETE "/api/security/authentication/duo/profiles/{owner.uuid}"

# The call:
curl -k https://<mgmt-
ip>/api/security/authentication/duo/profiles/f810005a-d908-11ed-a6e6-
0050568e8ef2 --request DELETE

# the response:
{}
```

Delete a Duo profile for an SVM or cluster

```
DELETE /security/authentication/duo/profiles/{owner.uuid}
```

Introduced In: 9.14

Deletes the Duo profile of the SVM or cluster.

Related ONTAP commands

- `security login duo delete`

Learn more

- [DOC /security/authentication/duo/profiles/{owner.uuid}](#)
- [DOC /security/accounts](#)

Parameters

Name	Type	In	Required	Description
owner.uuid	string	path	True	Account owner UUID.

Response

Status: 200, Ok

Error

Status: Default, Error

Name	Type	Description
error	returned_error	

Example error

```
{
  "error": {
    "arguments": [
      {
        "code": "string",
        "message": "string"
      }
    ],
    "code": "4",
    "message": "entry doesn't exist",
    "target": "uuid"
  }
}
```

Definitions

See Definitions

error_arguments

Name	Type	Description
code	string	Argument code
message	string	Message argument

returned_error

Name	Type	Description
arguments	array[error_arguments]	Message arguments
code	string	Error code
message	string	Error message
target	string	The target parameter that caused the error.

Retrieve a Duo profile configured for an SVM or cluster

GET /security/authentication/duo/profiles/{owner.uuid}

Introduced In: 9.14

Retrieves the Duo profile configured for the cluster or an SVM.

Related ONTAP commands

- `security login duo show`

Learn more

- [DOC /security/authentication/duo/profiles/{owner.uuid}](#)
- [DOC /security/accounts](#)

Parameters

Name	Type	In	Required	Description
owner.uuid	string	path	True	Account owner UUID.

Name	Type	In	Required	Description
fields	array[string]	query	False	Specify the fields to return.

Response

Status: 200, Ok

Name	Type	Description
_links	_links	
api_host	string	The URL at which the Duo API is hosted.
auto_push	boolean	Automatically sends a push notification for authentication when using Duo.
comment	string	Comment for the Duo profile.
fail_mode	string	Determines the behavior of the system when it cannot communicate with the Duo service.
fingerprint	string	The SHA fingerprint corresponding to the Duo secret key.
http_proxy	string	Specifies the HTTP proxy server to be used when connecting to the Duo service.
integration_key	string	The Integration Key associated with the Duo profile.
is_enabled	boolean	Indicates whether the Duo authentication feature is active or inactive.
max_prompts	integer	The maximum number of authentication attempts allowed for a user before the process is terminated.
owner	owner	SVM name and UUID for which the Duo profile is configured.

Name	Type	Description
push_info	boolean	Additional information sent along with the push notification for Duo authentication.
secret_key	string	The Secret Key associated with the Duo profile.
status	string	Information on the reachability status of Duo.

Example response

```
{
  "_links": {
    "next": {
      "href": "/api/resourcelink"
    },
    "self": {
      "href": "/api/resourcelink"
    }
  },
  "api_host": "api-****.duo.com",
  "auto_push": 1,
  "comment": "string",
  "fail_mode": "safe",
  "fingerprint": "string",
  "http_proxy": "IPAddress:port",
  "integration_key": "string",
  "is_enabled": 1,
  "max_prompts": 1,
  "owner": {
    "_links": {
      "self": {
        "href": "/api/resourcelink"
      }
    },
    "name": "svm1",
    "uuid": "02c9e252-41be-11e9-81d5-00a0986138f7"
  },
  "push_info": 1,
  "secret_key": "string",
  "status": "OK"
}
```

Error

Status: Default, Error

Name	Type	Description
error	returned_error	

Example error

```
{
  "error": {
    "arguments": [
      {
        "code": "string",
        "message": "string"
      }
    ],
    "code": "4",
    "message": "entry doesn't exist",
    "target": "uuid"
  }
}
```

Definitions

See Definitions

href

Name	Type	Description
href	string	

_links

Name	Type	Description
next	href	
self	href	

_links

Name	Type	Description
self	href	

owner

SVM name and UUID for which the Duo profile is configured.

Name	Type	Description
_links	_links	
name	string	The name of the SVM. This field cannot be specified in a PATCH method.
uuid	string	The unique identifier of the SVM. This field cannot be specified in a PATCH method.

error_arguments

Name	Type	Description
code	string	Argument code
message	string	Message argument

returned_error

Name	Type	Description
arguments	array[error_arguments]	Message arguments

Name	Type	Description
code	string	Error code
message	string	Error message
target	string	The target parameter that caused the error.

Update a Duo profile configured for an SVM or cluster

PATCH /security/authentication/duo/profiles/{owner.uuid}

Introduced In: 9.14

Updates a configured Duo profile for a cluster or an SVM.

Related ONTAP commands

- `security login duo modify`

Learn more

- [DOC /security/authentication/duo/profiles/{owner.uuid}](#)
- [DOC /security/accounts](#)

Parameters

Name	Type	In	Required	Description
owner.uuid	string	path	True	Account owner UUID

Request Body

Name	Type	Description
_links	_links	
api_host	string	The URL at which the Duo API is hosted.
auto_push	boolean	Automatically sends a push notification for authentication when using Duo.
comment	string	Comment for the Duo profile.

Name	Type	Description
fail_mode	string	Determines the behavior of the system when it cannot communicate with the Duo service.
fingerprint	string	The SHA fingerprint corresponding to the Duo secret key.
http_proxy	string	Specifies the HTTP proxy server to be used when connecting to the Duo service.
integration_key	string	The Integration Key associated with the Duo profile.
is_enabled	boolean	Indicates whether the Duo authentication feature is active or inactive.
max_prompts	integer	The maximum number of authentication attempts allowed for a user before the process is terminated.
owner	owner	SVM name and UUID for which the Duo profile is configured.
push_info	boolean	Additional information sent along with the push notification for Duo authentication.
secret_key	string	The Secret Key associated with the Duo profile.
status	string	Information on the reachability status of Duo.

Example request

```
{
  "_links": {
    "next": {
      "href": "/api/resourcelink"
    },
    "self": {
      "href": "/api/resourcelink"
    }
  },
  "api_host": "api-****.duo.com",
  "auto_push": 1,
  "comment": "string",
  "fail_mode": "safe",
  "fingerprint": "string",
  "http_proxy": "IPAddress:port",
  "integration_key": "string",
  "is_enabled": 1,
  "max_prompts": 1,
  "owner": {
    "_links": {
      "self": {
        "href": "/api/resourcelink"
      }
    },
    "name": "svm1",
    "uuid": "02c9e252-41be-11e9-81d5-00a0986138f7"
  },
  "push_info": 1,
  "secret_key": "string",
  "status": "OK"
}
```

Response

Status: 200, Ok

Error

Status: Default, Error

Name	Type	Description
error	returned_error	

Example error

```
{
  "error": {
    "arguments": [
      {
        "code": "string",
        "message": "string"
      }
    ],
    "code": "4",
    "message": "entry doesn't exist",
    "target": "uuid"
  }
}
```

Definitions

See Definitions

href

Name	Type	Description
href	string	

_links

Name	Type	Description
next	href	
self	href	

_links

Name	Type	Description
self	href	

owner

SVM name and UUID for which the Duo profile is configured.

Name	Type	Description
_links	_links	
name	string	The name of the SVM. This field cannot be specified in a PATCH method.
uuid	string	The unique identifier of the SVM. This field cannot be specified in a PATCH method.

duo

Duo profile for the SVM or cluster-management server (Cserver).

Name	Type	Description
_links	_links	
api_host	string	The URL at which the Duo API is hosted.
auto_push	boolean	Automatically sends a push notification for authentication when using Duo.

Name	Type	Description
comment	string	Comment for the Duo profile.
fail_mode	string	Determines the behavior of the system when it cannot communicate with the Duo service.
fingerprint	string	The SHA fingerprint corresponding to the Duo secret key.
http_proxy	string	Specifies the HTTP proxy server to be used when connecting to the Duo service.
integration_key	string	The Integration Key associated with the Duo profile.
is_enabled	boolean	Indicates whether the Duo authentication feature is active or inactive.
max_prompts	integer	The maximum number of authentication attempts allowed for a user before the process is terminated.
owner	owner	SVM name and UUID for which the Duo profile is configured.
push_info	boolean	Additional information sent along with the push notification for Duo authentication.
secret_key	string	The Secret Key associated with the Duo profile.
status	string	Information on the reachability status of Duo.

error_arguments

Name	Type	Description
code	string	Argument code

Name	Type	Description
message	string	Message argument

returned_error

Name	Type	Description
arguments	array[error_arguments]	Message arguments
code	string	Error code
message	string	Error message
target	string	The target parameter that caused the error.

Copyright information

Copyright © 2024 NetApp, Inc. All Rights Reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means—graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system—without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP "AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

LIMITED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (b)(3) of the Rights in Technical Data -Noncommercial Items at DFARS 252.227-7013 (FEB 2014) and FAR 52.227-19 (DEC 2007).

Data contained herein pertains to a commercial product and/or commercial service (as defined in FAR 2.101) and is proprietary to NetApp, Inc. All NetApp technical data and computer software provided under this Agreement is commercial in nature and developed solely at private expense. The U.S. Government has a non-exclusive, non-transferrable, nonsublicensable, worldwide, limited irrevocable license to use the Data only in connection with and in support of the U.S. Government contract under which the Data was delivered. Except as provided herein, the Data may not be used, disclosed, reproduced, modified, performed, or displayed without the prior written approval of NetApp, Inc. United States Government license rights for the Department of Defense are limited to those rights identified in DFARS clause 252.227-7015(b) (FEB 2014).

Trademark information

NETAPP, the NETAPP logo, and the marks listed at <http://www.netapp.com/TM> are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.