



HP-UX

ONTAP SAN Host

NetApp
May 12, 2021

Table of Contents

HP-UX 1

 Using HP-UX 11i v3 with NetApp ONTAP 1

HP-UX

Using HP-UX 11i v3 with NetApp ONTAP

Installing the HP-UX Host Utilities

You can download the compressed file containing the Host Utilities software packages from the NetApp Support Site. After you have the file, you must uncompress it to get the software packages you need to install the Host Utilities.

Steps

1. Download a copy of the compressed file containing the Host Utilities from the [NetApp Support Site](#) to a directory on your host.
2. Go to the directory containing the download.
3. Uncompress the file.

```
gunzip netapp_hpux_host_utilities_6.0_ia_pa.depot.gz
```

4. Enter the following command to install the software:

```
swinstall -s /netapp_hpux_host_utilities_6.0_ia_pa.depot NetApp_santoolkit
```

5. Reboot the host.

SAN Toolkit

The toolkit is installed automatically when you install the NetApp Host Utilities package. This kit provides the `sanlun` utility, which helps you manage LUNs and HBAs. The `sanlun` command returns information about the LUNs mapped to your host, multipathing, and information necessary to create initiator groups.

Example

In the following example, the `sanlun lun show` command returns LUN information.

```

#sanlun lun show

controller(7mode) /                               device
host      lun
vserver(Cmode)   lun-pathname                     filename
adapter protocol size  mode
-----
-----
sanboot_unix      /vol/hpux_215_boot_en_0/goot_hpux_215_lun
/dev/rdisk/c11t0d0 fcd0   FCP      150g   C
sanboot_unix      /vol/hpux_215_boot_en_0/goot_hpux_215_lun
/dev/rdisk/c24t0d0 fcd1   FCP      150g   C
sanboot_unix      /vol/hpux_215_boot_en_0/goot_hpux_215_lun
/dev/rdisk/c21t0d0 fcd1   FCP      150g   C
sanboot_unix      /vol/hpux_215_boot_en_0/goot_hpux_215_lun
/dev/rdisk/c12t0d0 fcd0   FCP      150g   C

```

SAN Booting

Before you begin

If you decide to use SAN booting, it must be supported by your configuration. You can use the [NetApp Interoperability Matrix Tool](#) to verify that your OS, HBA, HBA firmware and the HBA boot BIOS, and ONTAP version are supported.

SAN booting is the process of setting up a SAN-attached disk (a LUN) as a boot device for a HP-UX host. The Host Utilities support SAN booting with FC and FCoE protocols in HP-UX environments.

Multipathing

Multipathing allows you to configure multiple network paths between the host and storage system. If one path fails, traffic continues on the remaining paths. For a host to have multiple paths to a LUN, multipathing must be enabled. The HP-UX Host Utilities support different multipathing solutions based on your configuration. The following is for the Native Multipathing solution.

Non-ASA Configuration

For non-ASA configuration there should be two groups of paths with different priorities. The paths with the higher priorities are Active/Optimized, meaning they are serviced by the controller where the aggregate is located. The paths with the lower priorities are active but are non-optimized because they are served from a different controller. The non-optimized paths are only used when no optimized paths are available.

Example

The following example displays the correct output for an ONTAP LUN with two Active/Optimized paths and two Active/Non-Optimized paths:

```
# sanlun lun show -p vs39:/vol/vol24_3_0/lun24_0
      ONTAP Path: vs39:/vol/vol24_3_0/lun24_0
      LUN: 37
      LUN Size: 15g
      Host Device: /dev/rdisk/disk942
      Mode: C
      Multipath Policy: A/A
      Multipath Provider: Native
```

host	vserver	/dev/dsk	host	vserver	HP A/A
path	path	filename	host	vserver	path failover
state	type	or hardware path	adapter	LIF	priority
up	primary	/dev/dsk/c39t4d5	fcd0	hpux_3	0
up	primary	/dev/dsk/c41t4d5	fcd1	hpux_4	0
up	secondary	/dev/dsk/c40t4d5	fcd0	hpux_3	1
up	secondary	/dev/dsk/c42t4d5	fcd1	hpux_4	1

All SAN Array Configuration

In All SAN Array (ASA) configurations, all paths to a given Logical Unit (LUN) are active and optimized. This means I/O can be served through all paths at the same time, thereby enabling better performance.

Example

The following example displays the correct output for an ONTAP LUN:



All SAN Array (ASA) configurations are supported beginning in ONTAP 9.8 for HP-UX 11iv3

```

# sanlun lun show -p vs39:/vol/hpux_vol_1_1/hpux_lun

                ONTAP Path: vs39:/vol/hpux_vol_1_1/hpux_lun
                  LUN: 2
                LUN Size: 30g
            Host Device: /dev/rdisk/disk25
                  Mode: C
        Multipath Provider: None

-----
host      vsserver  /dev/dsk
path      path      filename          host      vsserver
state     type       or hardware path  adapter  LIF
-----
up        primary   /dev/dsk/c4t0d2  fcd0     248_1c_hp
up        primary   /dev/dsk/c6t0d2  fcd0     246_1c_hp
up        primary   /dev/dsk/c10t0d2 fcd1     246_1d_hp
up        primary   /dev/dsk/c8t0d2  fcd1     248_1d_hp

```

Recommended Settings

Following are some recommended parameter settings for HPUX 11i v3 and NetApp ONTAP LUNs. NetApp uses the default settings for HP-UX.

Parameter	Uses Default Value
transient_secs	120
leg_mpath_enable	TRUE
max_q_depth	8
path_fail_secs	120
load_bal_policy	Round_robin
lua_enabled	TRUE
esd_secs	30

Known Problems and Limitations

NetApp Bug ID	Title	Description	Partner ID
1344935	HPUX 11.31 Host intermittently reporting path status incorrectly on ASA setup.	Path reporting issues with ASA configuration.	NA

NetApp Bug ID	Title	Description	Partner ID
1306354	HPUX LVM creation sends I/O of block size above 1MB	<p>SCSI Maximum Transfer Length of 1 MB is enforced in ONTAP All SAN Array. To restrict the Maximum Transfer Length from HP-UX hosts when connected to ONTAP All SAN Array, it is required to set the Maximum I/O size allowed by the HP-UX SCSI subsystem to 1 MB.</p> <p>Refer HP-UX vendor documentation for details.</p>	NA

Copyright Information

Copyright © 2021 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system-without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP "AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at <http://www.netapp.com/TM> are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.