



# **Activate the destination volume**

## **System Manager Classic**

NetApp  
January 21, 2022

# Table of Contents

- Activate the destination volume ..... 1
- Verify the status of the source volume ..... 1
- Break the SnapMirror relationship ..... 1
- Verify the destination volume status ..... 3

# Activate the destination volume

When the source volume is unable to serve data due to events such as data corruption, accidental deletion or an offline state, you must activate the destination volume to provide data access until you recover the data on the source volume. Activation involves stopping future SnapMirror data transfers and breaking the SnapMirror relationship.

## Verify the status of the source volume

When the source volume is unavailable, you must verify that the source volume is offline and then identify the destination volume that must be activated for providing data access.

### About this task


You must perform this task from the **source** cluster.

### Steps

1. Navigate to the **Volumes** window.
2. Select the source volume, and then verify that the source volume is offline.
3. Identify the destination volume in the SnapMirror relationship.
  - Starting with ONTAP 9.3: Double-click the source volume to view the details, and then click **PROTECTION** to identify the destination volume in the SnapMirror relationship and the name of the SVM that contains the volume.



- ONTAP 9.2 or earlier: Click the **Data Protection** tab at the bottom of the Volumes page to identify the destination volume in the SnapMirror relationship and the name of the SVM that contains the volume.



## Break the SnapMirror relationship

You must quiesce and break the SnapMirror relationship to activate the destination

volume. After quiescing, future SnapMirror data transfers are disabled.

### Before you begin

The destination volume must be mounted on the destination SVM namespace.

### About this task


You must perform this task from the **destination** cluster.

### Steps

1. Depending on the System Manager version that you are running, perform one of the following steps:
  - ONTAP 9.4 or earlier: Click **Protection > Relationships**.
  - Starting with ONTAP 9.5: Click **Protection > Volume Relationships**.
2. Select the SnapMirror relationship between the source and the destination volumes.
3. Click **Operations > Quiesce** to disable future data transfers.
4. Select the confirmation check box, and then click **Quiesce**.

The quiesce operation might take some time; you must not perform any other operation on the SnapMirror relationship until the transfer status is displayed as *Quiesced*.

5. Click **Operations > Break**.
6. Select the confirmation check box, and then click **Break**.



The SnapMirror relationship is in `Broken Off` state.

Source Sto...	Source Vol...	Destinatio...	Destinatio...	Is Healthy	Relationsh...	Transfer St...	Relationship	Lag Time	Policy Name	Policy Type
svm1	svm1_root	svm1_svm1_j...	svm2	Yes	SnapMirrored	Idle	Mirror	26 mins	DPDefault	Asynchronous...
svm1	vol1	svm1_vol1_m...	svm2	Yes	<b>Broken Off</b>	Idle	Mirror	None	DPDefault	Asynchronous...

Source Location:	svm1.vol1	Is Healthy:	Yes	Transfer Status:	Idle
Destination Location:	svm2:svm1_vol1_mirror	Relationship State:	<b>Broken Off</b>	Current Transfer Type:	None
Source Cluster:	cluster-1	Network Compression Ratio:	Not Applicable	Current Transfer Error:	None
Destination Cluster:	cluster-1			Last Transfer Error:	None
Transfer Schedule:	hourly			Last Transfer Type:	Update
Data Transfer Rate:	Unlimited			Latest Snapshot Timestamp:	02/22/2017 13:05:00
Lag Time:	None			Latest Snapshot Copy:	snapmirror-9b4das7c-e5d0-11e6-b44e-0008981a1bda_2149622820_2017-

## Verify the destination volume status

After breaking the SnapMirror relationship, you must verify that the destination volume has read/write access and that the destination volume settings match the settings of the source volume.

### About this task


You must perform this task from the **destination** cluster.

### Steps

1. Navigate to the **Volumes** window.
2. Select the destination volume from the **Volumes** list, and then verify that the destination volume type is `rw`, which indicates read/write access.
3. Verify that the volume settings such as thin provisioning, deduplication, compression, and autogrow on the destination volume match the settings of the source volume.

You can use the volume settings information that you noted after creating the SnapMirror relationship to verify the destination volume settings.

4. If the volume settings do not match, modify the settings on the destination volume as required:
  - a. Click **Edit**.
  - b. Modify the general settings, storage efficiency settings, and advanced settings for your environment, as required.
  - c. Click **Save and Close**.



- d. Verify that the columns in the **Volumes** list are updated with the appropriate values.
5. Enable Snapshot copy creation for the destination volume.
  - a. Depending on your ONTAP version, navigate to the **Configure Volume Snapshot Copies** page in one of the following ways:

Starting with ONTAP 9.3: Select the destination volume, and then click **Actions > Manage Snapshots > Configure**.

ONTAP 9.2 or earlier: Select the destination volume, and then click **Snapshot Copies > Configure**.
  - b. Select the **Enable scheduled Snapshot Copies** check box, and then click **OK**.

Configure Volume Snapshot Copies



? Snapshot Reserve (%): 5

Make Snapshot directory (.snapshot) visible

Visibility of .snapshot directory on this volume at the client mount points.

Enable scheduled Snapshot Copies

**Snapshot Policies and Schedules**

Select a Snapshot policy that has desired schedules for Snapshot copies:

Snapshot Policy: default

Schedules of Selected Snapshot Policy:

Schedul...	Retained S...	Schedule	SnapMirror Label
hourly	6	Advance cron - {Minu...	-
daily	2	Daily - Run at 0 hour 1...	daily
weekly	2	On weekdays - Sund...	weekly

Current Timezone: US/Pacific

[Tell me more about Snapshot configurations](#)

OK

Cancel

## Copyright Information

Copyright © 2022 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system- without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP "AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

## Trademark Information

NETAPP, the NETAPP logo, and the marks listed at <http://www.netapp.com/TM> are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.