



Configure protected and recovery site resources

ONTAP tools for VMware vSphere 10

NetApp
November 17, 2025

Table of Contents

- Configure protected and recovery site resources 1
 - Configure network mappings 1
 - Configure folder mappings 1
 - Configure resource mappings 2
 - Configure placeholder datastores 2
 - Configure SRA using array manager 3

Configure protected and recovery site resources

Configure network mappings

You should configure your resource mappings like VM networks, ESXi hosts, and folders on both sites to enable the mapping of each resource from the protected site to the appropriate resource at the recovery site.

You should complete the following resource configurations:

- Network mappings
- Folder mappings
- Resource mappings
- Placeholder datastores

Before you begin

You should have connected the protected and recovery sites.

Steps

1. Log in to vCenter Server and select **Site Recovery > Sites**.
2. Select your protected site and select **Manage**.
3. Select **Network Mappings > New** in the manage tab to create a new network mapping.
4. In the Create Network Mapping wizard, do the following:
 - a. Select **Automatically Prepare Mappings for Networks with Matching Names** and select **Next**.
 - b. Select the required data center objects for the protected and recovery sites and select **Add Mappings**.
 - c. Select **Next** after mappings are created successfully.
 - d. Select the object used earlier to create reverse mapping, then select **Finish**.

Result

The Network Mappings page displays the protected site resources and the recovery site resources. You can follow the same steps for other networks in your environment.

Configure folder mappings

You should map your folders on the protected site and recovery site to enable communication between them.

Before you begin

You should have connected the protected and recovery sites.

Steps

1. Log in to vCenter Server and select **Site Recovery > Sites**.
2. Select your protected site and select **Manage**.
3. Select **Folder Mappings > Folder** icon in the Manage tab to create a new folder mapping.

4. In the Create Folder Mapping wizard, perform the following:
 - a. Select **Automatically Prepare Mappings for Folders with Matching Names** and select **Next**.
 - b. Select the required data center objects for the protected and recovery sites and select **Add Mappings**.
 - c. Select **Next** after mappings are created successfully.
 - d. Select the object used earlier to create reverse mapping and then select **Finish**.

Result

The Folder Mappings page displays the protected site resources and the recovery site resources. You can follow the same steps for other networks in your environment.

Configure resource mappings

You should map your resources on the protected site and recovery site so that virtual machines are configured to fail over into one group of hosts or the other.

Before you begin

You should have connected the protected and recovery sites.



In VMware Live Site Recovery, resources can be resource pools, ESXi hosts, or vSphere clusters.

Steps

1. Log in to vCenter Server and select **Site Recovery > Sites**.
2. Select your protected site and select **Manage**.
3. Select **Resource Mappings > New** in the manage tab to create a new resource mapping.
4. In the Create Resource Mapping wizard, perform the following:
 - a. Select **Automatically Prepare Mappings for Resource with Matching Names** and select **Next**.
 - b. Select the required data center objects for the protected and recovery sites and select **Add Mappings**.
 - c. Select **Next** after mappings are created successfully.
 - d. Select the object used earlier to create reverse mapping and then select **Finish**.

Result

The Resource Mappings page displays the protected site resources and the recovery site resources. You can follow the same steps for other networks in your environment.

Configure placeholder datastores

You should configure a placeholder datastore to hold a place in the vCenter inventory at the recovery site for the protected virtual machine (VM). The placeholder datastore does not need to be large as the placeholder VMs are small and use only a few hundred or fewer kilobytes.

Before you begin

- You should have connected the protected and recovery sites.

- You should have configured your resource mappings.

Steps

1. Log in to vCenter Server and select **Site Recovery > Sites**.
2. Select your protected site and select **Manage**.
3. Select **Placeholder Datastores > New** in the manage tab to create a new placeholder datastore.
4. Select the appropriate datastore and select **OK**.



Placeholder datastores can be local or remote and should not be replicated.

5. Repeat steps 3 to 5 to configure a placeholder datastore for the recovery site.

Configure SRA using array manager

You can configure Storage Replication Adapter (SRA) by using the Array Manager wizard of VMware Live Site Recovery to enable interactions between VMware Live Site Recovery and storage virtual machines (SVMs).

Before you begin

- You should have paired the protected sites and recovery sites in VMware Live Site Recovery.
- You should have configured your onboarded storage before configuring the array manager.
- You should have configured and replicated the SnapMirror relationships between the protected sites and recovery sites.
- You should have enabled the SVM management LIFs to enable multitenancy.

SRA supports cluster-level management and SVM-level management. If you add storage at a cluster level, then you can discover and perform operations on all the SVMs in the cluster. If you add storage at an SVM level, then you can manage only that specific SVM.

Steps

1. In VMware Live Site Recovery, select **Array Managers > Add Array Manager**.
2. Enter the following information to describe the array in VMware Live Site Recovery:
 - a. Enter a name to identify the array manager in the **Display Name** field.
 - b. In the **SRA Type** field, select **NetApp Storage Replication Adapter for ONTAP**.
 - c. Enter the information to connect to the cluster or the SVM:
 - If you are connecting to a cluster, you should enter the cluster management LIF.
 - If you are connecting directly to an SVM, you should enter the IP address of the SVM management LIF.



When configuring the array manager, you should use the same connection (IP address) for the storage system that was used to onboard the storage system in ONTAP tools for VMware vSphere. For example, if the array manager configuration is SVM scoped, then the storage under ONTAP tools for VMware vSphere should be added at SVM level.

- d. If you are connecting to a cluster, enter the name of the SVM in the **SVM name** field.

You can also leave this field blank.

- e. Enter the volumes to be discovered in the **Volume include list** field.

You can enter the source volume at the protected site and the replicated destination volume at the recovery site.

For example, if you want to discover volume *src_vol1* that is in a SnapMirror relationship with volume *dst_vol1*, you should specify *src_vol1* in the protected site field and *dst_vol1* in the recovery site field.

- f. **(Optional)** Enter the volumes to be excluded from discovery in the **Volume exclude list** field.

You can enter the source volume at the protected site and the replicated destination volume at the recovery site.

For example, if you want to exclude volume *src_vol1* that is in a SnapMirror relationship with volume *dst_vol1*, you should specify *src_vol1* in the protected site field and *dst_vol1* in the recovery site field.

3. Select **Next**.

4. Verify that the array is discovered and displayed at the bottom of the Add Array Manager window and select **Finish**.

You can follow the same steps for the recovery site by using the appropriate SVM management IP addresses and credentials. On the Enable Array Pairs screen of the Add Array Manager wizard, you should verify that the correct array pair is selected, and that it shows as ready to be enabled.

Copyright information

Copyright © 2025 NetApp, Inc. All Rights Reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means—graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system—without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

LIMITED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (b)(3) of the Rights in Technical Data -Noncommercial Items at DFARS 252.227-7013 (FEB 2014) and FAR 52.227-19 (DEC 2007).

Data contained herein pertains to a commercial product and/or commercial service (as defined in FAR 2.101) and is proprietary to NetApp, Inc. All NetApp technical data and computer software provided under this Agreement is commercial in nature and developed solely at private expense. The U.S. Government has a non-exclusive, non-transferrable, nonsublicensable, worldwide, limited irrevocable license to use the Data only in connection with and in support of the U.S. Government contract under which the Data was delivered. Except as provided herein, the Data may not be used, disclosed, reproduced, modified, performed, or displayed without the prior written approval of NetApp, Inc. United States Government license rights for the Department of Defense are limited to those rights identified in DFARS clause 252.227-7015(b) (FEB 2014).

Trademark information

NETAPP, the NETAPP logo, and the marks listed at <http://www.netapp.com/TM> are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.