



Upgrade ONTAP tools for VMware vSphere

ONTAP tools for VMware vSphere 10

NetApp
November 17, 2025

This PDF was generated from <https://docs.netapp.com/us-en/ontap-tools-vmware-vsphere-103/upgrade/upgrade-ontap-tools.html> on November 17, 2025. Always check docs.netapp.com for the latest.

Table of Contents

Upgrade ONTAP tools for VMware vSphere	1
Upgrade from ONTAP tools for VMware vSphere 10.x to 10.3	1
Upgrade error codes	4

Upgrade ONTAP tools for VMware vSphere

Upgrade from ONTAP tools for VMware vSphere 10.x to 10.3

The upgrade is supported for both HA and non-HA deployments. The supported upgrade paths are:

From ONTAP tools for VMware vSphere 10.1 and 10.2 configuration	To ONTAP tools for VMware vSphere 10.3 configuration
Non-HA small	Non-HA and advanced small
Non-HA medium	Non-HA and advanced medium
Advanced small	Non-HA and advanced small
Advanced medium	Non-HA and advanced medium
HA small	HA small
HA medium	HA medium
HA large	HA large



Upgrades from ONTAP tools for VMware vSphere 10.1 and 10.2 to 10.3 are supported. Direct upgrades from ONTAP tools 10.0 to 10.3 are not supported.

Before you begin

For a non-HA upgrade, power off the ONTAP tools VM, and for an HA upgrade, power off the first node before making the following changes to the virtual machine (VM) settings.

- Add an additional 100 GB hard disk to each node, as the service data is stored locally on the VM.
- Change the CPU and memory for the powered-off VM according to the flavor of your deployment. Enable the hot plugin for CPU and RAM.

10.3 Deployment Type	CPU(Core) per node	Memory(GB) per node	Disk Space(GB) per node	Total CPU(Core)	Memory(GB)	Total Disk Space(GB)
Non-HA Small	9	18	350	9	18	350
Non-HA Medium	13	26	350	13	26	350
HA Small	9	18	350	27	54	1050
HA Medium	13	26	350	39	78	1050
HA Large	17	34	350	51	102	1050

- Power ON the VM after the changes are done and wait for the services to come to a running state.
- In case of HA deployment, make the resource changes, enable the hot plugin for CPU and RAM, and add 100 GB hard disks for the second and the third node as well. There is no need to reboot these nodes.

- If the appliance was deployed as a local path (easy deployment) with ONTAP tools 10.1 or 10.2, you need to take a quiesce snapshot before upgrading.

If you're upgrading from ONTAP tools for VMware vSphere 10.0 to 10.1, you need to complete the following steps before proceeding with the upgrade task:

Enable Diagnostics

1. From the vCenter Server, open a console to ONTAP tools.
2. Log in as the maintenance user.
3. Enter **4** to select **Support and Diagnostics**.
4. Enter **2** to select **Enable remote diagnostic access**.
5. Enter **y** to set the password of your choice.
6. Log in to the VM IP address from the terminal/putty with the user as 'diag' and the password that was set in the previous step.

Take a backup of MongoDB

Run the following commands to take a backup of MongoDB:

- `kn exec -it ntv-mongodb-0 sh` - `kn` is an alias of `kubectl -n ntv-system`.
- Run `env | grep MONGODB_ROOT_PASSWORD` command inside the pod.
- Run `exit` command to come out of the pod.
- Run `kn exec ntv-mongodb-0 --mongodump -u root -p MONGODB_ROOT_PASSWORD --archive=/tmp/mongodb-backup.gz --gzip` command to replace the `MONGO_ROOT_PASSWORD` set from the above command.
- Run `kn cp ntv-mongodb-0:/tmp/mongodb-backup.gz ./mongodb-backup.gz` command to copy the mongodb backup created using the above command from the pod to the host.

Take the quiese snapshot of all the volumes

- Run '`kn get pvc`' command and save the command output.
- Take snapshots of all the volumes one by one using one of the following methods:
 - From CLI, run the command `volume snapshot create -vserver <vserver_name> -volume <volume_name> -snapshot <snapshot_name>`
 - From the ONTAP System Manager user interface, search the volume by its name in the search bar, then open that volume by selecting on the name. Go to snapshot and add the snapshot of that volume.

Take the snapshot of ONTAP tools for VMware vSphere VMs in vCenter (3VMs in case of HA Deployment, 1 VM in case of non-HA deployment)

- In the vSphere client user interface, select the VM.
- Go to the snapshots tab and select the **Take Snapshot** button. Take a quiesced snapshot of the VM. Refer to [Take a Snapshot of a Virtual Machine](#) for details.

Before performing the upgrade, delete the completed pods from the log bundle with the prefix "generate-support-bundle-job." If support bundle generation is in progress, wait for it to complete and then delete the pod.

For any type of upgrade, you need to add an additional 100 GB hard Disk Drive (HDD). To add an HDD,

perform the following task.


1. Select the VM in single node configuration or all three VMs in HA configuration.
2. Right-click on the VM(s) and select **Add New Device > Hard Disk**
3. Add a 100 GB HDD in the **New Hard disk** field.
4. Select **Apply**

After adding the hard disk, update the VM's resources for the respective configurations and restart the primary VM.

A new HDD will be created. Dynamic storage provisioner uses this HDD to generate or replicate the volumes.

Steps

1. Upload ONTAP tools for VMware vSphere upgrade ISO to content library.
2. In the primary VM page, select **Actions > Edit Settings**. To identify the primary VM name:
 - a. Enable diag shell on any node
 - b. Run the following command: `grep sourceHost /opt/netapp/meta/ansible_vars.yaml`
3. Select the content library ISO file in the edit settings window under the **CD/DVD drive** field.
4. Select the ISO file and select **OK**. Choose the connected checkbox across the **CD/DVD drive** field.



5. From the vCenter Server, open a console to ONTAP tools.
6. Log in as the maintenance user.
7. Enter **3** to select the System Configuration menu.
8. Enter **7** to select the upgrade option.
9. When you upgrade, the following actions are performed automatically:
 - a. Certificate upgrade

b. Remote plug-in upgrade

After upgrading to ONTAP tools for VMware vSphere 10.3, you can:

- Disable the services from the manager user interface
- Move from a non-HA setup to an HA setup
- Scale up a non-HA small configuration a non-HA medium or to a HA medium or large configuration.
- In case of a non-HA upgrade, reboot the ONTAP tools VM to reflect the changes. In case of an HA upgrade, reboot the first node to reflect the changes on the node.

After you finish

After you upgrade from previous releases of ONTAP tools for VMware vSphere to 10.3, rescan the SRA adapters to verify that the details are updated on the VMware Live Site Recovery Storage Replication Adapters page.

After you upgrade successfully, delete the Trident volumes from ONTAP manually using the following procedure:



These steps are not required if the ONTAP tools for VMware vSphere 10.1 or 10.2 was in non-HA small or medium (local path) configurations.

1. From the vCenter Server, open a console to ONTAP tools.
2. Log in as the maintenance user.
3. Enter **4** to select the **Support and Diagnostics** menu.
4. Enter **1** to select the **Access diagnostics shell** option.
5. Run the following command

```
sudo python3 /home/maint/scripts/ontap_cleanup.py
```

6. Enter the ONTAP username and password

This deletes all the Trident volumes in ONTAP used in ONTAP tools for VMware vSphere 10.1/10.2.

Related information

[Migrate from ONTAP tools for VMware vSphere 9.x to 10.3](#)

Upgrade error codes

You might encounter error codes during ONTAP tools for VMware vSphere upgrade operation. The error codes are five digits long, where the first two digits represent the script that encountered the issue, and the last three digits represent the specific workflow within that script.

All error logs are recorded in the ansible-perl-errors.log file to facilitate easy tracking and resolution of issues. This log file contains the error code and the failed Ansible task.



The error codes provided on this page are for reference only. Contact the support team if error persists or if there's no resolution mentioned.

The following table lists the error codes and the corresponding file names.

Error code	Script name
00	firstboot-network-config.pl, mode deploy
01	firstboot-network-config.pl, mode upgrade
02	firstboot-inputs-validation.pl
03	firstboot-deploy-otv-ng.pl, deploy, HA
04	firstboot-deploy-otv-ng.pl, deploy, non-HA
05	firstboot-deploy-otv-ng.pl, reboot
06	firstboot-deploy-otv-ng.pl, upgrade, HA
07	firstboot-deploy-otv-ng.pl, upgrade, non-HA
08	firstboot-otv-recovery.pl
09	post-deploy-upgrade.pl

The last three digits of the error code indicate the specific workflow error within the script:

Upgrade error code	Workflow	Resolution
068	Debian packages rollback has failed	Use zero-RPO or snapshot based recovery and retry upgrade.
069	Failed restoring files	Use zero-RPO or snapshot based recovery and retry upgrade.
070	Failed deleting backup	-
071	Kubernetes cluster was not healthy	-
074	Mount ISO has failed	Check the /var/log/upgrade-run.log and retry upgrade.
075	Upgrade pre-checks has failed	Retry the upgrade.
076	Registry upgrade has failed	Use zero-RPO or snapshot based recovery and retry upgrade.
077	Registry rollback has failed	Use zero-RPO or snapshot based recovery and retry upgrade.
078	Operator upgrade has failed	Use zero-RPO or snapshot based recovery and retry upgrade.
079	Operator rollback has failed	Use zero-RPO or snapshot based recovery and retry upgrade.
080	Services upgrade has failed	Use zero-RPO or snapshot based recovery and retry upgrade.

081	Services rollback has failed	Use zero-RPO or snapshot based recovery and retry upgrade.
082	Deleting old images from container failed	Use zero-RPO or snapshot based recovery and retry upgrade.
083	Deleting backup has failed	Use zero-RPO or snapshot based recovery and retry upgrade.
084	Changing JobManager back to Production failed	<p>Follow the below steps to recover/complete the upgrade.</p> <ol style="list-style-type: none"> 1. Enable Diagnostic Shell 2. Run the command: <code>sudo perl /home/maint/scripts/post-deploy-upgrade.pl --postupgrade</code> 3. Check the logs at <code>/var/log/post-deploy-upgrade.log</code>
087	Post upgrade steps failed.	<p>Perform the following steps to recover/complete the upgrade.</p> <ol style="list-style-type: none"> 1. Enable Diagnostic Shell 2. Run <code>sudo perl /home/maint/scripts/post-deploy-upgrade.pl --postupgrade</code> command 3. Check the logs at <code>/var/log/post-deploy-upgrade.log</code>
088	Configuring log rotate for journald has failed	Check the VM network settings compatible with the host on which VM is hosted. You can try to migrate the VM to another host and restart.
089	Changing ownership of summary log rotate config file has failed	Retry the upgrade.
093	Dynamic storage provisioner upgrade has failed	Retry the upgrade.
094	Dynamic storage provisioner rollback has failed	Retry the upgrade.
095	OS upgrade failed	No recovery for OS upgrade. ONTAP tools services are upgraded and new pods will be running.
096	Install dynamic storage provisioner	Check the upgrade logs and retry upgrade.

097	Uninstalling services for upgrade has failed	Use zero RPO or snapshot based recovery and retry upgrade.
098	copying dockercred secret from ntv-system to dynamic storage provisioner namespace has failed	Check the upgrade logs and retry upgrade.
099	Failed to validate the new HDD addition	Add the new HDD to all the nodes in case of HA and to one node in case of non-HA deployment.
108	Seeding script failed	-
109	backing up persistent volume data has failed	Check the upgrade logs and retry upgrade.
110	restoring persistent volume data has failed	Use zero-RPO or snapshot based recovery and retry upgrade.
111	Updating etcd timeout parameters for RKE2 has failed	Check the upgrade logs and retry upgrade.
112	Uninstall dynamic storage provisioner has failed	-
113	Refresh resources on secondary nodes has failed	Check the upgrade logs and retry upgrade.



ONTAP tools for VMware vSphere 10.3 does not support zero RPO.

Learn more about [How to restore ONTAP tools for VMware vSphere if upgrade fails from version 10.0 to 10.1](#)

Copyright information

Copyright © 2025 NetApp, Inc. All Rights Reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means—graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system—without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

LIMITED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (b)(3) of the Rights in Technical Data -Noncommercial Items at DFARS 252.227-7013 (FEB 2014) and FAR 52.227-19 (DEC 2007).

Data contained herein pertains to a commercial product and/or commercial service (as defined in FAR 2.101) and is proprietary to NetApp, Inc. All NetApp technical data and computer software provided under this Agreement is commercial in nature and developed solely at private expense. The U.S. Government has a non-exclusive, non-transferrable, nonsublicensable, worldwide, limited irrevocable license to use the Data only in connection with and in support of the U.S. Government contract under which the Data was delivered. Except as provided herein, the Data may not be used, disclosed, reproduced, modified, performed, or displayed without the prior written approval of NetApp, Inc. United States Government license rights for the Department of Defense are limited to those rights identified in DFARS clause 252.227-7015(b) (FEB 2014).

Trademark information

NETAPP, the NETAPP logo, and the marks listed at <http://www.netapp.com/TM> are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.