



Manage SMI-S Provider advanced settings

NetApp SMI-S Provider

NetApp

February 12, 2024

This PDF was generated from <https://docs.netapp.com/us-en/smis-provider/concept-manage-smi-s-agent-advanced-settings-overview.html> on February 12, 2024. Always check docs.netapp.com for the latest.

Table of Contents

- Manage SMI-S Provider advanced settings 1
 - Overview 1
 - Specify the SMI-S Provider automatic cache refresh interval 1
 - Specify the concrete job lifetime value 1
 - Specify the ONTAPI timeout value 2
 - Specify the maximum number of threads per message service queue 2
 - Enable or disable authentication for NetApp SMI-S Provider 3
 - Enable indications in SMI-S Provider 3

Manage SMI-S Provider advanced settings

Overview

You can manage advanced settings for SMI-S Provider, such as specifying the SMI-S cache refresh interval, ONTAPI timeout, and maximum number of threads per message service queue.

Specify the SMI-S Provider automatic cache refresh interval

By default, SMI-S Provider automatically retrieves information from storage systems every five minutes (300 seconds). You can set the automatic cache refresh interval (CACHE_REFRESH_SEC environment variable) to a value from 300 through 86400 seconds (24 hours).

Before you begin

- You must already have login credentials as Administrator.
- You must already have logged in to the host system as Administrator.

About this task

If you want to manually refresh the state of the storage system at any time, you can use the `smis refresh` command.

Steps

1. Access NetApp SMI-S Provider.
2. Create a system or user environment variable named `CACHE_REFRESH_SEC` with the new refresh interval value (in seconds).

For information about creating environment variables, see your Windows documentation.

3. Restart the CIM server:

```
smis cimserver restart
```

Specify the concrete job lifetime value

SMI-S Provider tracks the progress of asynchronous operations by creating *concrete jobs*. You can increase the concrete job lifetime from the default of 60 minutes (3600 seconds) to a value through 86400 seconds (24 hours).

Before you begin

- You must already have login credentials as Administrator.
- You must already have logged in to the host system as Administrator.

Step

1. Create a system or user environment variable named `JOB_LIFETIME_SEC` with the new lifetime value (in

seconds).

For information about creating environment variables, see your Windows documentation.

Specify the ONTAPI timeout value

SMI-S Provider makes ONTAP API (ONTAPI) calls to storage systems. By default, the ONTAPI timeout is 300 seconds. You can set the timeout to a value from 60 to 300 seconds.

Before you begin

- You must already have login credentials as Administrator.
- You must already have logged in to the host system as Administrator.

Step

1. Create a system or user environment variable named `ONTAPI_TIMEOUT_SEC` with the new timeout value (in seconds).

For information about creating environment variables, see your Windows documentation.

Specify the maximum number of threads per message service queue

By default, SMI-S Provider allows 80 threads per message service queue. You can specify the maximum thread value as 1 through 5000. Increasing the maximum number of threads can impact the SMI-S Provider machine's performance, so carefully consider whether you need to increase this value.

Before you begin

- You must already have login credentials as Administrator.
- You must already have logged in to the host system as Administrator.

About this task

If your trace file shows many lines of `insufficient resources` output, you must increase the number of threads in increments of 500.

If you set the maximum number of threads to fewer than 20, using the `cimcli -n root/ontap niall` command, the provider becomes unresponsive and returns the `Insufficient threadpool` message in the trace file. If this occurs, you must increase the number of threads in increments of 500 and then restart the provider.

Steps

1. Access NetApp SMI-S Provider.
2. Create a system or user environment variable named `PEGASUS_MAX_THREADS_PER_SVC_QUEUE` with the new maximum thread value.

For information about creating environment variables, see your Windows documentation.

3. Restart the CIM server:

```
smis cimserver restart
```

Enable or disable authentication for NetApp SMI-S Provider

By default, authentication is enabled for SMI-S Provider. If authentication causes errors on your system, you can optionally disable it. If authentication has been disabled and you want to reenable it, you can do so.

Before you begin

- You must already have login credentials as Administrator.
- You must already have logged in as Administrator.
- Any client, including System Center Virtual Machine Manager (SCVMM), must be connected to the provider using cimuser and cimpassword.

Steps

1. Access NetApp SMI-S Provider.
2. Set the authentication for SMI-S Provider:

Action	Command
Enable authentication if previously disabled	<pre>cimconfig -p -s enableAuthentication=true</pre>
Disable authentication	<pre>cimconfig -p -s enableAuthentication=false</pre>

CIMOM does not use Windows authentication.

3. Restart NetApp SMI-S Provider:

```
smis cimserver restart
```

Enable indications in SMI-S Provider

Alert, FileSystem Quota, and Lifecycle indications are disabled by default. You can enable these indications by setting the environment variable `PEGASUS_DISABLE_INDICATIONS` to `false`.

Before you begin

- You must already have login credentials as Administrator.
- You must already have logged in to the host system as Administrator.

About this task

When `PEGASUS_DISABLE_INDICATIONS` is set to `false`, then Alert (`ONTAP_AlertIndication`),

FileSystem Quota (ONTAP_FSQuotaIndication), and Lifecycle indications are enabled on NetApp SMI-S Provider.

Steps

1. Access NetApp SMI-S Provider.
2. Set the PEGASUS_DISABLE_INDICATIONS environment variable to false.
3. Restart the CIM server:

```
smis cimserver restart
```

Copyright information

Copyright © 2024 NetApp, Inc. All Rights Reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means—graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system—without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

LIMITED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (b)(3) of the Rights in Technical Data -Noncommercial Items at DFARS 252.227-7013 (FEB 2014) and FAR 52.227-19 (DEC 2007).

Data contained herein pertains to a commercial product and/or commercial service (as defined in FAR 2.101) and is proprietary to NetApp, Inc. All NetApp technical data and computer software provided under this Agreement is commercial in nature and developed solely at private expense. The U.S. Government has a non-exclusive, non-transferrable, nonsublicensable, worldwide, limited irrevocable license to use the Data only in connection with and in support of the U.S. Government contract under which the Data was delivered. Except as provided herein, the Data may not be used, disclosed, reproduced, modified, performed, or displayed without the prior written approval of NetApp, Inc. United States Government license rights for the Department of Defense are limited to those rights identified in DFARS clause 252.227-7015(b) (FEB 2014).

Trademark information

NETAPP, the NETAPP logo, and the marks listed at <http://www.netapp.com/TM> are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.