



Grid nodes and services

StorageGRID

NetApp
December 03, 2025

This PDF was generated from <https://docs.netapp.com/us-en/storagegrid-118/primer/nodes-and-services.html> on December 03, 2025. Always check docs.netapp.com for the latest.

Table of Contents

Grid nodes and services	1
Grid nodes and services: Overview	1
Types of grid nodes	1
Hardware and software nodes	1
StorageGRID services	2
What is an Admin Node?	4
Differences between primary and non-primary Admin Nodes	4
Preferred sender Admin Node	5
Primary services for Admin Nodes	6
What is a Storage Node?	6
Types of Storage Nodes	6
Primary services for Storage Nodes	7
What is a Gateway Node?	11
Primary services for Gateway Nodes	11
What is an Archive Node?	12
Primary services for Archive Nodes	12

Grid nodes and services

Grid nodes and services: Overview

The basic building block of a StorageGRID system is the grid node. Nodes contain services, which are software modules that provide a set of capabilities to a grid node.

Types of grid nodes

The StorageGRID system uses four types of grid nodes:

Admin Nodes

Provide management services such as system configuration, monitoring, and logging. When you sign in to the Grid Manager, you are connecting to an Admin Node. Each grid must have one primary Admin Node and might have additional non-primary Admin Nodes for redundancy. You can connect to any Admin Node, and each Admin Node displays a similar view of the StorageGRID system. However, maintenance procedures must be performed using the primary Admin Node.

Admin Nodes can also be used to load balance S3 and Swift client traffic.

See [What is an Admin Node?](#)

Storage Nodes

Manage and store object data and metadata. Each site in your StorageGRID system must have at least three Storage Nodes.

See [What is a Storage Node?](#)

Gateway Nodes (optional)

Provide a load-balancing interface that client applications can use to connect to StorageGRID. A load balancer seamlessly directs clients to an optimal Storage Node, so that the failure of nodes or even an entire site is transparent.

See [What is a Gateway Node?](#)

Archive Nodes (deprecated)

Provide an optional interface through which object data can be archived to tape.

See [What is an Archive Node?](#)

Hardware and software nodes

StorageGRID nodes can be deployed as StorageGRID appliance nodes or as software-based nodes.

StorageGRID appliance nodes

StorageGRID hardware appliances are specially designed for use in a StorageGRID system. Some appliances can be used as Storage Nodes. Other appliances can be used as Admin Nodes or Gateway Nodes. You can combine appliance nodes with software-based nodes or deploy fully engineered, all-appliance grids that have no dependencies on external hypervisors, storage, or compute hardware.

See the following to learn about the available appliances:

- [StorageGRID Appliance Documentation](#)
- [NetApp Hardware Universe](#)

Software-based nodes

Software-based grid nodes can be deployed as VMware virtual machines or within container engines on a Linux host.

- Virtual machine (VM) in VMware vSphere: See [Install StorageGRID on VMware](#).
- Within a container engine on Red Hat Enterprise Linux: See [Install StorageGRID on Red Hat Enterprise Linux](#).
- Within a container engine on Ubuntu or Debian: See [Install StorageGRID on Ubuntu or Debian](#).

Use the [NetApp Interoperability Matrix Tool \(IMT\)](#) to determine the supported versions.

During initial installation of a new software-based Storage Node you can specify that it only be used to [store metadata](#).

StorageGRID services

The following is a complete list of StorageGRID services.

Service	Description	Location
Account Service Forwarder	Provides an interface for the Load Balancer service to query the Account Service on remote hosts and provides notifications of Load Balancer Endpoint configuration changes to the Load Balancer service.	Load Balancer service on Admin Nodes and Gateway Nodes
ADC (Administrative Domain Controller)	Maintains topology information, provides authentication services, and responds to queries from the LDR and CMN services.	At least three Storage Nodes containing the ADC service at each site
AMS (Audit Management System)	Monitors and logs all audited system events and transactions to a text log file.	Admin Nodes
ARC (Archive)	Provides the management interface with which you configure connections to external archival storage, such as the cloud through an S3 interface or tape through TSM middleware.	Archive Nodes
Cassandra Reaper	Performs automatic repairs of object metadata.	Storage Nodes
Chunk service	Manages erasure-coded data and parity fragments.	Storage Nodes
CMN (Configuration Management Node)	Manages system-wide configurations and grid tasks. Each grid has one CMN service.	Primary Admin Node

Service	Description	Location
DDS (Distributed Data Store)	Interfaces with the Cassandra database to manage object metadata.	Storage Nodes
DMV (Data Mover)	Moves data to cloud endpoints.	Storage Nodes
Dynamic IP (dynip)	Monitors the grid for dynamic IP changes and updates local configurations.	All nodes
Grafana	Used for metrics visualization in the Grid Manager.	Admin Nodes
High Availability	Manages high availability virtual IPs on nodes configured on the High Availability Groups page. This service is also known as the keepalived service.	Admin and Gateway Nodes
Identity (idnt)	Federates user identities from LDAP and Active Directory.	Storage Nodes that use the ADC service
Lambda Arbitrator	Manages S3 Select SelectObjectContent requests.	All nodes
Load Balancer (nginx-gw)	Provides load balancing of S3 and Swift traffic from clients to Storage Nodes. The Load Balancer service can be configured through the Load Balancer Endpoints configuration page. This service is also known as the nginx-gw service.	Admin and Gateway Nodes
LDR (Local Distribution Router)	Manages the storage and transfer of content within the grid.	Storage Nodes
MISCd Information Service Control Daemon	Provides an interface for querying and managing services on other nodes and for managing environmental configurations on the node such as querying the state of services running on other nodes.	All nodes
nginx	Acts as an authentication and secure communication mechanism for various grid services (such as Prometheus and Dynamic IP) to be able to talk to services on other nodes over HTTPS APIs.	All nodes
nginx-gw	Powers the Load Balancer service.	Admin and Gateway Nodes

Service	Description	Location
NMS (Network Management System)	Powers the monitoring, reporting, and configuration options that are displayed through the Grid Manager.	Admin Nodes
Persistence	Manages files on the root disk that need to persist across a reboot.	All nodes
Prometheus	Collects time series metrics from services on all nodes.	Admin Nodes
RSM (Replicated State Machine)	Ensures platform service requests are sent to their respective endpoints.	Storage Nodes that use the ADC service
SSM (Server Status Monitor)	Monitors hardware conditions and reports to the NMS service.	An instance is present on every grid node
Trace collector	Performs trace collection to gather information for use by technical support. The trace collector service uses open source Jaeger software.	Admin Nodes

What is an Admin Node?

Admin Nodes provide management services such as system configuration, monitoring, and logging. Admin Nodes can also be used to load balance S3 and Swift client traffic. Each grid must have one primary Admin Node and might have any number of non-primary Admin Nodes for redundancy.

Differences between primary and non-primary Admin Nodes

When you sign in to the Grid Manager or the Tenant Manager, you are connecting to an Admin Node. You can connect to any Admin Node, and each Admin Node displays a similar view of the StorageGRID system. However, the primary Admin Node provides more functionality than non-primary Admin Nodes. For example, most maintenance procedures must be performed from the primary Admin Nodes.

The table summarizes the capabilities of primary and non-primary Admin Nodes.

Capabilities	Primary Admin Node	Non-primary Admin Node
Includes the AMS service	Yes	Yes
Includes the CMN service	Yes	No
Includes the NMS service	Yes	Yes

Capabilities	Primary Admin Node	Non-primary Admin Node
Includes the Prometheus service	Yes	Yes
Includes the SSM service	Yes	Yes
Includes the Load Balancer and High Availability services	Yes	Yes
Supports the Management Application Program Interface (mgmt-api)	Yes	Yes
Can be used for all network-related maintenance tasks, for example IP address change and updating NTP servers	Yes	No
Can perform EC rebalance after Storage Node expansion	Yes	No
Can be used for the volume restoration procedure	Yes	Yes
Can collect log files and system data from one or more nodes	Yes	No
Sends alert notifications, AutoSupport packages, and SNMP traps and informs	Yes. Acts as the preferred sender .	Yes. Acts as a standby sender.

Preferred sender Admin Node

If your StorageGRID deployment includes multiple Admin Nodes, the primary Admin Node is the preferred sender for alert notifications, AutoSupport packages, SNMP traps and informs, and legacy alarm notifications.

Under normal system operations, only the preferred sender sends notifications. However, all other Admin Nodes monitor the preferred sender. If a problem is detected, other Admin Nodes act as *standby senders*.

Multiple notifications might sent in these cases:

- If Admin Nodes become "islanded" from each other, both the preferred sender and the standby senders will attempt to send notifications, and multiple copies of notifications might be received.
- If standby sender detects problems with the preferred sender and starts sending notifications, the preferred sender might regain its ability to send notifications. If this occurs, duplicate notifications might be sent. The standby sender will stop sending notifications when it no longer detects errors on the preferred sender.



When you test AutoSupport packages, all Admin Nodes send the test. When you test alert notifications, you must sign in to every Admin Node to verify connectivity.

Primary services for Admin Nodes

The following table shows the primary services for Admin Nodes; however, this table does not list all node services.

Service	Key function
Audit Management System (AMS)	Tracks system activity and events.
Configuration Management Node (CMN)	Manages system-wide configuration.
High Availability	Manages high availability virtual IP addresses for groups of Admin Nodes and Gateway Nodes. Note: This service is also found on Gateway Nodes.
Load Balancer	Provides load balancing of S3 and Swift traffic from clients to Storage Nodes. Note: This service is also found on Gateway Nodes.
Management Application Program Interface (mgmt-api)	Processes requests from the Grid Management API and the Tenant Management API.
Network Management System (NMS)	Provides functionality for the Grid Manager.
Prometheus	Collects and stores time-series metrics from the services on all nodes.
Server Status Monitor (SSM)	Monitors the operating system and underlying hardware.

What is a Storage Node?

Storage Nodes manage and store object data and metadata. Storage Nodes include the services and processes required to store, move, verify, and retrieve object data and metadata on disk.

Each site in your StorageGRID system must have at least three Storage Nodes.

Types of Storage Nodes

All Storage Nodes that were installed before StorageGRID 11.8 store both objects and the metadata for those objects. Starting in StorageGRID 11.8, you can choose the Storage Node type for new software-based storage nodes:

Object and metadata Storage Nodes

By default, all new Storage Nodes installed in StorageGRID 11.8 will store both objects and metadata.

Metadata-only Storage Nodes (software-based nodes only)

You can specify that a new software-based Storage Node be used to store only metadata. You can also add a metadata-only software-based Storage Node to your StorageGRID system during StorageGRID system expansion.



You can only select the Storage Node type when initially installing the software-based node or when you install the software-based node during StorageGRID system expansion. You can't change the type after the node installation is complete.

Installing a metadata-only node is typically not required. However, using a Storage Node exclusively for metadata can make sense if your grid stores a very large number of small objects. Installing dedicated metadata capacity provides a better balance between the space needed for a very large number of small objects and the space needed for the metadata for all those objects.

Software-based metadata-only node resources must match the existing Storage Nodes resources. For example:

- If the existing StorageGRID site is using SG6000 or SG6100 appliances, the software-based metadata-only nodes must meet the following minimum requirements:
 - 128 GB RAM
 - 8 core CPU
 - 8 TB SSD or equivalent storage for the Cassandra database (rangedb/0)
- If the existing StorageGRID site is using virtual Storage Nodes with 24 GB RAM, 8 core CPU, and 3 TB or 4TB of metadata storage, the software-based metadata-only nodes should use similar resources (24 GB RAM, 8 core CPU, and 4TB of metadata storage (rangedb/0)).

When adding a new StorageGRID site, the new site total metadata capacity should, at minimum, match existing StorageGRID sites and new site resources should match the Storage Nodes at existing StorageGRID sites.

When installing a grid with software-based metadata-only nodes, the grid must also contain a minimum number of nodes for object storage:

- For a single-site grid, at least two Storage Nodes are configured for objects and metadata.
- For a multi-site grid, at least one Storage Node per site are configured for objects and metadata.

Software-based Storage Nodes display a metadata-only indication for each metadata-only node on all pages that list the Storage Node type.

Primary services for Storage Nodes

The following table shows the primary services for Storage Nodes; however, this table does not list all node services.



Some services, such as the ADC service and the RSM service, typically exist only on three Storage Nodes at each site.

Service	Key function
Account (acct)	Manages tenant accounts.
Administrative Domain Controller (ADC)	<p>Maintains topology and grid-wide configuration.</p> <p>Details</p> <p>The Administrative Domain Controller (ADC) service authenticates grid nodes and their connections with each other. The ADC service is hosted on a minimum of three Storage Nodes at a site.</p> <p>The ADC service maintains topology information including the location and availability of services. When a grid node requires information from another grid node or an action to be performed by another grid node, it contacts an ADC service to find the best grid node to process its request. In addition, the ADC service retains a copy of the StorageGRID deployment's configuration bundles, allowing any grid node to retrieve current configuration information.</p> <p>To facilitate distributed and islanded operations, each ADC service synchronizes certificates, configuration bundles, and information about services and topology with the other ADC services in the StorageGRID system.</p> <p>In general, all grid nodes maintain a connection to at least one ADC service. This ensures that grid nodes are always accessing the latest information. When grid nodes connect, they cache other grid nodes' certificates, enabling systems to continue functioning with known grid nodes even when an ADC service is unavailable. New grid nodes can only establish connections by using an ADC service.</p> <p>The connection of each grid node lets the ADC service gather topology information. This grid node information includes the CPU load, available disk space (if it has storage), supported services, and the grid node's site ID. Other services ask the ADC service for topology information through topology queries. The ADC service responds to each query with the latest information received from the StorageGRID system.</p>
Cassandra	Stores and protects object metadata.
Cassandra Reaper	Performs automatic repairs of object metadata.
Chunk	Manages erasure-coded data and parity fragments.
Data Mover (dmv)	Moves data to Cloud Storage Pools.

Service	Key function
Distributed Data Store (DDS)	<p>Monitors object metadata storage.</p> <p>Details</p> <p>Each Storage Node includes the Distributed Data Store (DDS) service. This service interfaces with the Cassandra database to perform background tasks on the object metadata stored in the StorageGRID system.</p> <p>The DDS service tracks the total number of objects ingested into the StorageGRID system as well as the total number of objects ingested through each of the system's supported interfaces (S3 or Swift).</p>
Identity (idnt)	Federates user identities from LDAP and Active Directory.

Service	Key function
Local Distribution Router (LDR)	<p>Processes object storage protocol requests and manages object data on disk.</p> <p>Details</p> <p>Each Storage Node includes the Local Distribution Router (LDR) service. This service handles content transport functions, including data storage, routing, and request handling. The LDR service does most of the StorageGRID system's hard work by handling data transfer loads and data traffic functions.</p> <p>The LDR service handles the following tasks:</p> <ul style="list-style-type: none"> • Queries • Information lifecycle management (ILM) activity • Object deletion • Object data storage • Object data transfers from another LDR service (Storage Node) • Data storage management • Protocol interfaces (S3 and Swift) <p>The LDR service also maps each S3 and Swift object to its unique UUID.</p> <p>Object stores</p> <p>The underlying data storage of an LDR service is divided into a fixed number of object stores (also known as storage volumes). Each object store is a separate mount point.</p> <p>The object stores in a Storage Node are identified by a hexadecimal number from 0000 to 002F, which is known as the volume ID. Space is reserved in the first object store (volume 0) for object metadata in a Cassandra database; any remaining space on that volume is used for object data. All other object stores are used exclusively for object data, which includes replicated copies and erasure-coded fragments.</p> <p>To ensure even space usage for replicated copies, object data for a given object is stored to one object store based on available storage space. When an object store fills to capacity, the remaining object stores continue to store objects until there is no more room on the Storage Node.</p> <p>Metadata protection</p> <p>StorageGRID stores object metadata in a Cassandra database, which interfaces with the LDR service.</p> <p>To ensure redundancy and thus protection against loss, three copies of object metadata are maintained at each site. This replication is non-configurable and performed automatically. For details, see Manage object metadata storage.</p>

Service	Key function
Replicated State Machine (RSM)	Ensures that S3 platform services requests are sent to their respective endpoints.
Server Status Monitor (SSM)	Monitors the operating system and underlying hardware.

What is a Gateway Node?

Gateway Nodes provide a dedicated load-balancing interface that S3 and Swift client applications can use to connect to StorageGRID. Load balancing maximizes speed and connection capacity by distributing the workload across multiple Storage Nodes. Gateway Nodes are optional.

The StorageGRID Load Balancer service is provided on all Admin Nodes and all Gateway Nodes. It performs Transport Layer Security (TLS) termination of client requests, inspects the requests, and establishes new secure connections to the Storage Nodes. The Load Balancer service seamlessly directs clients to an optimal Storage Node, so that the failure of nodes or even an entire site is transparent.

You configure one or more load balancer endpoints to define the port and network protocol (HTTPS or HTTP) that incoming and outgoing client requests will use to access the Load Balancer services on Gateway and Admin Nodes. The load balancer endpoint also defines the client type (S3 or Swift), the binding mode, and optionally a list of allowed or blocked tenants. See [Considerations for load balancing](#).

As required, you can group the network interfaces of multiple Gateway Nodes and Admin Nodes into a high availability (HA) group. If the active interface in the HA group fails, a backup interface can manage the client application workload. See [Manage high availability \(HA\) groups](#).

Primary services for Gateway Nodes

The following table shows the primary services for Gateway Nodes; however, this table does not list all node services.

Service	Key function
High Availability	Manages high availability virtual IP addresses for groups of Admin Nodes and Gateway Nodes. Note: This service is also found on Admin Nodes.
Load Balancer	Provides Layer 7 load balancing of S3 and Swift traffic from clients to Storage Nodes. This is the recommended load balancing mechanism. Note: This service is also found on Admin Nodes.
Server Status Monitor (SSM)	Monitors the operating system and underlying hardware.

What is an Archive Node?

Support for Archive Nodes is deprecated and will be removed in a future release.

Support for Archive Nodes is deprecated and will be removed in a future release. Moving objects from an Archive Node to an external archival storage system through the S3 API has been replaced by ILM Cloud Storage Pools, which offer more functionality.



The Cloud Tiering - Simple Storage Service (S3) option is also deprecated. If you are currently using an Archive Node with this option, [migrate your objects to a Cloud Storage Pool](#) instead.

Additionally, you should remove Archive Nodes from the active ILM policies in StorageGRID 11.7 or earlier. Removing object data stored on Archive Nodes will simplify future upgrades. See [Working with ILM rules and ILM policies](#).

Primary services for Archive Nodes

The following table shows the primary services for Archive Nodes; however, this table does not list all node services.

Service	Key function
Archive (ARC)	Communicates with a Tivoli Storage Manager (TSM) external tape storage system.
Server Status Monitor (SSM)	Monitors the operating system and underlying hardware.

Copyright information

Copyright © 2025 NetApp, Inc. All Rights Reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means—graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system—without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

LIMITED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (b)(3) of the Rights in Technical Data -Noncommercial Items at DFARS 252.227-7013 (FEB 2014) and FAR 52.227-19 (DEC 2007).

Data contained herein pertains to a commercial product and/or commercial service (as defined in FAR 2.101) and is proprietary to NetApp, Inc. All NetApp technical data and computer software provided under this Agreement is commercial in nature and developed solely at private expense. The U.S. Government has a non-exclusive, non-transferrable, nonsublicensable, worldwide, limited irrevocable license to use the Data only in connection with and in support of the U.S. Government contract under which the Data was delivered. Except as provided herein, the Data may not be used, disclosed, reproduced, modified, performed, or displayed without the prior written approval of NetApp, Inc. United States Government license rights for the Department of Defense are limited to those rights identified in DFARS clause 252.227-7015(b) (FEB 2014).

Trademark information

NETAPP, the NETAPP logo, and the marks listed at <http://www.netapp.com/TM> are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.