



Use Perforce integration

Workload Factory for NetApp Console

NetApp

October 07, 2026

Table of Contents

- Use Perforce integration. 1
 - Learn about Perforce integration in Workload Factory for EDA. 1
 - What is CI/CD? 1
 - CI/CD features 1
 - Projects and workspaces in EDA 1
 - Automation with Workload Factory Codebox. 2
 - Cost 2
 - Licensing 2
 - Regions 2
 - Getting help 2
 - Manage EDA projects in Workload Factory for EDA 2
 - Create a project 2
 - View existing projects. 3
 - Edit a project 4
 - View a project's workspaces 4
 - Delete a project 4
 - Manage versions of Workload Factory for EDA projects 5
 - Create a snapshot of a project. 5
 - Create a clone of a project. 5
 - Create an EDA workspace 6
 - Integrate Workload Factory for EDA with Perforce 7

Use Perforce integration

Learn about Perforce integration in Workload Factory for EDA

Integrating Perforce with CI/CD pipelines enhances the development process by automating builds, tests, and deployments, leading to faster and more reliable software delivery.

Continuous Integration and Continuous Deployment (CI/CD) in EDA is a rapid build environment creation tool for software builders. It enables fast setup of personal development environments, saving time and enabling self-service for developers while empowering DevOps teams to retain control of the infrastructure. Using CI/CD, software developers can quickly create workspaces without needing specialized data storage or understanding of the development infrastructure.

What is CI/CD?

By using CI/CD, you can streamline the way developers manage and interact with different versions of their software. It works with Perforce Helix Core to instantly clone software versions and create workspaces for development, QA, and CI/CD.

You can easily create a project and assign a volume that represents your software environment and its artifacts. As you update your software, you can take snapshots of the volume, capturing the state of your software at that moment. You can access any software version instantly without resyncing, saving time and resources.

Using the snapshot and clone capabilities of NetApp ONTAP, you can quickly access different versions of your software, so you can develop and release updates faster. For more information about Workload Factory, refer to the [Workload Factory overview](#).

CI/CD features

- Create, edit, and remove projects. See [Manage projects](#).
- Create snapshots of defined software versions. See [Manage project versions](#).
- Create, and delete workspaces (based on clones). See [Create a workspace](#).
- Create access policies to control access to a project.
- Analyze the capacity usage of each project.
- Control clone size limits and clone retention for each project.
- Integrate with version control systems such as Perforce. See [Integrate with Perforce](#).

Projects and workspaces in EDA

You can create a project and assign a volume that represents your software environment and its artifacts. Each time that you create a new version of the software, you need resync the volume data and create a project snapshot to mark the volume state as a known version. The project source volume might get rolling updates and have multiple snapshots to mark multiple versions. You can use each snapshot immediately as an instant clone, a dedicated or shared editable repository available to developers, QA or build processes. A clone in the context of a specific software version is a workspace.

Automation with Workload Factory Codebox

Workload Factory introduces built-in automation with the *Codebox*. The Codebox offers the following automation benefits:

- **Code snippet generation:** Infrastructure-as-Code (IaC) snippets are generated during resource creation, enabling seamless integration with existing orchestration workflows.
- **Infrastructure-as-code co-pilot:** the Codebox is an Infrastructure-as-code (IaC) co-pilot that helps developers and DevOps generate code to execute any operation supported by Workload Factory.
- **Code viewer and automation catalog:** the Codebox provides a code viewer for quick analysis of automation and an automation catalog for quick future re-use.

Cost

There is no cost for using the CI/CD capability of Workload Factory.

Licensing

No special licenses are needed from NetApp to use the CI/CD capabilities of Workload Factory.

Regions

EDA is supported in all commercial regions where FSx for ONTAP is supported. [View supported Amazon regions](#).

The following AWS regions aren't supported:

- China regions
- Secret Cloud
- Top Secret Cloud

Getting help

Amazon FSx for NetApp ONTAP is an AWS first-party solution. For support, use the Support Center in your AWS Management Console to open a case. Select "FSx for ONTAP" and the category, then provide the required information.

For general questions about Workload Factory or Workload Factory applications and services, refer to [Get help for EDA for Workload Factory](#).

Manage EDA projects in Workload Factory for EDA

You can manage EDA projects to control how your code and artifacts are managed for each project in NetApp Workload Factory for EDA.

Create a project

You can create a new EDA project so that you can leverage the data protection features of your FSx for ONTAP file system for your code and artifacts.

Steps

1. Log in to the [NetApp Console](#).
2. Select the menu , **Workloads > EDA**.
3. Select **CI/CD**.
4. Select **Add project**.
5. On the Create project page, provide the following:
 - a. **Project name**: Enter a name for the project.
 - b. **Description**: Enter a description for the project.
 - c. **Filesystem**: Provide the following:
 - i. **Credentials**: Select the Amazon AWS credentials to use. EDA uses these credentials to discover FSx for ONTAP file systems that you can use with this project and to create clones and snapshots of projects.
 - ii. **Region**: Select the region that this FSx for ONTAP file system resides in.
 - iii. **FSx for ONTAP file system**: Select an FSx for ONTAP file system to use with this project.

You can only select file systems that are configured with a link. [Learn more about links](#).
 - iv. **Choose a volume**: Select a volume on which to store the project; EDA uses this volume as a software repository.

You can only select volumes that are configured as an NFS share.
 - d. **Operation policies**: Provide limits for project clones:
 - i. **Maximum retention in days**: Enter the maximum number of days that a clone should be retained. After this number of days, Workload Factory removes the clone.
 - ii. **Maximum number of clones per user or group**: Enter the maximum number of clones that can be provisioned for a user or group.
 - iii. **Maximum clone size in GiB**: Enter the maximum size in GiB of a project clone.
 - e. **Access policies**: Explicitly grant project access to specific users or groups:
 - i. **Policy enforcement scope**: Enter single IP addresses or IP address ranges to limit project access to only those IP addresses or ranges.

For example: 172.16.0.0/24
 - ii. **User or group identifiers**: Enter user or group identifiers to limit project access to only those users or groups.

For example: User1234
6. Select **Create**.

Result

The project is created, and appears in the list of projects on the Projects page.

View existing projects

You can view existing projects created in NetApp Workload Factory for EDA by following these steps.

Steps

1. Log in to the [NetApp Console](#).
2. Select the menu , **Workloads > EDA**.
3. Select **CI/CD**.
4. Select **Go to Projects page**.
5. View the existing projects listed on the Projects page.

Edit a project

You can edit the settings of a project at any time.

Steps

1. Log in to the [NetApp Console](#).
2. Select the menu , **Workloads > EDA**.
3. Select **CI/CD**.
4. Select **Go to Projects page**.
5. On the Projects page, select  for the project you want to edit, and then select **Edit**.
6. Make any needed changes to the project configuration.
7. Select **Save**.

View a project's workspaces

A clone or snapshot of a project is known as a workspace. When you create a workspace, it is retained for as long as the project's operation policy allows. You can view existing workspaces for a project by following these steps.

Steps

1. Log in to the [NetApp Console](#).
2. Select the menu , **Workloads > EDA**.
3. Select **CI/CD**.
4. Select **Go to Projects page**.
5. On the Projects page, choose a project and select **View**.
6. View the status and details of all workspaces for this project.
7. If you see alerts or warnings for a workspace, hover over the alert or warning icon to see the reason.

Delete a project

You can delete a project when it is no longer needed by following these steps.

Steps

1. Log in to the [NetApp Console](#).
- 2.

Select the menu , **Workloads > EDA**.

3. Select **CI/CD**.
4. Select **Go to Projects page**.
5. On the Projects page, select  for the project you want to delete.
6. Select **Delete**.
7. In the confirmation dialog, select **Delete**.

Result

The project is deleted, and any code or artifacts associated with the project are deleted from the volume. Snapshots and clones of the project are retained.

Manage versions of Workload Factory for EDA projects

Work with different versions of your EDA projects by creating on-demand snapshots and clones directly from Workload Factory. Snapshots and clones of a project are stored in the file system that was associated with the project when it was created. You can also manage snapshots and clones using the [Workload Factory REST API](#).

Create a snapshot of a project

You can create a snapshot of a project by following these steps.

Steps

1. Log in to the [NetApp Console](#).
2. Select the menu , **Workloads > EDA**.
3. Select **CI/CD**.
4. Select **Go to Projects page**.
5. On the Projects page, select  for the project you want to snapshot.
6. In the resulting menu, select **Create a snapshot**.
7. In the **Create snapshot** dialog, choose a name for the snapshot and select **Create**.

Create a clone of a project

Clone an EDA project from a snapshot by following these steps. When you create a clone, a new editable volume is created to contain the clone.

Steps

1. Log in to the [NetApp Console](#).
2. Select the menu , **Workloads > EDA**.
3. Select **CI/CD**.
4. Select **Go to Projects page**.
5. On the Projects page, select  for the project you want to clone.

6. In the resulting menu, select **Create a clone**.
7. In the **Create clone** dialog, do the following:
 - a. Enter a name for the clone.

The default name for the clone is the project name with a suffix of the current date and time.

- b. Select a snapshot to use as the base for the clone.
- c. Select **Create**.

Result

Workload Factory creates a new clone of the project, and the clone appears as a new project on the Projects page.

Create an EDA workspace

A workspace in NetApp Workload Factory for EDA is a Perforce representation of a project at a specific moment in time. Workspaces are created using a project snapshot as a basis. You can create new workspaces within an EDA project. You can create workspaces from the Perforce UI.

Before you begin

Ensure you have integrated EDA with the Perforce Helix Visual Client. See [Integrate EDA with Perforce](#) for more information.

Steps

1. Log in to Perforce.
2. In the Perforce menu, select **View > WF**.

The Workload Factory login screen appears within the Perforce UI.

3. Log in using one of the [console experiences](#).

4. Select the menu  and then select **EDA**.

5. Select **CI/CD**.

6. Select **Create project** and then select **Create workspace**.

7. On the Create a workspace project page, provide the following:

- a. Select a snapshot to use as a basis for the workspace.
- b. Enter a name for the workspace.
- c. Optionally, enter a user identifier to claim the workspace. This identifier should match the Perforce user ID of the developer that will use this workspace.

8. Select **Create**.

Result

The workspace is created, and appears in the list of workspaces on the Workspaces page.

Integrate Workload Factory for EDA with Perforce

Integrate EDA with the Perforce Helix Visual Client (P4V) so that developers can manage your workspaces using the Perforce CLI. This enables developers to quickly switch between projects and workspaces, saving time during development.

Steps

1. Download the [P4V integration file](#).
2. Open P4V and go to **Tools > Manage Tools > HTML tabs**.
3. Select **Import HTML tabs**.
4. Select the P4V integration XML file and select **Import**.
5. Go to **View > Workload Factory**.

Result

The NetApp Workload Factory for EDA web UI appears as an HTML tab within the P4V client.

What's next?

[Create and manage EDA projects](#).

Copyright information

Copyright © 2026 NetApp, Inc. All Rights Reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means—graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system—without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

LIMITED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (b)(3) of the Rights in Technical Data -Noncommercial Items at DFARS 252.227-7013 (FEB 2014) and FAR 52.227-19 (DEC 2007).

Data contained herein pertains to a commercial product and/or commercial service (as defined in FAR 2.101) and is proprietary to NetApp, Inc. All NetApp technical data and computer software provided under this Agreement is commercial in nature and developed solely at private expense. The U.S. Government has a non-exclusive, non-transferrable, nonsublicensable, worldwide, limited irrevocable license to use the Data only in connection with and in support of the U.S. Government contract under which the Data was delivered. Except as provided herein, the Data may not be used, disclosed, reproduced, modified, performed, or displayed without the prior written approval of NetApp, Inc. United States Government license rights for the Department of Defense are limited to those rights identified in DFARS clause 252.227-7015(b) (FEB 2014).

Trademark information

NETAPP, the NETAPP logo, and the marks listed at <http://www.netapp.com/TM> are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.