



Managing your account

Cloud Manager

Ben Cammett, Tom Onacki
April 19, 2021

Table of Contents

- Managing your account 1
 - Managing your account with the Tenancy API 1
 - Creating and managing users 1
 - Creating and managing service accounts 5
 - Managing workspaces 8
 - Managing a Connector's workspaces 9
 - Managing subscriptions 9
 - Changing your account name 10
 - Allowing private previews 10
 - Allowing third-party services 10
 - Disabling the SaaS platform 10

Managing your account

After you perform initial setup, you can administer your account settings later by managing users, service accounts, workspaces, Connectors, and subscriptions.

[Learn more about how Cloud Central accounts work.](#)

Managing your account with the Tenancy API

If you want to manage your account settings by sending API requests, then you'll need to use the *Tenancy* API. This API is different than the Cloud Manager API, which you use to create and manage working environments.

[View endpoints for the Tenancy API.](#)

Creating and managing users


The user's in your account can access the manage the resources in your account's workspaces.

Adding users


Associate Cloud Central users with the Cloud Central account so those users can create and manage working environments in Cloud Manager.

Steps


1. If the user hasn't already done so, ask the user to go to [NetApp Cloud Central](#) and sign up.
2. From the top of Cloud Manager, click the **Account** drop-down.



3. Click **Manage Account** next to the currently selected account.



4. From the Users tab, click **Associate User**.
5. Enter the user's email address and select a role for the user:
 - **Account Admin**: Can perform any action in Cloud Manager.
 - **Workspace Admin**: Can create and manage resources in assigned workspaces.
 - **Compliance Viewer**: Can only view compliance information and generate reports for workspaces that they have permission to access.
6. If you selected Workspace Admin or Compliance Viewer, select one or more workspaces to associate with that user.



Associate User

To add a user to your NetApp Cloud Account, that user must already have signed up at [NetApp Cloud Central](#). Enter the email address that they used when signing up with Cloud Central.

User's Email

Role

Associate User to Workspaces

7. Click **Associate User**.

Result


The user should receive an email from NetApp Cloud Central titled "Account Association." The email includes the information needed to access Cloud Manager.

Removing users


Disassociating a user makes it so they can no longer access the resources in a Cloud Central account.

Steps

1. From the top of Cloud Manager, click the **Account** drop-down and click **Manage Account**.



2. From the Users tab, click the action menu in the row that corresponds to the user.



3. Click **Disassociate User** and click **Disassociate** to confirm.

Result


The user can no longer access the resources in this Cloud Central account.

Managing a Workspace Admin's workspaces


You can associate and disassociate Workspace Admins with workspaces at any time. Associating the user enables them to create and view the working environments in that workspace.

Steps

1. From the top of Cloud Manager, click the **Account** drop-down and click **Manage Account**.



2. From the Users tab, click the action menu in the row that corresponds to the user.



3. Click **Manage Workspaces**.

4. Select the workspaces to associate with the user and click **Apply**.

Result

The user can now access those workspaces from Cloud Manager, as long as the Connector was also associated with the workspaces.

Creating and managing service accounts

A service account acts as a "user" that can make authorized API calls to Cloud Manager for automation purposes. This makes it easier to manage automation because you don't need to build automation scripts based on a real person's user account who can leave the company at any time. And if you're using federation, you can create a token without generating a refresh token from the cloud.

You give permissions to a service account by assigning it a role, just like any other Cloud Manager user. You can also associate the service account with specific workspaces in order to control the working environments (resources) that the service can access.


When you create the service account, Cloud Manager enables you to copy or download a client ID and client secret for the service account. This key pair is used for authentication with Cloud Manager.

Creating a service account


Create as many service accounts as you need to manage the resources in your working environments.

Steps

1. From the top of Cloud Manager, click the **Account** drop-down.



2. Click **Manage Account** next to the currently selected account.



3. From the Users tab, click **Create Service Account**.
4. Enter a name and select a role. If you chose a role other than Account Admin, choose the workspace to associate with this service account.
5. Click **Create**.
6. Copy or download the client ID and client secret.

The client secret is visible only once and is not stored anywhere by Cloud Manager. Copy or download the secret and store it safely.
7. Click **Close**.

Obtaining a bearer token for a service account

In order to make API calls to the [Tenancy API](#), you'll need to obtain a bearer token for a service account.


```
curl --location --request POST 'https://netapp-cloud-account.auth0.com/oauth/token' \
--header 'Content-Type: application/json' \
--data-raw '{
  "grant_type": "client_credentials",
  "client_secret": "<client secret>",
  "audience": "https://api.cloud.netapp.com",
  "client_id": "<client id>"
}'
```

Copying the client ID

You can copy a service account's client ID at any time.

Steps

1. From the Users tab, click the action menu in the row that corresponds to the service account.




2. Click **Client ID**.
3. The ID is copied to your clipboard.

Recreating keys

Recreating the key will delete the existing key for this service account and then create a new key. You won't be able to use the previous key.

Steps

1. From the Users tab, click the action menu in the row that corresponds to the service account.



2. Click **Recreate Key**.
3. Click **Recreate** to confirm.
4. Copy or download the client ID and client secret.

The client secret is visible only once and is not stored anywhere by Cloud Manager. Copy or download the secret and store it safely.


5. Click **Close**.

Deleting a service account

Delete a service account if you no longer need to use it.

Steps

1. From the Users tab, click the action menu in the row that corresponds to the service account.



2. Click **Delete**.
3. Click **Delete** again to confirm.

Managing workspaces

Manage your workspaces by creating, renaming, and deleting them. Note that you can't delete a workspace if it contains any resources. It must be empty.

Steps

1. From the top of Cloud Manager, click the **Account** drop-down and click **Manage Account**.
2. Click **Workspaces**.
3. Choose one of the following options:
 - Click **Add New Workspace** to create a new workspace.

- Click **Rename** to rename the workspace.
- Click **Delete** to delete the workspace.

Managing a Connector's workspaces

You need to associate the Connector with workspaces so Workspace Admins can access those workspaces from Cloud Manager.

If you only have Account Admins, then associating the Connector with workspaces isn't required. Account Admins have the ability to access all workspaces in Cloud Manager by default.

[Learn more about users, workspaces, and Connectors.](#)

Steps

1. From the top of Cloud Manager, click the **Account** drop-down and click **Manage Account**.
2. Click **Connector**.
3. Click **Manage Workspaces** for the Connector that you want to associate.
4. Select the workspaces to associate with the Connector and click **Apply**.

Managing subscriptions

After you subscribe from a cloud provider's marketplace, each subscription is available from the Account Settings widget. You have the option to rename a subscription and to disassociate the subscription from one or more accounts.

For example, let's say that you have two accounts and each is billed through separate subscriptions. You might disassociate a subscription from one of the accounts so the users in that account don't accidentally choose the wrong subscription when creating a Cloud Volume ONTAP working environment.


[Learn more about subscriptions.](#)

Steps

1. From the top of Cloud Manager, click the **Account** drop-down and click **Manage Account**.
2. Click **Subscriptions**.

You'll only see the subscriptions that are associated with the account that you're currently viewing.

3. Click the action menu in the row that corresponds to the subscription that you want to manage.



Name	Service	Cloud Provider	Status
QA Subscription	test-service	aws	Unsubscribed
metering service subscription QA !!!!	cloud-volumes-ontap	aws	Subscribed

The screenshot shows a table with two rows of subscription data. The second row is highlighted, and an action menu is open over it, showing options for 'Rename Subscription' and 'Manage Accounts'. The table has a blue header and a search icon in the top right corner.

4. Choose to rename the subscription or to manage the accounts that are associated with the subscription.

Changing your account name

Change your account name at any time to change it to something meaningful for you.

Steps

1. From the top of Cloud Manager, click the **Account** drop-down and click **Manage Account**.
2. In the **Overview** tab, click the edit icon next to the account name.
3. Type a new account name and click **Save**.

Allowing private previews

Allow private previews in your account to get access to new NetApp cloud services that are made available as a preview in Cloud Manager.

Services in private preview are not guaranteed to behave as expected and might sustain outages and be missing functionality.

Steps

1. From the top of Cloud Manager, click the **Account** drop-down and click **Manage Account**.
2. In the **Overview** tab, enable the **Allow Private Preview** setting.

Allowing third-party services

Allow third-party services in your account to get access to third-party services that are available in Cloud Manager. Third-party services are cloud services similar to the services that NetApp offers, but they're managed and supported by third-party companies.

Steps

1. From the top of Cloud Manager, click the **Account** drop-down and click **Manage Account**.
2. In the **Overview** tab, enable the **Allow Third Party Services** setting.

Disabling the SaaS platform

We don't recommend disabling the SaaS platform unless you need to in order to comply with your company's security policies. Disabling the SaaS platform limits your ability to use NetApp's integrated cloud services.

The following services aren't available from Cloud Manager if you disable the SaaS platform:

- Cloud Compliance
- Kubernetes
- Cloud Tiering
- Global File Cache

If you do disable the SaaS platform, you'll need to perform all tasks from [the local user interface that is available on a Connector](#).



This is an irreversible action that will prevent you from using the Cloud Manager SaaS platform. You'll need to perform actions from the local Connector. You won't have the ability to use many of NetApp's integrated cloud services, and re-enabling the SaaS platform will require the help of NetApp support.

Steps

1. From the top of Cloud Manager, click the **Account** drop-down and click **Manage Account**.
2. In the Overview tab, toggle the option to disable use of the SaaS platform.

Copyright Information

Copyright © 2021 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system-without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP "AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at <http://www.netapp.com/TM> are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.