



Setting up workspaces and users in the Cloud Central account

Cloud Manager

Ben Cammett, Tom Onacki
September 02, 2021

This PDF was generated from https://docs.netapp.com/us-en/occm/task_setting_up_cloud_central_accounts.html on October 26, 2021. Always check docs.netapp.com for the latest.

Table of Contents

- Setting up workspaces and users in the Cloud Central account 1
 - Adding workspaces 1
 - Adding users 2
 - Associating Workspace Admins with workspaces 3
 - Associating Connectors with workspaces 4
 - What's next? 5

Setting up workspaces and users in the Cloud Central account

When you log in to Cloud Manager for the first time, you're prompted to create a *NetApp Cloud Central account*. This account provides multi-tenancy and enables you to organize users and resources in isolated *workspaces*.

[Learn more about how Cloud Central accounts work.](#)


Set up your Cloud Central account so users can access Cloud Manager and access the working environments in a workspace. Just add a single user or add multiple users and workspaces.

Adding workspaces


In Cloud Manager, workspaces enable you to isolate a set of working environments from other working environments and from other users. For example, you can create two workspaces and associate separate users with each workspace.

Steps

1. From the top of [Cloud Manager](#), click the **Account** drop-down.



2. Click **Manage Account** next to the currently selected account.



3. Click **Workspaces**.
4. Click **Add New Workspace**.

5. Enter a name for the workspace and click **Add**.

After you finish


If a Workspace Admin needs access to this workspace, then you'll need to associate the user. You'll also need to associate Connectors with the workspace so Workspace Admins can use those Connectors.

Adding users


Associate Cloud Central users with the Cloud Central account so those users can create and manage working environments in Cloud Manager.

Steps

1. If the user hasn't already done so, ask the user to go to [NetApp Cloud Central](#) and sign up.
2. From the top of [Cloud Manager](#), click the **Account** drop-down and click **Manage Account**.



3. From the Members tab, click **Associate User**.
4. Enter the user's email address and select a role for the user:
 - **Account Admin**: Can perform any action in Cloud Manager.
 - **Workspace Admin**: Can create and manage resources in assigned workspaces.
 - **Compliance Viewer**: Can only view Cloud Data Sense governance and compliance information and generate reports for workspaces that they have permission to access.
 - **SnapCenter Admin**: Can use the SnapCenter Service to create application consistent backups and restore data using those backups. This service is currently in Beta.
5. If you selected an account other than Account Admin, select one or more workspaces to associate with that user.



Associate User

To add a user to your NetApp Cloud Account, that user must already have signed up at [NetApp Cloud Central](#). Enter the email address that they used when signing up with Cloud Central.

User's Email

Role

Associate User to Workspaces

6. Click **Associate**.

Result


The user should receive an email from NetApp Cloud Central titled "Account Association." The email includes the information needed to access Cloud Manager.

Associating Workspace Admins with workspaces


You can associate Workspace Admins with additional workspaces at any time. Associating the user enables them to create and view the working environments in that workspace.

Steps

1. From the top of Cloud Manager, click the **Account** drop-down and click **Manage Account**.



2. From the Members tab, click the action menu in the row that corresponds to the user.



3. Click **Manage Workspaces**.
4. Select one or more workspaces and click **Apply**.

Result

The user can now access those workspaces from Cloud Manager, as long as the Connector was also associated with the workspaces.

Associating Connectors with workspaces


You need to associate a Connector with workspaces so Workspace Admins can use those Connectors to create Cloud Volumes ONTAP systems.

If you only have Account Admins, then associating the Connector with workspaces isn't required. Account Admins have the ability to access all workspaces in Cloud Manager by default.

[Learn more about users, workspaces, and Connectors.](#)

Steps

1. From the top of Cloud Manager, click the **Account** drop-down and click **Manage Account**.



2. Click **Connector**.
3. Click **Manage Workspaces** for the Connector that you want to associate.
4. Select one or more workspaces and click **Apply**.

Result

Workspace Admins can now use those Connectors to create Cloud Volumes ONTAP systems.

What's next?

Now that you've set up your account, you can manage it any time by removing users, managing workspaces, Connectors, and subscriptions. [Learn more](#).

Copyright Information

Copyright © 2021 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system-without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP "AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at <http://www.netapp.com/TM> are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.