



# **snaplock compliance-clock commands**

ONTAP 9.10.1 commands

NetApp  
September 27, 2022

# Table of Contents

- snaplock compliance-clock commands ..... 1
  - snaplock compliance-clock initialize ..... 1
  - snaplock compliance-clock show ..... 1
  - snaplock compliance-clock ntp modify ..... 2
  - snaplock compliance-clock ntp show ..... 3

# snaplock compliance-clock commands

## snaplock compliance-clock initialize

Initializes the node ComplianceClock

**Availability:** This command is available to *cluster* administrators at the *admin* privilege level.

### Description

`snaplock compliance-clock initialize` command is used to initialize System ComplianceClock from the system clock. System ComplianceClock can be initialized only once by the user. Once initialized, user cannot make any changes to the System ComplianceClock. Hence, user should ensure that system clock is correct before initializing the System ComplianceClock.

### Parameters

**-node {<nodename>|local} - Node**

Specifies the name of the node on which System ComplianceClock needs to be initialized.

**[-force <true>] - Forces Initialization**

If you use this paramter, it will suppress the warning message during `snaplock compliance-clock initialize` operation.

### Examples

```
cluster-1::> snaplock compliance-clock initialize -node nodel
```

```
Warning: You are about to initialize the secure ComplianceClock of the  
node
```

```
    nodel to the current value of the node's system clock. This  
    procedure can be performed only once on a given node, so you  
should
```

```
    ensure that the system time is set correctly before proceeding.
```

```
    The current node's system clock is: Wed Nov 26 16:18:30 IST 2014
```

```
Do you want to continue? {y|n}: y
```

```
cluster-1::>
```

## snaplock compliance-clock show

Displays the node ComplianceClock

**Availability:** This command is available to *cluster* and *Vserver* administrators at the *admin* privilege level.

## Description

The `snaplock compliance-clock show` command will display System ComplianceClock of the nodes in the cluster. It will display the following information:

- Node name
- ComplianceClock Time

## Parameters

**{ [-fields <fieldname>,...]**

If you specify the `-fields <fieldname>, ...` parameter, the command output also includes the specified field or fields. You can use `'-fields ?'` to display the fields to specify.

**| [-instance ] }**

If you specify the `-instance` parameter, the command displays detailed information about all fields.

**[-node {<nodename>|local}] - Node**

If this parameter is specified, the command will display ComplianceClock for that particular node only.

**[-time <text>] - ComplianceClock Time of the Node**

If this parameter is specified, the command will display nodes having the same `-time` value.

## Examples

```
cluster1::> snaplock compliance-clock show
Node                               ComplianceClock Time
-----
node1                               Mon Jan 12 11:34:15 IST 2015 +05:30
node2                               Mon Jan 12 11:34:10 IST 2015 +05:30
2 entries were displayed.
```

```
cluster1::> snaplock compliance-clock show -node node1
Node                               ComplianceClock Time
-----
node1                               Mon Jan 12 11:34:45 IST 2015 +05:30
```

## snaplock compliance-clock ntp modify

Modify SnapLock ComplianceClock synchronization setting

**Availability:** This command is available to *cluster* administrators at the *advanced* privilege level.

## Description

The `snaplock compliance-clock ntp modify` command modifies the option to enable or disable the SnapLock ComplianceClock synchronization with the system time. The ComplianceClock is synchronized only when an NTP server has been configured so that the system time follows the NTP time and the skew between the ComplianceClock time and the system time is greater than 1 day.

## Parameters

**`[-is-sync-enabled {true|false}]` - Enable ComplianceClock sync to NTP system time**

Specifies whether synchronization should be enabled or not. This is a cluster wide option.

## Examples

```
cluster1::> snaplock compliance-clock ntp modify -is-sync-enabled true
```

## snaplock compliance-clock ntp show

Display SnapLock ComplianceClock synchronization setting

**Availability:** This command is available to *cluster* administrators at the *advanced* privilege level.

## Description

The `snaplock compliance-clock ntp show` command will display ComplianceClock synchronization setting. It will display the following information:

- `is-sync-enabled` - Displays if the option to synchronize the ComplianceClock with system time has been enabled or not.

## Examples

```
cluster1::> snaplock compliance-clock ntp show
Enable clock sync to NTP system time: true
```

## Copyright Information

Copyright © 2022 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system-without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP "AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

## Trademark Information

NETAPP, the NETAPP logo, and the marks listed at <http://www.netapp.com/TM> are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.