



cft events

ONTAP EMS reference

NetApp
November 20, 2025

Table of Contents

| | |
|-------------------------------|---|
| cft events | 1 |
| cft.trans events | 1 |
| cft.trans.aggr.end | 1 |
| cft.trans.aggr.failed | 1 |
| cft.trans.aggr.start | 1 |
| cft.trans.commit.end | 2 |
| cft.trans.commit.failed | 2 |
| cft.trans.commit.start | 3 |
| cft.trans.revert.end | 3 |
| cft.trans.revert.failed | 3 |
| cft.trans.revert.start | 4 |
| cft.trans.vol.end | 4 |
| cft.trans.vol.failed | 5 |
| cft.trans.vol.start | 5 |

cft events

cft.trans events

cft.trans.aggr.end

Severity

INFORMATIONAL

Description

This message occurs when Copy-Free Transition of a 7-Mode aggregate to clustered Data ONTAP® is successful.

Corrective Action

(None).

Syslog Message

Copy-Free Transition session:%s on node "%s" for aggregate UUID:%s using Snapshot:%s completed successfully.

Parameters

sessionId (STRING): Unique session identification number.

node (STRING): Name of the target controller.

aggrUuid (STRING): UUID of the aggregate.

snapshot (STRING): Aggregate Snapshot® copy name.

cft.trans.aggr.failed

Severity

ALERT

Description

This message occurs when Copy-Free Transition of a 7-Mode aggregate to clustered Data ONTAP® fails.

Corrective Action

Contact technical support for assistance.

Syslog Message

Copy-Free Transition session:%s on node "%s" for aggregate UUID:%s using Snapshot:%s failed.

Parameters

sessionId (STRING): Unique session identification number.

node (STRING): Name of the target controller.

aggrUuid (STRING): UUID of the aggregate.

snapshot (STRING): Aggregate Snapshot® copy name.

cft.trans.aggr.start

Severity

INFORMATIONAL

Description

This message occurs when Copy-Free Transition of a 7-Mode aggregate to clustered Data ONTAP® starts.

Corrective Action

(None).

Syslog Message

Copy-Free Transition session:%s on node "%s" for aggregate UUID:%s using Snapshot:%s started.

Parameters

sessionId (STRING): Unique session identification number.

node (STRING): Name of the target controller.

aggrUuid (STRING): UUID of the aggregate.

snapshot (STRING): Aggregate Snapshot® copy name.

cft.trans.commit.end**Severity**

INFORMATIONAL

Description

This message occurs when Copy-Free Transition commit on a transitioned aggregate in clustered Data ONTAP® is successful.

Corrective Action

(None).

Syslog Message

Copy-Free Transition session:%s commit phase for aggregate UUID:%s" completed successfully.

Parameters

sessionId (STRING): Unique session identification number.

aggrUuid (STRING): UUID of the aggregate.

cft.trans.commit.failed**Severity**

EMERGENCY

Description

This message occurs when Copy-Free Transition commit of a transitioned aggregate in clustered Data ONTAP® fails.

Corrective Action

Contact technical support for assistance.

Syslog Message

Copy-Free Transition session:%s commit phase for aggregate UUID:%s " failed.

Parameters

sessionId (STRING): Unique session identification number.

aggrUuid (STRING): UUID of the aggregate.

cft.trans.commit.start

Severity

INFORMATIONAL

Description

This message occurs when Copy-Free Transition commit of a transitioned aggregate in clustered Data ONTAP® starts.

Corrective Action

(None).

Syslog Message

Copy-Free Transition session:%s commit phase for aggregate UUID:%s" started.

Parameters

sessionId (STRING): Unique session identification number.

aggrUuid (STRING): UUID of the aggregate.

cft.trans.revert.end

Severity

INFORMATIONAL

Description

This message occurs when a Copy-Free Transition revert operation for an aggregate is successfully completed.

Corrective Action

(None).

Syslog Message

Copy-Free Transition session:%s revert to Data ONTAP 7-Mode version:%s for aggregate UUID:%s on node "%s" completed successfully.

Parameters

sessionId (STRING): Unique session identification number.

kernelVersion (STRING): Kernel Version of 7-Mode needed for the revert operation.

aggrUuid (STRING): UUID of the aggregate.

node (STRING): Name of the target controller.

cft.trans.revert.failed

Severity

ALERT

Description

This message occurs when a Copy-Free Transition revert operation of a transitioned aggregate in clustered Data ONTAP® fails.

Corrective Action

Contact technical support for assistance.

Syslog Message

Copy-Free Transition session:%s revert to Data ONTAP 7-Mode version:%s for aggregate UUID:%s on node "%s" failed.

Parameters

sessionId (STRING): Unique session identification number.

kernelVersion (STRING): Kernel version of 7-Mode needed for the revert operation.

aggrUuid (STRING): UUID of the aggregate.

node (STRING): Name of the target controller.

cft.trans.revert.start

Severity

INFORMATIONAL

Description

This message occurs when a Copy-Free Transition revert for an aggregate starts.

Corrective Action

(None).

Syslog Message

Copy-Free Transition session:%s revert to Data ONTAP 7-Mode version:%s for aggregate UUID:%s on node "%s" started.

Parameters

sessionId (STRING): Unique session identification number.

kernelVersion (STRING): Kernel version of 7-Mode needed for the revert operation.

aggrUuid (STRING): UUID of the aggregate.

node (STRING): Name of the target controller.

cft.trans.vol.end

Severity

INFORMATIONAL

Description

This message occurs when Copy-Free Transition's volume transition job, responsible for transitioning 7-Mode volumes to clustered Data ONTAP®, is complete. It provides the details of the number of successful transitions and the number of failures, with references for rectification and corrective measures.

Corrective Action

(None).

Syslog Message

Copy-Free Transition session:%s volume transition job for %d volumes is complete. %d volumes transitioned successfully and %d volumes failed.

Parameters

sessionId (STRING): Unique session identification number.

numVolumes (INT): Number of volumes transitioning.

successTransVols (INT): Number of volumes successfully transitioned.

failedTransVols (INT): Number of volumes that failed to transition.

cft.trans.vol.failed

Severity

ERROR

Description

This message occurs when Copy-Free Transition of a 7-Mode volume to clustered Data ONTAP® fails.

Corrective Action

Contact technical support for assistance.

Syslog Message

Copy-Free Transition session:%s for volume UUID:%s contained in aggregate UUID:%s and associated with Vserver "%s" failed.

Parameters

sessionId (STRING): Unique session identification number.

volUuid (STRING): Volume unique identifier.

aggrUuid (STRING): UUID of the containing aggregate.

vserver (STRING): Vserver associated with the volume.

cft.trans.vol.start

Severity

INFORMATIONAL

Description

This message occurs when Copy-Free Transition's volume transition job, responsible for transitioning 7-Mode volumes to clustered Data ONTAP®, starts.

Corrective Action

(None).

Syslog Message

Copy-Free Transition session:%s volume transition job for %d volumes started.

Parameters

sessionId (STRING): Unique session identification number.

numVolumes (INT): Number of volumes transitioning.

Copyright information

Copyright © 2025 NetApp, Inc. All Rights Reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means—graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system—with prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

LIMITED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (b)(3) of the Rights in Technical Data -Noncommercial Items at DFARS 252.227-7013 (FEB 2014) and FAR 52.227-19 (DEC 2007).

Data contained herein pertains to a commercial product and/or commercial service (as defined in FAR 2.101) and is proprietary to NetApp, Inc. All NetApp technical data and computer software provided under this Agreement is commercial in nature and developed solely at private expense. The U.S. Government has a non-exclusive, non-transferrable, nonsublicensable, worldwide, limited irrevocable license to use the Data only in connection with and in support of the U.S. Government contract under which the Data was delivered. Except as provided herein, the Data may not be used, disclosed, reproduced, modified, performed, or displayed without the prior written approval of NetApp, Inc. United States Government license rights for the Department of Defense are limited to those rights identified in DFARS clause 252.227-7015(b) (FEB 2014).

Trademark information

NETAPP, the NETAPP logo, and the marks listed at <http://www.netapp.com/TM> are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.