



Preparing data protection features for transition

ONTAP 7-Mode Transition

NetApp
October 09, 2025

This PDF was generated from https://docs.netapp.com/us-en/ontap-7mode-transition/copy-free/task_preparing_cluster_for_transitioning_volume_snapmirror_relationships.html on October 09, 2025. Always check docs.netapp.com for the latest.

Table of Contents

Preparing data protection features for transition	1
Preparing the cluster for transitioning volume SnapMirror relationships	1
Data protection transition: supported and unsupported configurations	1
Supported configurations	1
Unsupported configurations	2

Preparing data protection features for transition

You must perform some manual steps for transitioning 7-Mode SnapMirror relationships. You must also be aware of the data protection relationships that are supported and unsupported for transition.

Preparing the cluster for transitioning volume SnapMirror relationships

For transitioning 7-Mode volume SnapMirror relationships, you must add the SnapMirror license to the source and destination clusters. You must also create a cluster peer relationship between the clusters to which the primary and secondary volumes of the SnapMirror relationships are transitioned and create the SnapMirror schedules.

You must have recorded the SnapMirror schedules defined in the `/etc/snapmirror.conf` file of the 7-Mode secondary system.

Steps

1. Add the SnapMirror license on both the source and destination clusters:

```
system license add license_code
```

2. From each cluster, create the cluster peer relationship.

[Cluster and SVM peering express configuration](#)

3. Create schedules on the secondary SVMs that match the schedules in the 7-Mode secondary system:

```
job schedule cron create
```

Related information

[ONTAP 9 commands](#)

Data protection transition: supported and unsupported configurations

You can transition a volume that is part of a SnapMirror relationship. However, some data protection and disaster recovery configurations are not supported for transition and therefore you have to perform some manual steps for transitioning these configurations.

Supported configurations

You can transition volume SnapMirror relationships by using the 7-Mode Transition Tool. You can perform a copy-free transition of primary and secondary HA pairs. You must then manually set up the volume SnapMirror relationships after transition.

[Transitioning a SnapMirror relationship](#)

Unsupported configurations

- SnapVault relationships

Volumes that are the source of a SnapVault relationship can be migrated; however, the SnapVault relationship is not transitioned. A volume that is the destination of a SnapVault relationship can be migrated only after the SnapVault backups are stopped.

[NetApp Technical Report 4052: Successfully Transitioning to Clustered Data ONTAP \(Data ONTAP 8.2.x and 8.3\)](#)

- Qtree SnapMirror relationships

Volumes with qtrees that are the source of a qtree SnapMirror relationship can be transitioned, but the qtree SnapMirror relationship is not transitioned. A volume with a qtree that is the destination of a qtree SnapMirror relationship can be migrated only after the qtree SnapMirror relationship is broken.

- Disaster recovery vFiler unit

Volumes that are the source of a disaster recovery vFiler unit can be migrated; however, the disaster recovery vFiler unit is not transitioned. A volume that is the destination of a disaster recovery vFiler unit can be migrated only after the disaster recovery relationship is deleted.

- NDMP configuration

After the transition is complete, you must manually set up backup policies for the transitioned volumes in ONTAP.

[Data protection using tape backup](#)

- Synchronous SnapMirror relationships

This feature is not supported in ONTAP; however, the volumes that are part of the relationship can be transitioned.

Related information

[Customizing the transition of 7-Mode configurations](#)

Copyright information

Copyright © 2025 NetApp, Inc. All Rights Reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means—graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system—without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

LIMITED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (b)(3) of the Rights in Technical Data -Noncommercial Items at DFARS 252.227-7013 (FEB 2014) and FAR 52.227-19 (DEC 2007).

Data contained herein pertains to a commercial product and/or commercial service (as defined in FAR 2.101) and is proprietary to NetApp, Inc. All NetApp technical data and computer software provided under this Agreement is commercial in nature and developed solely at private expense. The U.S. Government has a non-exclusive, non-transferrable, nonsublicensable, worldwide, limited irrevocable license to use the Data only in connection with and in support of the U.S. Government contract under which the Data was delivered. Except as provided herein, the Data may not be used, disclosed, reproduced, modified, performed, or displayed without the prior written approval of NetApp, Inc. United States Government license rights for the Department of Defense are limited to those rights identified in DFARS clause 252.227-7015(b) (FEB 2014).

Trademark information

NETAPP, the NETAPP logo, and the marks listed at <http://www.netapp.com/TM> are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.