



Reactivate the source volume

System Manager Classic

NetApp
April 09, 2024

This PDF was generated from https://docs.netapp.com/us-en/ontap-sm-classic/volume-disaster-recovery/task_resynchronizing_source_volume.html on April 09, 2024. Always check docs.netapp.com for the latest.

Table of Contents

Reactivate the source volume	1
Resynchronize the source volume	1
Update the source volume	2
Reactivate the source volume	3

Reactivate the source volume

When the source volume becomes available, you must resynchronize the data from the destination volume to the source volume, update any modifications after the resynchronization operation, and activate the source volume.

Resynchronize the source volume

When the source volume is online, you must resynchronize the data between the destination volume and the source volume to replicate the latest data from the destination volume.

Before you begin

The source volume must be online.

About this task


You must perform the task from the **destination** cluster.

The following image shows that the data is replicated from the active destination volume to the read-only source volume:



Steps

1. Depending on the System Manager version that you are running, perform one of the following steps:
 - ONTAP 9.4 or earlier: Click **Protection > Relationships**.
 - Beginning with ONTAP 9.5: Click **Protection > Volume Relationships**.
2. Select the SnapMirror relationship between the source and destination volumes.
3. Make a note of the transfer schedule and the policy configured for the SnapMirror relationship.
4. Click **Operations > Reverse Resync**.
5. Select the confirmation check box, and then click **Reverse Resync**.



Beginning with ONTAP 9.3, the SnapMirror policy of the relationship is set to `MirrorAllSnapshots` and the mirror schedule is set to `None`.

If you are running ONTAP 9.2 or earlier, the SnapMirror policy of the relationship is set to `DPDefault` and the mirror schedule is set to `None`.

6. On the source cluster, specify a SnapMirror policy and schedule that match the protection configuration of the original SnapMirror relationship:
 - a. Depending on the System Manager version that you are running, perform one of the following steps:
 - ONTAP 9.4 or earlier: Click **Protection > Relationships**.
 - Beginning with ONTAP 9.5: Click **Protection > Volume Relationships**.
 - b. Select the SnapMirror relationship between the resynchronized source volume and the destination volume, and then click **Edit**.
 - c. Select the SnapMirror policy and schedule, and then click **OK**.

Update the source volume

After resynchronizing the source volume, you might want to ensure that all the latest changes are updated on the source volume before activating the source volume.

About this task

You must perform this task from the **source** cluster.

Steps

1. Depending on the System Manager version that you are running, perform one of the following steps:
 - ONTAP 9.4 or earlier: Click **Protection > Relationships**.
 - Beginning with ONTAP 9.5: Click **Protection > Volume Relationships**.

2. Select the SnapMirror relationship between the source and the destination volumes, and then click **Operations > Update**.
3. Perform an incremental transfer from the recent common Snapshot copy between the source and destination volumes.
 - Beginning with ONTAP 9.3: Select the **As per policy** option.
 - ONTAP 9.2 or earlier: Select the **On demand** option.
4. **Optional:** Select **Limit transfer bandwidth to** in order to limit the network bandwidth used for transfers, and then specify the maximum transfer speed.
5. Click **Update**.
6. Verify that the transfer status is **Idle** and last transfer type is **Update** in the **Details** tab.

The screenshot shows a 'Relationships' table with three rows. The third row is selected, showing a SnapMirrored relationship between source volume 'svm1_vvol1_mirror' and destination volume 'svm1_vvol1'. The 'Is Healthy' status is 'Yes', and the 'Transfer Status' is 'Idle'. Below the table, the 'Details' tab is active, showing configuration for the selected relationship. The 'Source Location' is 'svm2:svm1_vvol1_mirror' and the 'Destination Location' is 'svm1_vvol1'. The 'Transfer Status' is 'Idle', and the 'Last Transfer Type' is 'Update'. The 'Latest Snapshot Timestamp' is '02/22/2017 16:47:18' and the 'Latest Snapshot Copy' is 'snapmirror.20c56fe5-e6d8-11e6-b4de-00a0951a1bda_2149622807.2017-1'.

Source Sto...	Source Vol...	Destinatio...	Destinatio...	Is Healthy	Relationship	Transfer St...	Relationship	Lag Time	Policy Name	Policy Type
svm1	svm1_root	svm1_vvol1_r...	svm2	Yes	Snapmirrored	Idle	Mirror	44 min(s)	DPDefault	Asynchronous...
svm1	vvol123	svm1_vvol123...	svm2	Yes	Snapmirrored	Idle	Vault	4 hr(s) 56 min...	XDPDefault	Vault
svm2	svm1_vvol1_m...	vvol1	svm1	Yes	Snapmirrored	Idle	Mirror	2 min(s)	DPDefault	Asynchronous...

Details

Source Location: svm2:svm1_vvol1_mirror
 Destination Location: svm1_vvol1
 Source Cluster: cluster-1
 Destination Cluster: cluster-1
 Transfer Schedule: None
 Data Transfer Rate: Unlimited
 Lag Time: 2 min(s)

Is Healthy: Yes
 Relationship State: Snapmirrored
 Network Compression Ratio: Not Applicable

Transfer Status: Idle
 Current Transfer Type: None
 Current Transfer Error: None
 Last Transfer Error: None
 Last Transfer Type: Update
 Latest Snapshot Timestamp: 02/22/2017 16:47:18
 Latest Snapshot Copy: snapmirror.20c56fe5-e6d8-11e6-b4de-00a0951a1bda_2149622807.2017-1


Reactivate the source volume

After resynchronizing the data from the destination volume to the source volume, you must activate the source volume by breaking the SnapMirror relationship. You should then resynchronize the destination volume to protect the reactivated source volume.

About this task


Both the break and reverse resync operations are performed from the **source** cluster.

The following image shows that the source and destination volumes are read/write when you break the SnapMirror relationship. After the reverse resync operation, the data is replicated from the active source volume to the read-only destination volume.




Steps

1. Depending on the System Manager version that you are running, perform one of the following steps:
 - ONTAP 9.4 or earlier: Click **Protection > Relationships**.
 - Beginning with ONTAP 9.5: Click **Protection > Volume Relationships**.
2. Select the SnapMirror relationship between the source and the destination volumes.
3. Click **Operations > Quiesce**.
4. Select the confirmation check box, and then click **Quiesce**.
5. Click **Operations > Break**.
6. Select the confirmation check box, and then click **Break**.



7. Click **Operations > Reverse Resync**.
8. Select the confirmation check box, and then click **Reverse Resync**.



Beginning with ONTAP 9.3, the SnapMirror policy of the relationship is set to `MirrorAllSnapshots` and the SnapMirror schedule is set to `None`.

If you are running ONTAP 9.2 or earlier, the SnapMirror policy of the relationship is set to `DPDefault` and the SnapMirror schedule is set to `None`.

9. Navigate to the source volume in the volumes page, and verify that the SnapMirror relationship you created is listed and the relationship state is `Snapmirrored`.
10. On the destination cluster, specify a SnapMirror policy and schedule that match the protection configuration of the original SnapMirror relationship for the new SnapMirror relationship:
 - a. Depending on the System Manager version that you are running, perform one of the following steps:
 - ONTAP 9.4 or earlier: Click **Protection > Relationships**.
 - Beginning with ONTAP 9.5: Click **Protection > Volume Relationships**.
 - b. Select the SnapMirror relationship between the reactivated source and the destination volumes, and then click **Edit**.
 - c. Select the SnapMirror policy and schedule, and then click **OK**.

Results

The source volume has read/write access and is protected by the destination volume.

Copyright information

Copyright © 2024 NetApp, Inc. All Rights Reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means—graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system—without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

LIMITED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (b)(3) of the Rights in Technical Data -Noncommercial Items at DFARS 252.227-7013 (FEB 2014) and FAR 52.227-19 (DEC 2007).

Data contained herein pertains to a commercial product and/or commercial service (as defined in FAR 2.101) and is proprietary to NetApp, Inc. All NetApp technical data and computer software provided under this Agreement is commercial in nature and developed solely at private expense. The U.S. Government has a non-exclusive, non-transferrable, nonsublicensable, worldwide, limited irrevocable license to use the Data only in connection with and in support of the U.S. Government contract under which the Data was delivered. Except as provided herein, the Data may not be used, disclosed, reproduced, modified, performed, or displayed without the prior written approval of NetApp, Inc. United States Government license rights for the Department of Defense are limited to those rights identified in DFARS clause 252.227-7015(b) (FEB 2014).

Trademark information

NETAPP, the NETAPP logo, and the marks listed at <http://www.netapp.com/TM> are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.