



job commands

Command reference

NetApp
February 02, 2026

Table of Contents

job commands	1
job delete	1
Description	1
Parameters	1
Examples	1
Related Links	1
job pause	1
Description	1
Parameters	1
Examples	2
Related Links	2
job resume	2
Description	2
Parameters	2
Examples	2
Related Links	2
job show-bynode	3
Description	3
Parameters	3
Examples	4
job show-cluster	4
Description	4
Parameters	4
Examples	6
job show-completed	7
Description	7
Parameters	7
Examples	8
job show	9
Description	9
Parameters	9
Examples	11
job stop	12
Description	12
Parameters	12
Examples	12
Related Links	13
job unclaim	13
Description	13
Parameters	13
Examples	13
Related Links	13
job watch-progress	13

Description	14
Parameters	14
Examples	14
job history commands	14
job history show	14
job initstate commands	17
job initstate show	17
job private commands	19
job private delete	19
job private pause	20
job private resume	21
job private show-completed	22
job private show	24
job private stop	26
job private watch-progress	27
job schedule commands	28
job schedule delete	28
job schedule show-jobs	29
job schedule show	30
job schedule cron create	31
job schedule cron delete	32
job schedule cron modify	33
job schedule cron show	34
job schedule interval create	36
job schedule interval delete	37
job schedule interval modify	38
job schedule interval show	39

job commands

job delete

Delete a job

Availability: This command is available to *cluster* and *Vserver* administrators at the *admin* privilege level.

Description

The `job delete` command deletes a job. Use the [job show](#) command to view a list of running jobs that can be deleted.

Parameters

-id <integer> - Job ID

The numeric ID of the job you want to delete. A job ID is a positive integer.

[-vserver <vserver name>] - Owning Vserver

Use this parameter to specify the name of the Vserver that owns the job.

Examples

The following example deletes the job that has ID 99:

```
cluster1::> job delete -id 99
```

Related Links

- [job show](#)

job pause

Pause a job

Availability: This command is available to *cluster* and *Vserver* administrators at the *admin* privilege level.

Description

The `job pause` command pauses a job. Use the [job resume](#) command to resume a paused job. Use the [job show](#) command to view a list of running jobs that can be paused.

Parameters

-id <integer> - Job ID

The numeric ID of the job you want to pause. A job ID is a positive integer.

[-vserver <vserver name>] - Owning Vserver

Use this parameter to specify the name of the Vserver that owns the job.

Examples

The following example pauses the job that has ID 183:

```
cluster1::> job pause -id 183
```

Related Links

- [job resume](#)
- [job show](#)

job resume

Resume a job

Availability: This command is available to *cluster* and *Vserver* administrators at the *admin* privilege level.

Description

The *job resume* command resumes a job that was previously paused by using the [job pause](#) command. Use the [job show](#) command to view a list of paused jobs that can be resumed.

Parameters

-id <integer> - Job ID

The numeric ID of the paused job to be resumed. A job ID is a positive integer.

[-vserver <vserver name>] - Owning Vserver

Use this parameter to specify the name of the Vserver that owns the job.

Examples

The following example resumes the paused job that has ID 183:

```
cluster1::> job resume -id 183
```

Related Links

- [job pause](#)
- [job show](#)

job show-bynode

Display a list of jobs by node

Availability: This command is available to *cluster* and *Vserver* administrators at the *admin* privilege level.

Description

The `job show-bynode` command displays information about jobs on a per-node basis. The command output depends on the parameters specified with the command. If no parameters are specified, the command displays information about all jobs in the cluster that are currently owned by a node.

To display detailed information about a specific job, run the command with the `-id` parameter. The detailed view includes all of the default information plus additional items.

You can specify additional parameters to display only information that matches the values you specify for those parameters. For example, to display information only about jobs running on a specific node, run the command with the `-node` parameter.

Parameters

{ [-fields <fieldname>,...]

If you specify the `-fields <fieldname>,...` parameter, the command output also includes the specified field or fields. You can use `'-fields ?'` to display the fields to specify.

| [-instance] }

If you specify the `-instance` parameter, the command displays detailed information about all fields.

[-node {<nodename>|local}] - Node

Use this parameter to display information only about the jobs that are associated with the node you specify.

[-id <integer>] - Job ID

Use this parameter to display information only about the jobs that match the ID or range of IDs you specify.

[-vserver <vserver name>] - Owning Vserver

Use this parameter with the name of a Vserver to display only jobs that are owned by that Vserver.

[-name <text>] - Name

Use this parameter to display information only about the jobs that match the job name you specify.

[-description <text>] - Description

Use this parameter to display information only about the jobs that match the description you specify.

[-affinity {Cluster|Node}] - Affinity

Use this parameter with an affinity value to display only jobs that match the affinity you specify.

[-username <text>] - User Name

Use this parameter with a username to display only jobs that are associated with that user.

Examples

The following example displays information about all jobs on a per-node basis:

```
node::> job show-bynode
          Owning
  Node      Job ID Name      Vserver      Affinity
-----  -----
node0      1501  log-rotation  node-vserver
                         Cluster
                         Descr:logrotation job
node1      1498  log-rotation  node-vserver
                         Cluster
                         Descr:logrotation job
node2      1499  log-rotation  node-vserver
                         Cluster
                         Descr:logrotation job
node3      1500  log-rotation  node-vserver
                         Cluster
                         Descr:logrotation job
```

job show-cluster

Display a list of cluster jobs

Availability: This command is available to *cluster* and *Vserver* administrators at the *admin* privilege level.

Description

The `job show-cluster` command displays information about cluster-affiliated jobs. The command output depends on the parameters specified with the command. If no parameters are specified, the command displays information about all cluster-affiliated jobs.

To display detailed information about a specific job, run the command with the `-id` parameter. The detailed view includes all of the default information plus additional items.

You can specify additional parameters to display only information that matches the values you specify for those parameters. For example, to display information only about jobs running on a specific node, run the command with the `-node` parameter.

Parameters

{ [-fields <fieldname>,...]

If you specify the `-fields <fieldname>,...` parameter, the command output also includes the specified field or fields. You can use `'-fields ?'` to display the fields to specify.

[[-instance]]

If you specify the `-instance` parameter, the command displays detailed information about all fields.

[-id <integer>] - Job ID

Use this parameter to display information only about the jobs that match the ID or range of IDs you specify.

[-vserver <vserver name>] - Owning Vserver

Use this parameter with the name of a Vserver to display only jobs that are owned by that Vserver.

[-name <text>] - Name

Use this parameter to display information only about the jobs that match the job name you specify.

[-description <text>] - Description

Use this parameter to display information only about the jobs that match the description you specify.

[-priority {Low|Medium|High|Exclusive}] - Priority

Use this parameter to display information only about the jobs that match the priority you specify.

[-node <nodename>] - Node

Use this parameter to display information only about the jobs that are associated with the node you specify.

[-affinity {Cluster|Node}] - Affinity

Use this parameter with an affinity value to display only jobs that match the affinity you specify.

[-schedule <job_schedule>] - Schedule

Use this parameter to display information only about the jobs that run on the schedule you specify.

[-queuetime <MM/DD HH:MM:SS>] - Queue Time

Use this parameter to display information only about the jobs that match the queue time you specify.

[-starttime <MM/DD HH:MM:SS>] - Start Time

Use this parameter to display information only about the jobs that match the start time you specify.

[-endtime <MM/DD HH:MM:SS>] - End Time

Use this parameter to display information only about the jobs that match the end time you specify.

[-dropdeadtime <MM/DD HH:MM:SS>] - Drop-dead Time

Use this parameter to display information only about the jobs that match the final timeout time you specify.

[-restarted {true|false}] - Restarted?

Use this parameter to display information only about the jobs that match the restart value you specify.

[-state

{Initial|Queued|Running|Waiting|Pausing|Paused|Quitting|Success|Failure|Reschedule|Error|Quit|Dead|Unknown|Restart|Dormant}] - State

Use this parameter to display information only about the jobs that match the job state you specify.

[-code <integer>] - Status Code

Use this parameter to display information only about the jobs that match the status code you specify.

[-completion <text>] - Completion String

Use this parameter to display information only about the jobs that match the completion text you specify.

[-jobtype <text>] - Job Type

Use this parameter to display information only about the jobs that match the job type you specify.

[-category <text>] - Job Category

Use this parameter to display information only about the jobs that match the job category you specify.

[-uuid <UUID>] - UUID

Use this parameter to display information only about the jobs that match the UUID you specify.

[-username <text>] - User Name

Use this parameter with a username to display only jobs that are associated with the user you specify.

Examples

The following example displays information about all cluster-affiliated jobs:

```
cluster1::> job show-cluster
          Owning
Job ID Name          Vserver  Node      State
----- -----
305   Auto_Mirror    node-vserver
                  -
                  Running
6202  mirror-03_10   node-vserver
                  -
                  Queued
      Descr:Auto mirror
6203  mirror-04_10   node-vserver
                  -
                  Queued
      Descr:Auto mirror
6204  mirror-01_10   node-vserver
                  -
                  Queued
      Descr:Auto mirror
6205  mirror-02_10   node-vserver
                  -
                  Queued
      Descr:Auto mirror
6206  mirror-05_10   node-vserver
                  -
                  Queued
      Descr:Auto mirror
```

job show-completed

Display a list of completed jobs

Availability: This command is available to *cluster* and *Vserver* administrators at the *admin* privilege level.

Description

The `job show-completed` command displays information about completed jobs. The command output depends on the parameters you specify with the command. If you do not use any parameters, the command displays information about all completed jobs.

To display detailed information about a specific job, run the command with the `-id` parameter. The detailed view includes all of the default information plus additional items.

You can specify additional parameters to display only information that matches those parameters. For instance, to display information only about jobs running on a specific node, run the command with the `-node` parameter.

Parameters

{ [-fields <fieldname>,...]

If you specify the `-fields <fieldname>,...` parameter, the command output also includes the specified field or fields. You can use `'-fields ?'` to display the fields to specify.

| [-instance] }

If you specify the `-instance` parameter, the command displays detailed information about all fields.

[-id <integer>] - Job ID

Use this parameter to display information only about the jobs that match the ID or range of IDs you specify.

[-vserver <vserver name>] - Owning Vserver

Use this parameter with the name of a Vserver to display only jobs that are owned by that Vserver.

[-name <text>] - Name

Use this parameter to display information only about the jobs that match the name you specify.

[-description <text>] - Description

Use this parameter to display information only about the jobs that match the description you specify.

[-priority {Low|Medium|High|Exclusive}] - Priority

Use this parameter to display information only about the jobs that match the priority you specify.

[-node <nodename>] - Node

Use this parameter to display information only about the jobs that are associated with the node you specify.

[-affinity {Cluster|Node}] - Affinity

Use this parameter with an affinity value to display only jobs that match the affinity you specify.

[-schedule <job_schedule>] - Schedule

If you use this parameter, the command displays information only about the jobs that have the schedule you specify.

[-queuetime <MM/DD HH:MM:SS>] - Queue Time

If you use this parameter, the command displays information only about the jobs that have the queue time you specify.

[-starttime <MM/DD HH:MM:SS>] - Start Time

Use this parameter to display information only about the jobs that have the start time you specify.

[-endtime <MM/DD HH:MM:SS>] - End Time

Use this parameter to display information only about the jobs that have the end time you specify.

[-dropdeadtime <MM/DD HH:MM:SS>] - Drop-dead Time

Use this parameter to display information only about the jobs that time out at the time you specify.

[-restarted {true|false}] - Restarted?

Use this parameter to display information only about the jobs that match the restart value you specify.

[-state

{Initial|Queued|Running|Waiting|Pausing|Paused|Quitting|Success|Failure|Reschedule|Error|Quit|Dead|Unknown|Restart|Dormant}] - State

Use this parameter to display information only about the jobs that match the job state you specify.

[-code <integer>] - Status Code

Use this parameter to display information only about the jobs that match the status code you specify.

[-completion <text>] - Completion String

Use this parameter to display information only about the jobs that match the completion text you specify.

[-jobtype <text>] - Job Type

Use this parameter to display information only about the jobs that match the job type you specify.

[-category <text>] - Job Category

Use this parameter to display information only about the jobs that match the job category you specify.

[-uuid <UUID>] - UUID

Use this parameter to display information only about the jobs that match the UUID you specify.

[-username <text>] - User Name

Use this parameter with a username to display only jobs that are associated with that user.

Examples

The following example displays information about all completed jobs:

```

node::> job show-completed
          Owning
Job ID Name          Vserver  End Time      Code      Completion
String
-----
-----
305    Auto_Mirror    node-vserver
                  10/10 08:07:05 0      Succeeded
6202   mirror-03_10   node-vserver
                  10/10 11:10:07 0
6203   mirror-04_10   node-vserver
                  10/10 12:10:09 0
6204   mirror-01_10   node-vserver
                  10/10 09:10:03 0
6205   mirror-02_10   node-vserver
                  10/10 10:10:08 0
6206   mirror-05_10   node-vserver
                  10/10 05:10:04 0

```

job show

Display a list of jobs

Availability: This command is available to *cluster* and *Vserver* administrators at the *admin* privilege level.

Description

The `job show` command displays information about jobs. By default, the command displays information about all current jobs.

To display detailed information about a specific job, run the command with the `-id` parameter.

You can specify additional parameters to select information that matches the values you specify for those parameters. For example, to display information only about jobs running on a specific node, run the command with the `-node` parameter.

Parameters

{ [-fields <fieldname>, ...]

If you specify the `-fields <fieldname>, ...` parameter, the command output also includes the specified field or fields. You can use `'-fields ?'` to display the fields to specify.

| [-inprogress]

Displays the job ID, the job name, the owning Vserver, and the progress of the job.

| [-jobstate]

Displays information about each job's state, including the queue state, whether the job was restarted, and when the job has completely timed out.

| [-jobuuid] (privilege: advanced)

Displays the job ID, the job name, the owning Vserver, and the job UUID.

| [-sched]

Displays the job ID, the job name, the owning Vserver, and the schedule on which the job runs.

| [-times]

Displays the job ID, the job name, the owning Vserver, the time when the job was last queued, the time when the job was last started, and the time when the job most recently ended.

| [-type]

Displays the job ID, the job name, the job type, and the job category.

| [-instance] }

If you specify the `-instance` parameter, the command displays detailed information about all fields.

[-id <integer>] - Job ID

Selects the jobs that match the ID or range of IDs that you specify.

[-vserver <vserver name>] - Owning Vserver

Selects jobs that are owned by the specified Vserver.

[-name <text>] - Name

Selects the jobs that match this parameter value.

[-description <text>] - Description

Selects the jobs that match this parameter value.

[-priority {Low|Medium|High|Exclusive}] - Priority

Selects the jobs that match this parameter value.

[-node <nodename>] - Node

Selects the jobs that match this parameter value.

[-affinity {Cluster|Node}] - Affinity

Selects the jobs that match this parameter value.

[-schedule <job_schedule>] - Schedule

Selects the jobs that match this parameter value.

[-queuetime <MM/DD HH:MM:SS>] - Queue Time

Selects the jobs that match this parameter value.

[-starttime <MM/DD HH:MM:SS>] - Start Time

Selects the jobs that match this parameter value.

[-endtime <MM/DD HH:MM:SS>] - End Time

Selects the jobs that match this parameter value.

[-dropdeadtime <MM/DD HH:MM:SS>] - Drop-dead Time

Selects the jobs that match this parameter value.

[-restarted {true|false}] - Restarted?

Selects the jobs that match this parameter value.

[-state

{Initial|Queued|Running|Waiting|Pausing|Paused|Quitting|Success|Failure|Reschedule|Error|Quit|Dead|Unknown|Restart|Dormant}] - State

Selects the jobs that match this parameter value.

[-code <integer>] - Status Code

Selects the jobs that match this parameter value.

[-completion <text>] - Completion String

Selects the jobs that match this parameter value.

[-jobtype <text>] - Job Type

Selects the jobs that match this parameter value.

[-category <text>] - Job Category

Selects the jobs that match this parameter value.

[-uuid <UUID>] - UUID (privilege: advanced)

Selects the jobs that match this parameter value.

[-progress <text>] - Execution Progress

Selects the jobs that match this parameter value.

[-username <text>] - User Name

Selects the jobs that match this parameter value.

[-restart-is-delayed-by-module <text>] - Restart Is Delayed by Module

Selects jobs which are or were delayed by the specified module during the restart. For example:
MCC_SWITCHBACK

Examples

The following example displays information about all jobs on the node named node1:

```

cluster1::> job show -node node1
                  Owning
Job ID Name      Vserver   Node      State
-----
308114 mirror-daily-3587206
                  node-vserver
                  node1      Running
      Descr:Auto-replicate to 1 mirror(s)
308115 mirror-daily-3618985
                  node-vserver
                  node1      Running
      Descr:Auto-replicate to 1 mirror(s)
308116 mirror-daily-3619010
                  node-vserver
                  node1      Queued
      Descr:Auto-replicate to 1 mirror(s)
308117 mirror-daily-3749547
                  node-vserver
                  node1      Queued
      Descr:Auto-replicate to 1 mirror(s)
4 entries were displayed.

```

job stop

Stop a job

Availability: This command is available to *cluster* and *Vserver* administrators at the *admin* privilege level.

Description

The `job stop` command stops a running job. A stopped job cannot be resumed. Use the [job pause](#) command to pause a job so that you can later resume it. Use the [job show](#) command to view a list of running jobs.

Parameters

-id <integer> - Job ID

The numeric ID of the job to stop. A job ID is a positive integer.

[-vserver <vserver name>] - Owning Vserver

Use this parameter to specify the name of the Vserver that owns the job.

Examples

The following example stops the job that has ID 101:

```
cluster1::> job stop -id 101
```

Related Links

- [job pause](#)
- [job show](#)

job unclaim

Unclaim a cluster job

Availability: This command is available to *cluster* and *Vserver* administrators at the *advanced* privilege level.

Description

The `job unclaim` command causes a cluster-affiliated job that is owned by an unavailable node to be unclaimed by that node. Another node in the cluster can then take ownership of the job. Use the [job show-cluster](#) command to obtain a list of cluster-affiliated jobs.

Parameters

-id <integer> - Job ID (privilege: advanced)

Use this parameter to specify the ID number of the job to unclaim.

[-vserver <vserver name>] - Owning Vserver (privilege: advanced)

Use this parameter to specify the name of the Vserver that owns the job.

Examples

The following example shows how to unclaim the cluster-affiliated job with the ID 27 that is owned by the Vserver `vs1`:

```
cluster1::*> job unclaim -vserver vs1 -id 27
```

Related Links

- [job show-cluster](#)

job watch-progress

Watch the progress of a job

Availability: This command is available to *cluster* and *Vserver* administrators at the *admin* privilege level.

Description

The `job watch-progress` command displays the progress of a job, and periodically updates that display. You can specify the frequency of the updates.

Parameters

`-id <integer>` - Job ID

Use this parameter to specify the numeric ID of the job to monitor.

`[-vserver <vserver name>]` - Owning Vserver

Use this parameter to specify the name of the Vserver that owns the job.

`[-interval <integer>]` - Refresh Interval (seconds)

Use this parameter to specify the number of seconds between updates.

Examples

The following example show how to monitor the progress of the job that has ID 222 on Vserver `vs0` . The progress display updates every 3 seconds.

```
cluster1::> job watch-progress -vserver vs0 -id 222 -interval 3
```

job history commands

job history show

Display a history of jobs

Availability: This command is available to `cluster` and `Vserver` administrators at the `admin` privilege level.

Description

The `job history show` command displays a history of completed jobs with newer entries displayed first. You can specify optional parameters to select information about job history items that match only those parameters. For example, to display information about jobs that were completed on February 27 at noon, run the command with `-endtime "02/27 12:00:00"`.

Parameters

{ `[-fields <fieldname>,...]`

If you specify the `-fields <fieldname>,...` parameter, the command output also includes the specified field or fields. You can use `'-fields ?'` to display the fields to specify.

`[-instance]`

If you specify the `-instance` parameter, the command displays detailed information about all fields.

[-node {<nodename>|local}] - Node

Selects the completed jobs that match this parameter value.

[-record <Sequence Number>] - Record ID

Selects the completed jobs that match the record ID or range of record IDs you specify. Note that record IDs are unique for each node, not for the cluster as a whole. As a result, there can be two records with the same record ID within the cluster.

[-vserver <vserver name>] - Owning Vserver

Selects the completed jobs that are owned by the Vserver you specify.

[-id <integer>] - Job ID

Selects the completed jobs that match this parameter value.

[-endtime <MM/DD HH:MM:SS>] - End Time

Selects jobs that completed at the time you specify. This parameter is most useful when used with a range of times.

[-starttime <MM/DD HH:MM:SS>] - Start Time

Selects completed jobs that were started at the time you specify. This parameter is most useful when used with a range of times.

[-name <text>] - Name

Selects the completed jobs that match this parameter value.

[-description <text>] - Description

Selects the completed jobs that match this parameter value.

[-code <integer>] - Status Code

Selects the completed jobs that match this parameter value. Each job defines its own status codes. The completion text is more informative, but support technicians may request this numeric code.

[-progress <text>] - Progress String

Selects the completed jobs that match this parameter value.

[-completion <text>] - Completion String

Selects the completed jobs that match this parameter value.

[-jobuuid <UUID>] - Job UUID (privilege: advanced)

Selects the completed jobs that match this parameter value.

[-event-type {Idle|Running|Succeeded|Failed|Paused|Stopped|Deleted|Error}] - Event Type

Selects the completed jobs that match this parameter value.

[-event-time <MM/DD HH:MM:SS>] - Event Time

Selects the completed jobs that match this parameter value. This parameter is most useful when used with a range of times.

[-error-code <integer>] - Job Manager Error Code

Selects the completed jobs that match this parameter value.

[-error-text <text>] - Job Manager Error Text

Selects the completed jobs that match this parameter value.

[-username <text>] - User Name

Selects the completed jobs that match this parameter value.

Examples

The following example displays information about all completed jobs:

```
cluster1::> job history show
          Owning
Time      Node      Vserver      Name      Event
Job ID
-----
-----
08/23 08:58:24 node1      node1-vs      Vol Create      Succeeded
76
      Description: Create testvol
      Completion: Successful
08/23 08:58:22 node1      node1-vs      Vol Create      Running
76
      Description: Create testvol
08/22 08:16:36 node1      node1-vs      CLUSTER BACKUP AUTO weekly
                                         Succeeded
4
      Description: Cluster Backup Job
08/22 08:15:49 node1      node1-vs      CLUSTER BACKUP AUTO weekly
                                         Running
4
      Description: Cluster Backup Job
08/22 08:15:08 node1      node1-vs      CLUSTER BACKUP AUTO weekly
                                         Idle
4
      Description: Cluster Backup Job
08/22 08:15:03 node1      node1-vs      CLUSTER BACKUP AUTO weekly
                                         Running
4
      Description: Cluster Backup Job
6 entries were displayed.
```

The following example shows how to use a range with the "endtime" parameter to select only the events that ended between 8:15 and 8:16 on August 22nd.

```

cluster1::> job history show -endtime "08/22 08:15:00".."08/22 08:16:00"
                                         Owning
Time          Node          Vserver      Name          Event
Job ID
-----
-----
08/22 08:15:49 node1          node1-vs    CLUSTER BACKUP AUTO weekly
                                         Running
4
  Description: Cluster Backup Job
08/22 08:15:08 node1          node1-vs    CLUSTER BACKUP AUTO weekly
                                         Idle
4
  Description: Cluster Backup Job
08/22 08:15:03 node1          node1-vs    CLUSTER BACKUP AUTO weekly
                                         Running
4
  Description: Cluster Backup Job
3 entries were displayed.

```

job initstate commands

job initstate show

Display init state for job managers

Availability: This command is available to *cluster* administrators at the *advanced* privilege level.

Description

The `job initstate show` command displays information about the initialization states of job-manager processes.

Parameters

`[-fields <fieldname>,...]`

If you specify the `-fields <fieldname>,...` parameter, the command output also includes the specified field or fields. You can use `-fields ?` to display the fields to specify.

`| [-instance] (privilege: advanced) }`

If you specify the `-instance` parameter, the command displays detailed information about all fields.

`[-node {<nodename>|local}] - Node (privilege: advanced)`

Selects the nodes that match this parameter value.

[-process <process_name>] - Process Name (privilege: advanced)

Selects the nodes that match this parameter value.

[-initialized {true|false}] - Initialized? (privilege: advanced)

Selects the nodes that match this parameter value (true means initialized; false means not initialized).

[-cache-root <text>] - Cache Root (privilege: advanced)

Selects the nodes that match this parameter value.

[-siteid <UUID>] - Site ID (privilege: advanced)

Selects the nodes that match this parameter value.

[-hp-threads <integer>] - High Priority Threads (privilege: advanced)

Selects the nodes that have the number of high-priority threads you specify.

[-mp-threads <integer>] - Medium Priority Threads (privilege: advanced)

Selects the nodes that have the number of medium-priority threads you specify.

[-lp-threads <integer>] - Low Priority Threads (privilege: advanced)

Selects the nodes that have the number of low-priority threads you specify.

[-tx-interval <integer>] - Transaction Interval (privilege: advanced)

Selects the nodes that have the number of seconds you specify as their transaction interval.

[-initmsg <text>] - Initialization Message (privilege: advanced)

Selects the nodes that match this parameter value.

[-thread-initmsg <text>] - Thread Initialization Message (privilege: advanced)

Selects the nodes that match this parameter value. The thread initialization message contains information about thread status. If there is no information to communicate, this message is empty.

[-recovery-enabled {true|false}] - Job Failover Enabled? (privilege: advanced)

Selects the nodes that match this parameter value (true means enabled, false means not enabled).

[-ex-threads <integer>] - Exclusive Priority Threads (privilege: advanced)

Selects the nodes that match this parameter value.

Examples

The following example shows how to display general job-manager initialization-state information for a cluster.

```
cluster1::*> job initstate show
              HP    MP    LP    EX
Node        Process  Init? Thr  Thr  Thr  Thr  TX Int Failover?
-----  -----
node1      mgwd    true   2    3    5    8   300 true
node2      mgwd    true   2    3    5    8   300 true
2 entries were displayed.
```

The following example shows how to display detailed job-manager initialization-state information for a node named node0 .

```
cluster1::*> job initstate show -instance -node node0
              Node: node0
              Process Name: mgwd
              Initialized?: true
              Cache Root: /mroot/jm_cache
              Site ID: 824e8f7d-f49-1d9-84af-00423b7352
              High Priority Threads: 2
              Medium Priority Threads: 3
              Low Priority Threads: 5
              Transaction Interval: 300
              Initialization Message: Initialized
              Are Threads Running?: -
              Job Failover Enabled?: true
              Exclusive Priority Threads: 8
```

job private commands

job private delete

Delete a job

Availability: This command is available to *cluster* and *Vserver* administrators at the *advanced* privilege level.

Description

The `job private delete` command deletes a private job. Private jobs are affiliated with a specific node and do not use any cluster facilities, such as the replicated database.

If you use this command on a job that does not support the delete operation, the command returns an error message.

Use the [job private show](#) command to view a list of private jobs that can be deleted.

Parameters

-node {<nodename>|local} - Node (privilege: advanced)

Use this parameter to specify the node with which the private job is associated.

-id <integer> - Job ID (privilege: advanced)

Use this parameter to specify the numeric ID of the private job to be deleted. A job ID is a positive integer.

[-vserver <vserver name>] - Owning Vserver (privilege: advanced)

Use this parameter to specify the name of the Vserver that owns the job.

Examples

The following example shows how to delete the job that has ID 273 from the node named node2 :

```
cluster1::*> job private delete -node node2 -id 273
```

Related Links

- [job private show](#)

job private pause

Pause a job

Availability: This command is available to *cluster* and *Vserver* administrators at the *advanced* privilege level.

Description

The `job private pause` command pauses a private job. Private jobs are affiliated with a specific node and do not use any cluster facilities, such as the replicated database.

If you use this command to pause a job that does not support it, the command returns an error message.

Use the `job private resume` command to resume a paused private job.

Use the `job private show` command to view a list of private jobs.

Parameters

-node {<nodename>|local} - Node (privilege: advanced)

Use this parameter to specify the node with which the private job is associated.

-id <integer> - Job ID (privilege: advanced)

Use this parameter to specify the numeric ID of the paused private job to be paused. A job ID is a positive integer.

[-vserver <vserver name>] - Owning Vserver (privilege: advanced)

Use this parameter to specify the name of the Vserver that owns the job.

Examples

The following example pauses the private job that has ID 99 on the node node1 :

```
cluster1::*> jobs private pause -node node1 -id 99
```

Related Links

- [job private resume](#)
- [job private show](#)

job private resume

Resume a job

Availability: This command is available to *cluster* and *Vserver* administrators at the *advanced* privilege level.

Description

The `job private resume` command resumes a private job that was paused by using the [job private pause](#) command. Private jobs are affiliated with a specific node and do not use any cluster facilities, such as the replicated database.

Use the [job private show](#) command to view a list of paused private jobs that can be resumed.

Parameters

-node {<nodename>|local} - Node (privilege: advanced)

Use this parameter to specify the node with which the paused private job is associated.

-id <integer> - Job ID (privilege: advanced)

Use this parameter to specify the numeric ID of the paused private job to be resumed. A job ID is a positive integer.

[-vserver <vserver name>] - Owning Vserver (privilege: advanced)

Use this parameter to specify the name of the Vserver that owns the job.

Examples

The following example resumes the paused private job that has ID 99 on a node named node2 :

```
cluster1::*> job private resume -node node2 -id 99
```

Related Links

- [job private pause](#)
- [job private show](#)

job private show-completed

Display a list of completed jobs

Availability: This command is available to *cluster* and *Vserver* administrators at the *advanced* privilege level.

Description

The `job private show-completed` command displays information about completed private jobs. Private jobs are affiliated with a specific node and do not use any cluster facilities, such as the replicated database.

Parameters

[-fields <fieldname>,...]

If you specify the `-fields <fieldname>, ...` parameter, the command output also includes the specified field or fields. You can use `'?` to display the fields to specify.

| [-instance] (privilege: advanced) }

If you specify the `-instance` parameter, the command displays detailed information about all fields.

[-node {<nodename>|local}] - Node (privilege: advanced)

Use this parameter to display information only about completed jobs that are associated with the node you specify.

[-id <integer>] - Job ID (privilege: advanced)

Use this parameter to display information only about completed jobs that have the ID you specify.

[-vserver <vserver name>] - Owning Vserver (privilege: advanced)

Use this parameter to display only completed jobs that are owned by the Vserver you specify.

[-name <text>] - Name (privilege: advanced)

Use this parameter to display information only about completed jobs that have the name you specify.

[-description <text>] - Description (privilege: advanced)

Use this parameter to display information only about completed jobs that have the description you specify.

[-priority {Low|Medium|High|Exclusive}] - Priority (privilege: advanced)

Use this parameter to display information only about completed jobs that have the priority you specify.

[-schedule <job_schedule>] - Schedule (privilege: advanced)

Use this parameter to display information only about completed jobs that have the schedule you specify.

[-queuetime <MM/DD HH:MM:SS>] - Queue Time (privilege: advanced)

Use this parameter to display information only about completed jobs that have the queue time you specify.

[-starttime <MM/DD HH:MM:SS>] - Start Time (privilege: advanced)

Use this parameter to display information only about completed jobs that have the start time you specify.

[-endtime <MM/DD HH:MM:SS>] - End Time (privilege: advanced)

Use this parameter to display information only about completed jobs that have the end time you specify.

[-dropdeadtime <MM/DD HH:MM:SS>] - Drop-dead Time (privilege: advanced)

Use this parameter to display information only about completed jobs that have the final timeout time you specify.

[-restarted {true|false}] - Restarted? (privilege: advanced)

Use this parameter to display information only about completed jobs that have the restart value you specify.

[-state

{Initial|Queued|Running|Waiting|Pausing|Paused|Quitting|Success|Failure|Reschedule|Error|Quit|Dead|Unknown|Restart|Dormant}] - State (privilege: advanced)

Use this parameter to display information only about completed jobs that have the job state you specify.

[-code <integer>] - Status Code (privilege: advanced)

Use this parameter to display information only about completed jobs that have the status code you specify.

[-completion <text>] - Completion String (privilege: advanced)

Use this parameter to display information only about completed jobs that have the completion text you specify.

[-jobtype <text>] - Job Type (privilege: advanced)

Use this parameter to display information only about completed jobs that have the job type you specify.

[-category <text>] - Job Category (privilege: advanced)

Use this parameter to display information only about completed jobs that have the job category you specify.

[-uuid <UUID>] - UUID (privilege: advanced)

Use this parameter to display information only about completed jobs that have the UUID you specify.

[-username <text>] - User Name (privilege: advanced)

Use this parameter to display information only about completed jobs that are associated with the user you specify.

Examples

The following example shows how to display information about all completed private jobs on the node named node1 :

```

cluster1::*> job private show-completed -node node1
Node: node1
          Owning
Job ID Name      Vserver   End Time   Code      Completion String
-----  -----
1      sync task    node1    02/17 15:03:23 0
2      load_balancing node1  02/17 16:29:28 0      DONE_VIF_STATS
3      snap-hourly   node1   02/17 16:05:00 0
4      snap-daily    node1   02/17 00:10:00 0
5      snap-weekly   node1   02/13 00:15:00 0
8      Cross-Cluster Manager node1 02/17 16:27:27 0      complete
9      reconcile service policy node1 02/17 15:03:12 0
7 entries were displayed.

```

job private show

Display a list of jobs

Availability: This command is available to *cluster* and *Vserver* administrators at the *advanced* privilege level.

Description

The `job private show` command displays information about private jobs. Private jobs are affiliated with a specific node and do not use any cluster facilities, such as the replicated database.

Parameters

`[-fields <fieldname>,...]`

If you specify the `-fields <fieldname>,...` parameter, the command output also includes the specified field or fields. You can use `'-fields ?'` to display the fields to specify.

`| [-inprogress] (privilege: advanced)`

Displays the job ID, name, owning Vserver, and progress of each private job.

`| [-jobstate] (privilege: advanced)`

Displays information about each private job's state, including the queue state, whether the job was restarted, and when the job has timed out.

`| [-jobuuid] (privilege: advanced)`

Displays the ID, name, owning Vserver, and UUID of each private job.

`| [-sched] (privilege: advanced)`

Displays the job ID, name, owning Vserver, and run schedule of each private job.

`| [-times] (privilege: advanced)`

Displays the queue time, start time, and end time of each private job.

| [-type] (privilege: advanced)

Displays the type and category of each private job.

| [-instance] (privilege: advanced) }

If you specify the -instance parameter, the command displays detailed information about all fields.

[-node {<nodename>|local}] - Node (privilege: advanced)

Selects the private jobs that match this parameter value. .

[-id <integer>] - Job ID (privilege: advanced)

Selects the private jobs that match the ID or range of IDs that you specify.

[-vserver <vserver name>] - Owning Vserver (privilege: advanced)

Selects the private jobs that match this parameter value.

[-name <text>] - Name (privilege: advanced)

Selects the private jobs that match this parameter value.

[-description <text>] - Description (privilege: advanced)

Selects the private jobs that match this parameter value.

[-priority {Low|Medium|High|Exclusive}] - Priority (privilege: advanced)

Selects the private jobs that match this parameter value.

[-schedule <job_schedule>] - Schedule (privilege: advanced)

Selects the private jobs that match this parameter value.

[-queuetime <MM/DD HH:MM:SS>] - Queue Time (privilege: advanced)

Selects the private jobs that match this parameter value.

[-starttime <MM/DD HH:MM:SS>] - Start Time (privilege: advanced)

Selects the private jobs that match this parameter value.

[-endtime <MM/DD HH:MM:SS>] - End Time (privilege: advanced)

Selects the private jobs that match this parameter value.

[-dropdeadtime <MM/DD HH:MM:SS>] - Drop-dead Time (privilege: advanced)

Selects the private jobs that match this parameter value.

[-restarted {true|false}] - Restarted? (privilege: advanced)

Selects the private jobs that match this parameter value.

[-state

{Initial|Queued|Running|Waiting|Pausing|Paused|Quitting|Success|Failure|Reschedule|Error|Quit|Dead|Unknown|Restart|Dormant}] - State (privilege: advanced)

Selects the private jobs that match this parameter value.

[-code <integer>] - Status Code (privilege: advanced)

Selects the private jobs that match this parameter value.

[-completion <text>] - Completion String (privilege: advanced)

Selects the private jobs that match this parameter value.

[-jobtype <text>] - Job Type (privilege: advanced)

Selects the private jobs that match this parameter value.

[-category <text>] - Job Category (privilege: advanced)

Selects the private jobs that match this parameter value.

[-uuid <UUID>] - UUID (privilege: advanced)

Selects the private jobs that match this parameter value.

[-progress <text>] - Execution Progress (privilege: advanced)

Selects the private jobs that match this parameter value.

[-username <text>] - User Name (privilege: advanced)

Selects the private jobs that match this parameter value.

Examples

The following example displays information about all private jobs on the local node:

```
cluster1::*> job private show -node local
Node: node1
                               Owning
Job ID Name                  Vserver   State
-----  -----
3      snap-hourly            cluster1  Queued
      Description: Auto-Snapshot
4      snap-daily              cluster1  Queued
      Description: Auto-Snapshot
5      snap-weekly             cluster1  Queued
      Description: Auto-Snapshot
6      sync task               cluster1  Queued
      Description: sync task
7      ldap-certs              cluster1  Queued
      Description: ldap resync
5 entries were displayed.
```

job private stop

Stop a job

Availability: This command is available to *cluster* and *Vserver* administrators at the *advanced* privilege level.

Description

The `job private stop` command stops a running private job. A private job is a job that is associated with a specific node and does not use cluster facilities. A stopped job cannot be restarted.

Parameters

-node {<nodename>|local} - Node (privilege: advanced)

This specifies the node on which the job is running.

-id <integer> - Job ID (privilege: advanced)

This specifies the numeric ID of the job that is to be stopped.

[-vserver <vserver name>] - Owning Vserver (privilege: advanced)

Use this parameter to specify the name of the Vserver that owns the job.

Examples

The following example stops a private job with the ID 416 on a node named node0:

```
cluster1::*> job private stop -node node0 -id 416
```

job private watch-progress

Watch the progress of a job

Availability: This command is available to *cluster* and *Vserver* administrators at the *advanced* privilege level.

Description

The `job private watch-progress` command displays and periodically updates the progress of a private job. A private job is a job that is associated with a specific node and does not use cluster facilities. You can specify the frequency of the progress updates.

Parameters

-node {<nodename>|local} - Node (privilege: advanced)

This specifies the node on which the job is running.

-id <integer> - Job ID (privilege: advanced)

This specifies the numeric ID of the job whose progress is to be monitored.

[-vserver <vserver name>] - Owning Vserver (privilege: advanced)

Use this parameter to specify the Vserver with which the paused private job is associated.

[-interval <integer>] - Refresh Interval (seconds) (privilege: advanced)

This optionally specifies, in seconds, the frequency of the updates.

Examples

The following example monitors the progress of the private job that has ID 127 on a node named node1. The progress is updated every 2 seconds.

```
cluster1::>* job private watch-progress -node node1 -id 127 -interval 2
Queued
```

job schedule commands

job schedule delete

Delete a schedule

Availability: This command is available to *cluster* and *Vserver* administrators at the *admin* privilege level.

Description

The `job schedule delete` command deletes a schedule. Use the [job schedule show](#) command to display all current schedules.

You cannot delete any schedules that are in use by jobs. Use the [job schedule show-jobs](#) command to display jobs by schedule.

You cannot delete any schedules that are referenced by:

- Volume snapshot policy entries
- SnapMirror entries
- SIS policy entries
- configuration backup settings

You must remove all references to a schedule before you can delete it. If you attempt to delete a schedule that is referenced, an error message will list which entries reference the schedule you want to delete. Use the `show` command for each of the items listed by the error message to display which entries reference the schedule. You may need to use the `-instance` parameter to display more detail.

Parameters

[-cluster <Cluster name>] - Cluster

This parameter specifies the name of the cluster on which you want to delete a schedule. By default, the schedule is deleted from the local cluster. In a MetroCluster configuration, the partner cluster can be specified if the local cluster is in switchover state.

[-vserver <vserver name>] - Vserver

This parameter specifies the name of the Vserver on which you want to delete a schedule.

-name <text> - Schedule Name

Use this parameter with the name of an existing schedule to specify the schedule you want to delete.

Examples

The following example deletes a schedule named overnightbackup:

```
cluster1::> job schedule delete -name overnightbackup
```

Related Links

- [job schedule show](#)
- [job schedule show-jobs](#)

job schedule show-jobs

Display the list of jobs by schedule

Availability: This command is available to *cluster* administrators at the *admin* privilege level.

Description

The `job schedule show-jobs` command displays information about jobs that are associated with schedules.

Parameters

{ [-fields <fieldname>,...]

If you specify the `-fields <fieldname>,...` parameter, the command output also includes the specified field or fields. You can use `-fields ?` to display the fields to specify.

| [-instance] }

If you specify the `-instance` parameter, the command displays detailed information about all fields.

[-name <text>] - Schedule Name

Use this parameter to display information only about the jobs that are associated with the schedule you specify.

[-affinity {Cluster|Node}] - Cluster / Node

Use this parameter to display information only about the jobs that match the affinity value you specify.

[-owner <text>] - Owner

Use this parameter to display information only about the jobs that are owned by the nodes you specify.

[-jobid <integer>] - ID

Use this parameter to display information only about the jobs that match the ID or range of IDs that you specify.

[-jobname <text>] - Job Name

Use this parameter to display information only about the jobs that match the name you specify.

[-scheduleuuid <UUID>] - Schedule Uuid

displays the Uuid of the specific job schedule.

Examples

The following example shows information about schedules that are associated with jobs:

```
cluster1::> job schedule show-jobs
Name          Type      Owner          Job ID      Job Name
Schedule Uuid
-----
-----
hourly        Cluster   -              98644      mirror-hourly
8bafba5a-ff9a-11eb-8531-005056a75903
weeklylog     Node      node0         1501       log-rotation
449c070c-ff9a-11eb-8531-005056a75903
weeklylog     Node      node1         1498       log-rotation
8bb0adca-ff9a-11eb-8531-005056a75903
weeklylog     Node      node2         1499       log-rotation
b15fce61-ff9a-11eb-8531-005056a75903
weeklylog     Node      node3         1500       log-rotation
8bb14bd2-ff9a-11eb-8531-005056a75903
5 entries were displayed.
```

job schedule show

Display a list of available schedules

Availability: This command is available to *cluster* and *Vserver* administrators at the *admin* privilege level.

Description

The `job schedule show` command displays information about schedules.

Parameters

{ [-fields <fieldname>,...]

If you specify the `-fields <fieldname>`, ... parameter, the command output also includes the specified field or fields. You can use `'-fields ?'` to display the fields to specify.

| [-instance] }

If you specify the `-instance` parameter, the command displays detailed information about all fields.

[-cluster <Cluster name>] - Cluster

Selects the schedules that match this parameter value.

[-vserver <vserver name>] - Vserver

Selects the schedules that match this parameter value. These job schedules can only be used by consumers in that Vserver.

[-name <text>] - Schedule Name

Selects the schedules that match this parameter value.

[-type {cron|interval|builtin}] - Schedule Type

Selects the schedules that match this parameter value.

[-description <text>] - Description

Selects the schedules that match this parameter value.

Examples

The following example displays information about all schedules:

```
cluster1::> job schedule show
Cluster      Vserver      Name      Type      Description
-----  -----  -----  -----  -----
-----  -----
cluster1
      data_vs_1
          5min      cron
@:00,:05,:10,:15,:20,:25,:30,:35,:40,:45,:50,:55
          daily      cron      @0:10
          hourly     cron      @:05
          monthly    cron      1@0:20
          weekly     cron      Sun@0:15
```

job schedule cron create

Create a cron schedule

Availability: This command is available to *cluster* and *Vserver* administrators at the *admin* privilege level.

Description

The `job schedule cron create` command creates a cron schedule. A cron schedule, like a UNIX cron job, runs at a specified time. You can also specify months, days of the month, or days of the week on which the schedule will run.

If you specify values for both days of the month and days of the week, they are considered independently. For example, a cron schedule with the day specification Friday, 13 runs every Friday and on the 13th day of each month, not just on every Friday the 13th.

Parameters

[-cluster <Cluster name>] - Cluster

This parameter specifies the name of the cluster on which you want to create a cron schedule. By default, the schedule is created on the local cluster. In a MetroCluster configuration, the partner cluster can be specified if the local cluster is in switchover state.

[-vserver <vserver name>] - Vserver

This parameter specifies the name of the Vserver on which you want to create a cron schedule.

-name <text> - Name

Use this parameter to specify the name of the cron schedule that you want to create.

[-month <cron_month>, ...] - Month

Use this parameter to specify months in which the schedule runs. Valid values are January, February, March, April, May, June, July, August, September, October, November, December, and all. Specify "all" to run the schedule every month.

[-dayofweek <cron_dayofweek>, ...] - Day of Week

Use this parameter to specify days of the week on which the schedule runs. Valid values are Sunday, Monday, Tuesday, Thursday, Friday, and Saturday, and all. Specify "all" to run the schedule every day.

[-day <cron_dayofmonth>, ...] - Day

Use this parameter to specify days of the month on which the schedule runs. Valid values range from 1 to 31.

[-hour <cron_hour>, ...] - Hour

Use this parameter to specify the hours value of the time of day at which the schedule runs. Valid values range from 0 (midnight) to 23 (11:00 p.m.). Specify "all" to run the schedule every hour.

-minute <cron_minute>, ... - Minute

Use this parameter to specify the minutes portion of the time of day at which the schedule runs. Valid values range from 0 to 59.

Examples

The following example creates a cron schedule named weekendcron that runs on weekend days (Saturday and Sunday) at 3:00 a.m.

```
cluster1::> job schedule cron create -name weekendcron -dayofweek  
"Saturday, Sunday" -hour 3 -minute 0
```

job schedule cron delete

Delete a cron schedule

Availability: This command is available to *cluster* and *Vserver* administrators at the *admin* privilege level.

Description

The `job schedule cron delete` command deletes a cron schedule. Use the [job schedule cron show](#) command to display all current cron schedules.

You cannot delete any cron schedules that are associated with jobs. Use the [job schedule show-jobs](#) command to display jobs by schedule.

Parameters

[-cluster <Cluster name>] - Cluster

This parameter specifies the name of the cluster on which you want to delete a cron schedule. By default, the schedule is deleted from the local cluster. In a MetroCluster configuration, the partner cluster can be specified if the local cluster is in switchover state.

[-vserver <vserver name>] - Vserver

This parameter specifies the name of the Vserver on which you want to delete a cron schedule.

-name <text> - Name

Use this parameter with the name of an existing cron schedule to specify the cron schedule that you want to delete.

Examples

The following example deletes a cron schedule named `midnightcron`:

```
cluster1::> job schedule cron delete -name midnightcron
```

Related Links

- [job schedule cron show](#)
- [job schedule show-jobs](#)

job schedule cron modify

Modify a cron schedule

Availability: This command is available to *cluster* and *Vserver* administrators at the *admin* privilege level.

Description

The `job schedule cron modify` command modifies a cron schedule. A cron schedule, like a UNIX cron job, runs at a specified time. You can also specify months, days of the month, or days of the week on which the schedule runs. Use the [job schedule cron show](#) command to display all current cron schedules. See the documentation for [job schedule cron show](#) for more information about how cron schedules work.

Modifying one parameter of a cron schedule does not affect the other parameters. For example, if cron schedule is set to run at 3:15 AM, and you modify the "hour" parameter to 4, the schedule's new time will be 4:15am. To clear a parameter of the schedule's interval, you must explicitly set that portion to "0" or "-". Some parameters can also be set to "all".

Parameters

[-cluster <Cluster name>] - Cluster

Use this parameter to specify the cluster of an existing cron schedule you want to modify. The local cluster is provided as the default value. In a MetroCluster configuration, the partner cluster can be specified if the local cluster is in switchover state.

[-vserver <vserver name>] - Vserver

Use this parameter to specify the Vserver of an existing cron schedule you want to modify.

-name <text> - Name

Use this parameter with the name of an existing cron schedule to specify the cron schedule you want to modify.

[-month <cron_month>, ...] - Month

Use this parameter to specify a new "month" value for the cron schedule. Valid values are January, February, March, April, May, June, July, August, September, October, November, December, or all. Specify "all" to run the schedule every month.

[-dayofweek <cron_dayofweek>, ...] - Day of Week

Use this parameter to specify a new "day of week" value for the cron schedule. Valid values include Sunday, Monday, Tuesday, Thursday, Friday, Saturday, or all. Specify "all" to run the schedule every day.

[-day <cron_dayofmonth>, ...] - Day

Use this parameter to specify a new "day of month" value for the cron schedule. Valid values range from 1 to 31.

[-hour <cron_hour>, ...] - Hour

Use this parameter to specify a new "hour of the day" value for the cron schedule. Valid values range from 0 (midnight) to 23 (11:00 p.m.). Specify "all" to run the schedule every hour.

[-minute <cron_minute>, ...] - Minute

Use this parameter to specify a new "minute of the hour" value for the cron schedule. Valid values range from 0 to 59.

Examples

The following example modifies a cron schedule named weekendcron so that it runs at 3:15 a.m.:

```
cluster1::> job schedule cron modify -name weekendcron -hour 3 -minute 15
```

Related Links

- [job schedule cron show](#)

job schedule cron show

Show cron schedules

Availability: This command is available to *cluster* and *Vserver* administrators at the *admin* privilege level.

Description

The job schedule cron show command displays information about cron schedules. A cron schedule runs a job at a specified time on specified days.

Parameters

{ [-fields <fieldname>,...]

If you specify the -fields <fieldname>,... parameter, the command output also includes the specified field or fields. You can use '-fields ?' to display the fields to specify.

| [-instance] }

If you specify the -instance parameter, the command displays detailed information about all fields.

[-cluster <Cluster name>] - Cluster

Selects the cron schedules that match this parameter value.

[-vserver <vserver name>] - Vserver

Selects the cron schedules that match this parameter value. These job schedules can only be used by consumers in that Vserver.

[-name <text>] - Name

Selects the cron schedules that match this parameter value.

[-month <cron_month>,...] - Month

Selects the cron schedules that match this parameter value. Valid values are January , February , March , April , May , June , July , August , September , October , November , December , or all .

[-dayofweek <cron_dayofweek>,...] - Day of Week

Selects the cron schedules that match this parameter value. Valid values include Sunday , Monday , Tuesday , Wednesday , Thursday , Friday , Saturday , or all .

[-day <cron_dayofmonth>,...] - Day

Selects the cron schedules that match this parameter value. Valid values range from 1 to 31 .

[-hour <cron_hour>,...] - Hour

Selects the cron schedules that match this parameter value.

[-minute <cron_minute>,...] - Minute

Selects the cron schedules that match the minute or range of minutes that you specify.

[-description <text>] - Description

Selects the cron schedules that match this parameter value.

Examples

The following example displays information about all current cron schedules:

```
cluster1::> job schedule cron show
Cluster      Vserver      Name      Description
-----  -----  -----  -----
cluster1
      data_vs_1
      5min
@:00,:05,:10,:15,:20,:25,:30,:35,:40,:45,:50,:55
      8hour      @2:15,10:15,18:15
      weekly      Sun@0:15
```

The following example displays information about the cron schedule named weekly:

```
cluster1::> job schedule cron show -name weekly -instance
Cluster: cluster1
  Vserver: data_vs_1
    Name: weekly
    Month: -
  Day of Week: Sunday
    Day: -
    Hour: 0
    Minute: 15
  Description: Sun@0:15
```

job schedule interval create

Create a schedule that runs on an interval

Availability: This command is available to *cluster* and *Vserver* administrators at the *admin* privilege level.

Description

The `job schedule interval create` creates an interval schedule. An interval schedule runs jobs at specified intervals after the previous job finishes. For instance, if a job uses an interval schedule of 12 hours and takes 30 minutes to complete, the job runs at the following times:

- Day one at 8:00 a.m. (the job's initial run)
- Day one at 8:30 p.m.
- Day two at 9:00 a.m.
- Day two at 9:30 p.m.

Each of the numerical parameters of the interval must be a whole number. These parameters can be used individually, or combined to define complex time values. For example, use a value of 1 day, 12 hours to create an interval of 1.5 days.

Large parameter values are converted into larger units. For example, if you create a schedule with an interval

of 36 hours, the [job schedule interval show](#) command will display it with an interval of 1 day 12 hours.

Parameters

[-cluster <Cluster name>] - Cluster

This parameter specifies the name of the cluster on which you want to create an interval schedule. By default, the schedule is created on the local cluster. In a MetroCluster configuration, the partner cluster can be specified if the local cluster is in switchover state.

[-vserver <vserver name>] - Vserver

This parameter specifies the name of the Vserver on which you want to create an interval schedule.

-name <text> - Name

Use this parameter to specify the name of the interval schedule you want to create.

[-days <integer>] - Days

Use this parameter to specify the "days" portion of the schedule's interval. A day is one calendar day.

[-hours <integer>] - Hours

Use this parameter to specify the "hours" portion of the schedule's interval.

[-minutes <integer>] - Minutes

Use this parameter to specify the "minutes" portion of the schedule's interval.

[-seconds <integer>] - Seconds

Use this parameter to specify the "seconds" portion of the schedule's interval.

Examples

The following example creates an interval schedule named `rollingdaily` that runs six hours after the completion of the previous occurrence of the job:

```
cluster1::> job schedule interval create -name rollingdaily -hours 6
```

Related Links

- [job schedule interval show](#)

job schedule interval delete

Delete an interval schedule

Availability: This command is available to *cluster* and *Vserver* administrators at the *admin* privilege level.

Description

The `job schedule interval delete` command deletes an interval schedule. Use the [job schedule interval show](#) command to display all current interval schedules.

You cannot delete interval schedules that are currently being run. Use the [job schedule show-jobs](#) command to

display jobs by schedule.

Parameters

[-cluster <Cluster name>] - Cluster

This parameter specifies the name of the cluster on which you want to delete an interval schedule. By default, the schedule is deleted from the local cluster. In a MetroCluster configuration, the partner cluster can be specified if the local cluster is in switchover state.

[-vserver <vserver name>] - Vserver

This parameter specifies the name of the Vserver on which you want to delete an interval schedule.

-name <text> - Name

Use this parameter with the name of an existing interval schedule to specify the interval schedule you want to delete.

Examples

The following example deletes an interval schedule named rollingdaily:

```
cluster1::> job schedule interval delete -name rollingdaily
```

Related Links

- [job schedule interval show](#)
- [job schedule show-jobs](#)

job schedule interval modify

Modify an interval schedule

Availability: This command is available to *cluster* and *Vserver* administrators at the *admin* privilege level.

Description

The `job schedule interval modify` command modifies an interval schedule. An interval schedule runs jobs at a specified interval after the previous job finishes. Use the [job schedule interval show](#) command to display all current interval schedules. See the documentation of [job schedule interval show](#) for more information on how interval schedules work.

Modifying one parameter of a schedule's interval does not affect the other parameters. For example, if a schedule's interval is 1 day 12 hours, and you modify the "hours" parameter to 16, the schedule's new interval is 1 day 16 hours. To clear a parameter of the schedule's interval, you must explicitly set that parameter to "0" or "-".

Parameters

[-cluster <Cluster name>] - Cluster

Use this parameter to specify the cluster of an existing interval schedule you want to modify. The local cluster is provided as the default value. In a MetroCluster configuration, the partner cluster can be specified

if the local cluster is in switchover state.

[-vserver <vserver name>] - Vserver

Use this parameter to specify the Vserver of an existing interval schedule you want to modify.

-name <text> - Name

Use this parameter with the name of an existing interval schedule to specify the interval schedule you want to modify.

[-days <integer>] - Days

Use this parameter to specify a different "days" value for the schedule's interval.

[-hours <integer>] - Hours

Use this parameter to specify a different "hours" value for the schedule's interval.

[-minutes <integer>] - Minutes

Use this parameter to specify a different "minutes" value for the schedule's interval.

[-seconds <integer>] - Seconds

Use this parameter to specify a different "seconds" value for the schedule's interval.

Examples

The following example sets the schedule named rollingdaily to run every eight hours:

```
cluster1::> job schedule interval modify -name rollingdaily -hours 8
```

Related Links

- [job schedule interval show](#)

job schedule interval show

Show interval schedules

Availability: This command is available to *cluster* and *Vserver* administrators at the *admin* privilege level.

Description

The `job schedule interval show` command displays information about interval schedules.

Parameters

{ [-fields <fieldname>,...]

If you specify the `-fields <fieldname>,...` parameter, the command output also includes the specified field or fields. You can use `'-fields ?'` to display the fields to specify.

| [-instance] }

If you specify the `-instance` parameter, the command displays detailed information about all fields.

[-cluster <Cluster name>] - Cluster

Selects the interval schedules that match this parameter value.

[-vserver <vserver name>] - Vserver

Selects the interval schedules that match this parameter value. These job schedules can only be used by consumers in that Vserver.

[-name <text>] - Name

Selects the interval schedules that match this parameter value.

[-days <integer>] - Days

Selects the interval schedules that match the day value or range of values you specify.

[-hours <integer>] - Hours

Selects the interval schedules that match the hour value or range of values you specify.

[-minutes <integer>] - Minutes

Selects the interval schedules that match the minute value or range of values you specify.

[-seconds <integer>] - Seconds

Selects the interval schedules that match the second value or range of values you specify.

[-description <text>] - Description

Selects the interval schedules that match the description you specify.

Examples

The following example displays information about all interval schedules:

```
cluster1::> job schedule interval show
Cluster      Vserver      Name          Description
-----      -----
-----      -----
cluster1      data_vs_1
                           rollingdaily
                           Every 8h
```

Copyright information

Copyright © 2026 NetApp, Inc. All Rights Reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means—graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system—without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

LIMITED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (b)(3) of the Rights in Technical Data -Noncommercial Items at DFARS 252.227-7013 (FEB 2014) and FAR 52.227-19 (DEC 2007).

Data contained herein pertains to a commercial product and/or commercial service (as defined in FAR 2.101) and is proprietary to NetApp, Inc. All NetApp technical data and computer software provided under this Agreement is commercial in nature and developed solely at private expense. The U.S. Government has a non-exclusive, non-transferrable, nonsublicensable, worldwide, limited irrevocable license to use the Data only in connection with and in support of the U.S. Government contract under which the Data was delivered. Except as provided herein, the Data may not be used, disclosed, reproduced, modified, performed, or displayed without the prior written approval of NetApp, Inc. United States Government license rights for the Department of Defense are limited to those rights identified in DFARS clause 252.227-7015(b) (FEB 2014).

Trademark information

NETAPP, the NETAPP logo, and the marks listed at <http://www.netapp.com/TM> are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.