



## **volume snaplock commands**

### Command reference

NetApp

February 02, 2026

# Table of Contents

volume snaplock commands .....	1
volume snaplock modify .....	1
Description .....	1
Parameters .....	1
Examples .....	3
Related Links .....	3
volume snaplock prepare-to-downgrade .....	3
Description .....	3
Examples .....	4
volume snaplock show .....	4
Description .....	4
Parameters .....	4
Examples .....	6

# volume snaplock commands

## volume snaplock modify

Modify SnapLock attributes of a SnapLock volume

**Availability:** This command is available to *cluster* and *Vserver* administrators at the *admin* privilege level.

### Description

The `volume snaplock modify` command modifies one or more SnapLock attributes of a SnapLock volume.

### Parameters

#### **-vserver <vserver name>** - Vserver

This specifies the vserver which owns the required SnapLock volume.

#### **-volume <volume name>** - Volume

This specifies the SnapLock volume whose attribute needs to be modified.

#### **[-minimum-retention-period {{<integer> seconds|minutes|hours|days|months|years} | infinite}]** - Minimum Retention Period

Specifies the minimum allowed retention period for files committed to WORM state on the volume. Any files committed with a retention period shorter than this minimum value, is assigned this minimum value.

If this option value is *infinite*, then every file committed to the volume will have a retention period that never expires.

Otherwise, the retention period is specified as a number followed by a suffix. The valid suffixes are seconds, minutes, hours, days, months, and years. For example, a value of 6months represents a retention period of 6 months. The maximum allowed retention period is 70 years. This option is not applicable while extending retention period of an already committed WORM file.

#### **[-default-retention-period {{<integer> seconds|minutes|hours|days|months|years} | min | max | infinite | unspecified}]** - Default Retention Period

Specifies the default retention period that is applied to files while committing to WORM state without an associated retention period.

If this option value is *min*, then minimum-retention-period is used as the default retention period. If this option value is *max*, then maximum-retention-period is used as the default retention period. If this option value is *infinite*, then a retention period that never expires will be used as the default retention period. If this option value is *unspecified*, then the file will be retained forever; however, the retention time can be changed to an absolute value.

The retention period can also be explicitly specified as a number followed by a suffix. The valid suffixes are seconds, minutes, hours, days, months, and years. For example, a value of 6months represents a retention period of 6 months. The maximum valid retention period is 70 years.

**[-maximum-retention-period {{<integer> seconds|minutes|hours|days|months|years} | infinite}] - Maximum Retention Period**

Specifies the maximum allowed retention period for files committed to WORM state on the volume. Any files committed with a retention period longer than this maximum value, is assigned this maximum value.

If this option value is *infinite*, then files that have retention period that never expires might be committed to the volume.

Otherwise, the retention period is specified as a number followed by a suffix. The valid suffixes are seconds, minutes, hours, days, months, and years. For example, a value of 6months represents a retention period of 6 months. The maximum allowed retention period is 70 years. This option is not applicable while extending retention period of an already committed WORM file.

**[-autocommit-period {{<integer> minutes|hours|days|months|years} | none}] - Autocommit Period**

Specifies the autocommit period for SnapLock volume. All files which are not modified for a period greater than the autocommit period of the volume are committed to WORM state.

The autocommit period option is specified as a number followed by a suffix. The valid suffixes for autocommit period are hours, minutes, days, months and years. For example, a value of 2hours represents an autocommit period of 2 hours. The minimum allowed autocommit period is 5 minutes and the maximum allowed autocommit period is 10 years.

If this option value is *none*, then autocommit is disabled on the SnapLock volume.

**[-is-volume-append-mode-enabled {true|false}] - Is Volume Append Mode Enabled**

Specifies if the volume append mode is enabled or disabled.

It can be modified only when the volume is not mounted and does not have any data or snapshots.

The volume append mode is not supported on SnapLock audit log volumes.

When it is enabled, all the files created with write permissions on the volume are WORM appendable files by default. All the WORM appendable files that are not modified for a period greater than the autocommit period of the volume are also committed to the WORM read-only state.

If it is set to *true*, then the volume append mode is enabled.

If it is set to *false*, then the volume append mode is disabled.

Volume append mode is disabled by default when the volume is created.

**[-privileged-delete {disabled|enabled|permanently-disabled}] - Privileged Delete**

Specifies the privileged-delete attribute of a SnapLock volume. This parameter must be specified alone.

If it is set to *enabled* then the privileged-delete operation can be performed using the [volume file privileged-delete](#) command.

If it is set to *disabled*, then the privileged-delete operation is not supported.

Once it is set to *permanently-disabled*, then neither the privileged-delete operation nor any change in the volume privileged-delete attribute is permitted.

## Examples

The following command sets `-default-retention-period` of a given SnapLock volume:

```
cluster1::> volume snaplock modify -volume vol_slc -default-retention
-period 2years

cluster1::>
```

The following command sets `-maximum-retention-period` of a given SnapLock volume to *infinite*:

```
cluster1::> volume snaplock modify -volume vol_slc -maximum-retention
-period infinite

cluster1::>
```

The following command enables the privileged-delete operation on a SnapLock volume.

```
cluster1::> volume snaplock modify -vserver vs1 -volume vol_sle
-privileged-delete enabled
[Job 38] Job succeeded: Privileged-delete Attribute Change for Volume
"vs1:vol_sle" Completed.
cluster1::>
cluster1::>volume snaplock show -vserver vs1 -volume vol_sle -fields
privileged-delete
vserver volume privileged-delete
-----
vs1      vol_sle  enabled

cluster1::>
```

## Related Links

- [volume file privileged-delete](#)

## volume snaplock prepare-to-downgrade

Prepares the system for downgrade

**Availability:** This command is available to *cluster* administrators at the *advanced* privilege level.

## Description

The `volume snaplock prepare-to-downgrade` command prepares nodes to downgrade to a release without SnapLock volume append mode feature. Prior to disabling the feature, the command disables volume

append mode on all SnapLock volumes in the cluster.

## Examples

The following example disables the SnapLock volume append mode feature in the local cluster:

```
cluster1::> volume snaplock prepare-to-downgrade
```

## volume snaplock show

Display SnapLock attributes of a SnapLock volume

**Availability:** This command is available to *cluster* and *Vserver* administrators at the *admin* privilege level.

## Description

The `volume snaplock show` command displays following information :

- Vserver name
- Volume name
- SnapLock Type of the volume
- Minimum retention period applicable of the volume
- Default retention period applicable of the volume
- Maximum retention period applicable of the volume
- Autocommit period of the volume
- Volume Append Mode attribute of the volume
- Privileged Delete attribute of the volume
- Litigation count on the volume
- Volume expiry time of the volume
- Volume ComplianceClock
- SnapLock audit log volume
- Unspecified retention file count on the volume

This command is applicable only for SnapLock volumes.

## Parameters

{ [-fields <fieldname>, ...]

If you specify the `-fields <fieldname>, ...` parameter, the command output also includes the specified field or fields. You can use `'-fields ?'` to display the fields to specify.

**[ [-instance ] ]**

If you specify the `-instance` parameter, the command displays detailed information about all fields.

**[ -vserver <vserver name> ] - Vserver**

If this parameter is specified, the command displays information for all the SnapLock volumes that match the specified `-vserver` value.

**[ -volume <volume name> ] - Volume**

If this parameter is specified, the command displays information for the specified `-volume` value.

**[ -type {non-snaplock|compliance|enterprise} ] - SnapLock Type**

If this parameter is specified, the command displays all the volumes that match the specified `-type` value.

**[ -minimum-retention-period {{<integer> seconds|minutes|hours|days|months|years} | infinite} ] - Minimum Retention Period**

If this parameter is specified, the command displays all the volumes that match the specified `-minimum-retention-period` value.

**[ -default-retention-period {{<integer> seconds|minutes|hours|days|months|years} | min | max | infinite | unspecified} ] - Default Retention Period**

If this parameter is specified, the command displays all the volumes that match the specified `-default-retention-period` value.

**[ -maximum-retention-period {{<integer> seconds|minutes|hours|days|months|years} | infinite} ] - Maximum Retention Period**

If this parameter is specified, the command displays all the volumes that match the specified `-maximum-retention-period` value.

**[ -autocommit-period {{<integer> minutes|hours|days|months|years} | none} ] - Autocommit Period**

If this parameter is specified, the command displays all the volumes that match the specified `-autocommit-period` value.

**[ -is-volume-append-mode-enabled {true|false} ] - Is Volume Append Mode Enabled**

If this parameter is specified, the command displays all the volumes that match the specified `-is-volume-append-mode-enabled` value.

**[ -privileged-delete {disabled|enabled|permanently-disabled} ] - Privileged Delete**

If this parameter is specified, the command displays all the volumes that match the specified `-privileged-delete` value.

**[ -expiry-time <text> ] - Expiry Time**

If this parameter is specified, the command displays all the volumes that match the specified `-expiry-time` value.

**[ -compliance-clock-time <text> ] - ComplianceClock Time**

If this parameter is specified, the command displays all the volumes that match the specified `-compliance-clock-time` value.

**[-litigation-count <integer>] - Litigation Count**

If this parameter is specified, the command displays all the volumes that match the specified -litigation-count value.

**[-is-audit-log-volume {true|false}] - Is SnapLock Audit Log Volume**

If this parameter is specified, the command displays all the volumes that match the specified -is-audit-log-volume value.

**[-unspecified-retention-file-count <integer>] - Unspecified Retention File Count**

If this parameter is specified, the command displays all the volumes that match the specified -unspecified-retention-file-count value.

## Examples

The following command shows summary of SnapLock volumes on a vserver:

```
cluster1::> volume snaplock show
Vserver          Volume          SnapLock Type ComplianceClock Time
-----  -----  -----
-----  -----
vs1            vol_slc        compliance    Mon Jan 19 14:12:34 IST 2015
+05:30
vs1            vol_sle        enterprise   Mon Jan 19 14:12:34 IST 2015
+05:30
2 entries were displayed.

cluster1::>
```

The following commands lists the complete SnapLock attributes of two given SnapLock volumes:

```
cluster1::> volume snaplock show -vserver vs1 -volume vol_slc
Vserver Name: vs1
          Volume Name: vol_slc
          SnapLock Type: compliance
          Minimum Retention Period: 1 years
          Default Retention Period: max
          Maximum Retention Period: 30 years
          Autocommit Period: 12 hours
          Is Volume Append Mode Enabled: false
          Privileged Delete: permanently-disabled
          Expiry Time: Thu May 11 14:37:21 GMT 2017
          ComplianceClock Time: Wed May 11 20:08:41 IST 2016 +05:30
          Litigation Count: 0
          Is SnapLock Audit Log Volume: false
          Unspecified Retention File Count: 0
```

```
cluster1::>
```

```
cluster1::> volume snaplock show -vserver vs1 -volume vol_sle
Vserver Name: vs1
          Volume Name: vol_sle
          SnapLock Type: enterprise
          Minimum Retention Period: 6 months
          Default Retention Period: min
          Maximum Retention Period: infinite
          Autocommit Period: none
          Is Volume Append Mode Enabled: false
          Privileged Delete: enabled
          Expiry Time: infinite
          ComplianceClock Time: Wed May 11 20:08:44 IST 2016 +05:30
          Litigation Count: 0
          Is SnapLock Audit Log Volume: false
          Unspecified Retention File Count: 0
```

## Copyright information

Copyright © 2026 NetApp, Inc. All Rights Reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means—graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system—without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

**LIMITED RIGHTS LEGEND:** Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (b)(3) of the Rights in Technical Data -Noncommercial Items at DFARS 252.227-7013 (FEB 2014) and FAR 52.227-19 (DEC 2007).

Data contained herein pertains to a commercial product and/or commercial service (as defined in FAR 2.101) and is proprietary to NetApp, Inc. All NetApp technical data and computer software provided under this Agreement is commercial in nature and developed solely at private expense. The U.S. Government has a non-exclusive, non-transferrable, nonsublicensable, worldwide, limited irrevocable license to use the Data only in connection with and in support of the U.S. Government contract under which the Data was delivered. Except as provided herein, the Data may not be used, disclosed, reproduced, modified, performed, or displayed without the prior written approval of NetApp, Inc. United States Government license rights for the Department of Defense are limited to those rights identified in DFARS clause 252.227-7015(b) (FEB 2014).

## Trademark information

NETAPP, the NETAPP logo, and the marks listed at <http://www.netapp.com/TM> are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.