



Manage cluster license managers

ONTAP 9.8 REST API reference

NetApp
August 29, 2024

Table of Contents

- Manage cluster license managers 1
 - Cluster licensing license-managers endpoint overview 1
 - Retrieve license managers 2
 - Retrieve license manager information 7
 - Update the license manager configuration 10

Manage cluster license managers

Cluster licensing license-managers endpoint overview

Overview

This API is used to manage information about the license manager instance associated with the cluster.

When an ONTAP cluster is initially created to use the capacity pools licensing model, information about the license manager instance that the cluster should use is pre-configured. Generally, this configuration does not need to be updated unless the license manager instance changes its IP address.

The license manager is currently bundled with the ONTAP Select Deploy utility and runs on the same VM as ONTAP Select Deploy. Use this API to update the license manager IP address when the Deploy VM changes its IP address.

Examples

Retrieving information about the license manager instance associated with the cluster

```
# API
curl -X GET "https://<mgmt-ip>/api/cluster/licensing/license-managers"

# Response
200 OK

# JSON Body
{
  "records": [
    {
      "uuid": "4ea7a442-86d1-11e0-ae1c-112233445566",
      "uri": {
        "host": "10.1.1.1",
      },
      "default": true
    }
  ],
  "num_records": 1,
  "_links": {
    "self": {
      "href": "/cluster/licensing/license-managers"
    }
  }
}
```

Updating an existing license manager instance

```
# API
curl -X PATCH "https://<mgmt-ip>/api/cluster/licensing/license-
managers/4ea7a442-86d1-11e0-ae1c-112233445566"

# JSON Body
{
  "uri": {
    "host": "10.1.1.3"
  }
}

# Response
202 Accepted
```

Retrieve license managers

GET /cluster/licensing/license-managers

Introduced In: 9.8

Retrieves a collection of license managers.

Learn more

- [DOC /cluster/licensing/license-managers](#)

Related ONTAP commands

- `system license license-manager show`

Parameters

| Name | Type | In | Required | Description |
|-------------|---------------|-------|----------|---------------------------------------|
| default | boolean | query | False | Filter by default |
| uri.host | string | query | False | Filter by uri.host |
| uuid | string | query | False | Filter by uuid |
| fields | array[string] | query | False | Specify the fields to return. |
| max_records | integer | query | False | Limit the number of records returned. |

| Name | Type | In | Required | Description |
|----------------|---------------|-------|----------|---|
| return_records | boolean | query | False | The default is true for GET calls. When set to false, only the number of records is returned. <ul style="list-style-type: none"> • Default value: 1 |
| return_timeout | integer | query | False | The number of seconds to allow the call to execute before returning. When iterating over a collection, the default is 15 seconds. ONTAP returns earlier if either max records or the end of the collection is reached. <ul style="list-style-type: none"> • Default value: 1 • Max value: 120 • Min value: 0 |
| order_by | array[string] | query | False | Order results by specified fields and optional [asc |

Response

Status: 200, Ok

| Name | Type | Description |
|-------------|----------------------------------|-------------------|
| _links | collection_links | |
| num_records | integer | Number of records |
| records | array[records] | |

Example response

```
{
  "_links": {
    "next": {
      "href": "/api/resourcelink"
    },
    "self": {
      "href": "/api/resourcelink"
    }
  },
  "records": [
    {
      "_links": {
        "self": {
          "href": "/api/resourcelink"
        }
      },
      "uri": {
        "host": "10.1.1.1"
      },
      "uuid": "4ea7a442-86d1-11e0-ae1c-112233445566"
    }
  ]
}
```

Error

Status: Default, Error

| Name | Type | Description |
|-------|-------|-------------|
| error | error | |

Example error

```
{
  "error": {
    "arguments": [
      {
        "code": "string",
        "message": "string"
      }
    ],
    "code": "4",
    "message": "entry doesn't exist",
    "target": "uuid"
  }
}
```

Definitions

See Definitions

href

| Name | Type | Description |
|------|--------|-------------|
| href | string | |

collection_links

| Name | Type | Description |
|------|----------------------|-------------|
| next | href | |
| self | href | |

self_link

| Name | Type | Description |
|------|----------------------|-------------|
| self | href | |

uri

License manager URI.

| Name | Type | Description |
|------|--------|--|
| host | string | License manager host name, IPv4 or IPv6 address. |

records

Information on a license manager instance associated with the cluster.

| Name | Type | Description |
|---------|---------------------------|--|
| _links | self_link | |
| default | boolean | Flag that indicates whether it's the default license manager instance used by the cluster.' When a capacity pool is created and if the license manager field is omitted, it is assumed that the license of the capacity pool is installed on the default license manager instance. |
| uri | uri | License manager URI. |
| uuid | string | |

error_arguments

| Name | Type | Description |
|---------|--------|------------------|
| code | string | Argument code |
| message | string | Message argument |

error

| Name | Type | Description |
|-----------|--|---|
| arguments | array[error_arguments] | Message arguments |
| code | string | Error code |
| message | string | Error message |
| target | string | The target parameter that caused the error. |

Retrieve license manager information

GET /cluster/licensing/license-managers/{uuid}

Introduced In: 9.8

Retrieves information about the license manager.

Learn more

- [DOC /cluster/licensing/license-managers](#)

Related ONTAP commands

- `system license license-manager show`

Parameters

| Name | Type | In | Required | Description |
|----------|---------|-------|----------|--------------------|
| uuid | string | path | True | |
| default | boolean | query | False | Filter by default |
| uri.host | string | query | False | Filter by uri.host |

| Name | Type | In | Required | Description |
|--------|---------------|-------|----------|-------------------------------|
| uuid | string | query | False | Filter by uuid |
| fields | array[string] | query | False | Specify the fields to return. |

Response

Status: 200, Ok

| Name | Type | Description |
|---------|---------------------------|--|
| _links | self_link | |
| default | boolean | Flag that indicates whether it's the default license manager instance used by the cluster.' When a capacity pool is created and if the license manager field is omitted, it is assumed that the license of the capacity pool is installed on the default license manager instance. |
| uri | uri | License manager URI. |
| uuid | string | |

Example response

```
{
  "_links": {
    "self": {
      "href": "/api/resourcelink"
    }
  },
  "uri": {
    "host": "10.1.1.1"
  },
  "uuid": "4ea7a442-86d1-11e0-ae1c-112233445566"
}
```

Error

Status: Default, Error

| Name | Type | Description |
|-------|-------|-------------|
| error | error | |

Example error

```
{
  "error": {
    "arguments": [
      {
        "code": "string",
        "message": "string"
      }
    ],
    "code": "4",
    "message": "entry doesn't exist",
    "target": "uuid"
  }
}
```

Definitions

See Definitions

href

| Name | Type | Description |
|------|--------|-------------|
| href | string | |

self_link

| Name | Type | Description |
|------|----------------------|-------------|
| self | href | |

uri

License manager URI.

| Name | Type | Description |
|------|--------|--|
| host | string | License manager host name, IPv4 or IPv6 address. |

error_arguments

| Name | Type | Description |
|---------|--------|------------------|
| code | string | Argument code |
| message | string | Message argument |

error

| Name | Type | Description |
|-----------|--|---|
| arguments | array[error_arguments] | Message arguments |
| code | string | Error code |
| message | string | Error message |
| target | string | The target parameter that caused the error. |

Update the license manager configuration

PATCH /cluster/licensing/license-managers/{uuid}

Introduced In: 9.8

Updates the license manager configuration.

Learn more

- [DOC /cluster/licensing/license-managers](#)

Related ONTAP commands

- `system license license-manager modify`

Parameters

| Name | Type | In | Required | Description |
|----------------|---------|-------|----------|--|
| uuid | string | path | True | |
| return_timeout | integer | query | False | <p>The number of seconds to allow the call to execute before returning. When doing a POST, PATCH, or DELETE operation on a single record, the default is 0 seconds. This means that if an asynchronous operation is started, the server immediately returns HTTP code 202 (Accepted) along with a link to the job. If a non-zero value is specified for POST, PATCH, or DELETE operations, ONTAP waits that length of time to see if the job completes so it can return something other than 202.</p> <ul style="list-style-type: none">• Default value: 1• Max value: 120• Min value: 0 |

Request Body

| Name | Type | Description |
|---------|-----------|--|
| _links | self_link | |
| default | boolean | Flag that indicates whether it's the default license manager instance used by the cluster.' When a capacity pool is created and if the license manager field is omitted, it is assumed that the license of the capacity pool is installed on the default license manager instance. |
| uri | uri | License manager URI. |
| uuid | string | |

Example request

```
{
  "_links": {
    "self": {
      "href": "/api/resourcelink"
    }
  },
  "uri": {
    "host": "10.1.1.1"
  },
  "uuid": "4ea7a442-86d1-11e0-ae1c-112233445566"
}
```

Response

Status: 202, Accepted

| Name | Type | Description |
|------|----------|-------------|
| job | job_link | |

Example response

```
{
  "job": {
    "_links": {
      "self": {
        "href": "/api/resourcelink"
      }
    },
    "uuid": "string"
  }
}
```

Error

Status: Default

ONTAP Error Response Codes

| Error Code | Description |
|------------|---|
| 1115532 | The requested update to the license manager information failed. |

| Name | Type | Description |
|--------|--------------|-------------|
| errors | array[error] | |

Example error

```
{
  "errors": [
    {
      "arguments": [
        {
          "code": "string",
          "message": "string"
        }
      ],
      "code": "4",
      "message": "entry doesn't exist",
      "target": "uuid"
    }
  ]
}
```

Definitions

See Definitions

href

| Name | Type | Description |
|------|--------|-------------|
| href | string | |

self_link

| Name | Type | Description |
|------|----------------------|-------------|
| self | href | |

uri

License manager URI.

| Name | Type | Description |
|------|--------|--|
| host | string | License manager host name, IPv4 or IPv6 address. |

license_manager

Information on a license manager instance associated with the cluster.

| Name | Type | Description |
|---------|---------------------------|---|
| _links | self_link | |
| default | boolean | Flag that indicates whether it's the default license manager instance used by the cluster.' When a capacity pool is created and if the license manager field is omitted, it is assumed that the license of the capacity pool is installed on the default license manager instance. |
| uri | uri | License manager URI. |
| uuid | string | |

_links

| Name | Type | Description |
|------|----------------------|-------------|
| self | href | |

job_link

| Name | Type | Description |
|------------------------|------------------------|---|
| _links | _links | |
| uuid | string | The UUID of the asynchronous job that is triggered by a POST, PATCH, or DELETE operation. |

error_arguments

| Name | Type | Description |
|---------|--------|------------------|
| code | string | Argument code |
| message | string | Message argument |

error

| Name | Type | Description |
|-----------|--|---|
| arguments | array[error_arguments] | Message arguments |
| code | string | Error code |
| message | string | Error message |
| target | string | The target parameter that caused the error. |

Copyright information

Copyright © 2024 NetApp, Inc. All Rights Reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means—graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system—without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP "AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

LIMITED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (b)(3) of the Rights in Technical Data -Noncommercial Items at DFARS 252.227-7013 (FEB 2014) and FAR 52.227-19 (DEC 2007).

Data contained herein pertains to a commercial product and/or commercial service (as defined in FAR 2.101) and is proprietary to NetApp, Inc. All NetApp technical data and computer software provided under this Agreement is commercial in nature and developed solely at private expense. The U.S. Government has a non-exclusive, non-transferrable, nonsublicensable, worldwide, limited irrevocable license to use the Data only in connection with and in support of the U.S. Government contract under which the Data was delivered. Except as provided herein, the Data may not be used, disclosed, reproduced, modified, performed, or displayed without the prior written approval of NetApp, Inc. United States Government license rights for the Department of Defense are limited to those rights identified in DFARS clause 252.227-7015(b) (FEB 2014).

Trademark information

NETAPP, the NETAPP logo, and the marks listed at <http://www.netapp.com/TM> are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.